



# Avid® Interplay® Engine and Avid Interplay Archive Engine Administration Guide

Version 2.4

## Legal Notices

Product specifications are subject to change without notice and do not represent a commitment on the part of Avid Technology, Inc.

This product is subject to the terms and conditions of a software license agreement provided with the software. The product may only be used in accordance with the license agreement.

Avid products or portions thereof are protected by one or more of the following United States Patents: 5,309,528; 5,355,450; 5,396,594; 5,440,348; 5,467,288; 5,513,375; 5,528,310; 5,557,423; 5,577,190; 5,584,006; 5,640,601; 5,644,364; 5,654,737; 5,724,605; 5,726,717; 5,745,637; 5,752,029; 5,754,851; 5,799,150; 5,812,216; 5,828,678; 5,842,014; 5,852,435; 5,959,610; 5,986,584; 5,999,406; 6,038,573; 6,057,829; 6,069,668; 6,141,007; 6,211,869; 6,336,093; 6,532,043; 6,546,190; 6,596,031; 6,728,682; 6,747,705; 6,763,523; 6,766,357; 6,847,373; 7,081,900; 7,403,561; 7,433,519; 7,441,193; 7,671,871; 7,684,096; D352,278; D372,478; D373,778; D392,267; D392,268; D392,269; D395,291; D396,853; D398,912. Other patents are pending.

Avid products or portions thereof are protected by one or more of the following European Patents: 0506870; 0635188; 0674414; 0752174; 0811290; 0811292; 0811293; 1050048; 1111910; 1629675. Other patents are pending.

This document is protected under copyright law. An authorized licensee of Avid Interplay may reproduce this publication for the licensee's own use in learning how to use the software. This document may not be reproduced or distributed, in whole or in part, for commercial purposes, such as selling copies of this document or providing support or educational services to others. This document is supplied as a guide for Avid Interplay. Reasonable care has been taken in preparing the information it contains. However, this document may contain omissions, technical inaccuracies, or typographical errors. Avid Technology, Inc. does not accept responsibility of any kind for customers' losses due to the use of this document. Product specifications are subject to change without notice.

Copyright © 2011 Avid Technology, Inc. and its licensors. All rights reserved. Printed in USA.

The following disclaimer is required by Apple Computer, Inc.:

APPLE COMPUTER, INC. MAKES NO WARRANTIES WHATSOEVER, EITHER EXPRESS OR IMPLIED, REGARDING THIS PRODUCT, INCLUDING WARRANTIES WITH RESPECT TO ITS MERCHANTABILITY OR ITS FITNESS FOR ANY PARTICULAR PURPOSE. THE EXCLUSION OF IMPLIED WARRANTIES IS NOT PERMITTED BY SOME STATES. THE ABOVE EXCLUSION MAY NOT APPLY TO YOU. THIS WARRANTY PROVIDES YOU WITH SPECIFIC LEGAL RIGHTS. THERE MAY BE OTHER RIGHTS THAT YOU MAY HAVE WHICH VARY FROM STATE TO STATE.

The following disclaimer is required by Sam Leffler and Silicon Graphics, Inc. for the use of their TIFF library:

Copyright © 1988–1997 Sam Leffler  
Copyright © 1991–1997 Silicon Graphics, Inc.

Permission to use, copy, modify, distribute, and sell this software [i.e., the TIFF library] and its documentation for any purpose is hereby granted without fee, provided that (i) the above copyright notices and this permission notice appear in all copies of the software and related documentation, and (ii) the names of Sam Leffler and Silicon Graphics may not be used in any advertising or publicity relating to the software without the specific, prior written permission of Sam Leffler and Silicon Graphics.

THE SOFTWARE IS PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EXPRESS, IMPLIED OR OTHERWISE, INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

IN NO EVENT SHALL SAM LEFFLER OR SILICON GRAPHICS BE LIABLE FOR ANY SPECIAL, INCIDENTAL, INDIRECT OR CONSEQUENTIAL DAMAGES OF ANY KIND, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER OR NOT ADVISED OF THE POSSIBILITY OF DAMAGE, AND ON ANY THEORY OF LIABILITY, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

The following disclaimer is required by the Independent JPEG Group:

This software is based in part on the work of the Independent JPEG Group.

This Software may contain components licensed under the following conditions:

Copyright (c) 1989 The Regents of the University of California. All rights reserved.

Redistribution and use in source and binary forms are permitted provided that the above copyright notice and this paragraph are duplicated in all such forms and that any documentation, advertising materials, and other materials related to such distribution and use acknowledge that the software was developed by the University of California, Berkeley. The name of the University may not be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Copyright (C) 1989, 1991 by Jef Poskanzer.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. This software is provided "as is" without express or implied warranty.

Copyright 1995, Trinity College Computing Center. Written by David Chappell.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. This software is provided "as is" without express or implied warranty.

Copyright 1996 Daniel Dardailler.

Permission to use, copy, modify, distribute, and sell this software for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Daniel Dardailler not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. Daniel Dardailler makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

Modifications Copyright 1999 Matt Koss, under the same license as above.

Copyright (c) 1991 by AT&T.

Permission to use, copy, modify, and distribute this software for any purpose without fee is hereby granted, provided that this entire notice is included in all copies of any software which is or includes a copy or modification of this software and in all copies of the supporting documentation for such software.

THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR AT&T MAKES ANY REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.

This product includes software developed by the University of California, Berkeley and its contributors.

The following disclaimer is required by Nexidia Inc.:

© 2010 Nexidia Inc. All rights reserved, worldwide. Nexidia and the Nexidia logo are trademarks of Nexidia Inc. All other trademarks are the property of their respective owners. All Nexidia materials regardless of form, including without limitation, software applications, documentation and any other information relating to Nexidia Inc., and its products and services are the exclusive property of Nexidia Inc. or its licensors. The Nexidia products and services described in these materials may be covered by Nexidia's United States patents: 7,231,351; 7,263,484; 7,313,521; 7,324,939; 7,406,415, 7,475,065; 7,487,086 and/or other patents pending and may be manufactured under license from the Georgia Tech Research Corporation USA.

The following disclaimer is required by Paradigm Matrix:

Portions of this software licensed from Paradigm Matrix.

The following disclaimer is required by Ray Sauers Associates, Inc.:

"Install-It" is licensed from Ray Sauers Associates, Inc. End-User is prohibited from taking any action to derive a source code equivalent of "Install-It," including by reverse assembly or reverse compilation, Ray Sauers Associates, Inc. shall in no event be liable for any damages resulting from reseller's failure to perform reseller's obligation; or any damages arising from use or operation of reseller's products or the software; or any other damages, including but not limited to, incidental, direct, indirect, special or consequential Damages including lost profits, or damages resulting from loss of use or inability to use reseller's products or the software for any reason including copyright or patent infringement, or lost data, even if Ray Sauers Associates has been advised, knew or should have known of the possibility of such damages.

The following disclaimer is required by Videomedia, Inc.:

"Videomedia, Inc. makes no warranties whatsoever, either express or implied, regarding this product, including warranties with respect to its merchantability or its fitness for any particular purpose."

"This software contains V-LAN ver. 3.0 Command Protocols which communicate with V-LAN ver. 3.0 products developed by Videomedia, Inc. and V-LAN ver. 3.0 compatible products developed by third parties under license from Videomedia, Inc. Use of this software will allow "frame accurate" editing control of applicable videotape recorder decks, videodisc recorders/players and the like."

The following disclaimer is required by Altura Software, Inc. for the use of its Mac2Win software and Sample Source Code:

©1993–1998 Altura Software, Inc.

The following disclaimer is required by Ultimatte Corporation:

Certain real-time compositing capabilities are provided under a license of such technology from Ultimatte Corporation and are subject to copyright protection.

The following disclaimer is required by 3Prong.com Inc.:

Certain waveform and vector monitoring capabilities are provided under a license from 3Prong.com Inc.

The following disclaimer is required by Interplay Entertainment Corp.:

The "Interplay" name is used with the permission of Interplay Entertainment Corp., which bears no responsibility for Avid products.

This product includes portions of the Alloy Look & Feel software from Incors GmbH.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

© DevelopMentor

This product may include the JCifs library, for which the following notice applies:

JCifs © Copyright 2004, The JCIFS Project, is licensed under LGPL (<http://jcifs.samba.org/>). See the LGPL.txt file in the Third Party Software directory on the installation CD.

Avid Interplay contains components licensed from LavanTech. These components may only be used as part of and in connection with Avid Interplay.

#### Attn. Government User(s). Restricted Rights Legend

U.S. GOVERNMENT RESTRICTED RIGHTS. This Software and its documentation are "commercial computer software" or "commercial computer software documentation." In the event that such Software or documentation is acquired by or on behalf of a unit or agency of the U.S. Government, all rights with respect to this Software and documentation are subject to the terms of the License Agreement, pursuant to FAR §12.212(a) and/or DFARS §227.7202-1(a), as applicable.

#### Trademarks

003, 192 Digital I/O, 192 I/O, 96 I/O, 96i I/O, Adrenaline, AirSpeed, ALEX, Alienbrain, AME, AniMatte, Archive, Archive II, Assistant Station, AudioPages, AudioStation, AutoLoop, AutoSync, Avid Active, Avid Advanced Response, Avid DNA, Avid DNxcel, Avid DNxHD, Avid DS Assist Station, Avid Liquid, Avid Media Engine, Avid Media Processor, Avid MEDIAArray, Avid Mojo, Avid Remote Response, Avid Unity, Avid Unity ISIS, Avid VideoRAID, AvidRAID, AvidShare, AVIDstripe, AVX, Axiom, Beat Detective, Beauty Without The Bandwidth, Beyond Reality, BF Essentials, Bomb Factory, Boom, Bruno, C|24, CaptureManager, ChromaCurve, ChromaWheel, Cineractive Engine, Cineractive Player, Cineractive Viewer, Color Conductor, Command|24, Command|8, Conectiv, Control|24, Cosmonaut Voice, CountDown, d2, d3, DAE, Dazzle, Dazle Digital Video Creator, D-Command, D-Control, Deko, DekoCast, D-Fi, D-Fx, Digi 003, DigiBase, DigiDelivery, Digidesign, Digidesign Audio Engine, Digidesign Development Partners, Digidesign Intelligent Noise Reduction, Digidesign TDM Bus, DigiLink, DigiMeter, DigiPanner, DigiProNet, DigiRack, DigiSnake, DigiSystem, Digital Choreography, Digital Nonlinear Accelerator, DigiTest, DigiTranslator, DigiWear, DINR, DNxCON, DPP-1, D-Show, DSP Manager, DS-StorageCalc, DV Toolkit, DVD Complete, D-Verb, Eleven, EM, Euphonix, EUCON, EveryPhase, Expander, ExpertRender, Fader Pack, Fairchild, FastBreak, Fast Track, Film Cutter, FilmScribe, Flexevent, FluidMotion, Frame Chase, FXDeko, HD Core, HD Process, HDPack, Home-to-Hollywood, HYBRID, HyperControl, HyperSPACE, HyperSPACE HDCAM, iKnowledge, Image Independence, Impact, Improv, iNEWS, iNEWS Assign, iNEWS ControlAir, Instantwrite, Instinct, Intelligent Content Management, Intelligent Digital Actor Technology, IntelliRender, Intelli-Sat, Intelli-sat Broadcasting Recording Manager, InterFX, Interplay, inTONE, Intraframe, iS Expander, ISIS, IsoSync, iS9, iS18, iS23, iS36, ISIS, IsoSync, KeyRig, KeyStudio, LaunchPad, LeaderPlus, LFX, Lightning, Link & Sync, ListSync, LKT-200, Lo-Fi, Luna, MachineControl, Magic Mask, Make Anything Hollywood, make manage move | media, Marquee, MassivePack, Massive Pack Pro, M-Audio, M-Audio Micro, Maxim, Mbox, Media Composer, MediaFlow, MediaLog, MediaMatch, MediaMix, Media Reader, Media Recorder, MEDIAArray, MediaServer, MediaShare, MetaFuze, MetaSync, MicroTrack, MIDI I/O, Midiman, Mix Rack, MixLab, Moviebox, Moviestar, MultiShell, NaturalMatch, NewsCutter, NewsView, Nitris, NL3D, NLP, Nova, NRV-10 interFX, NSDOS, NSWIN, Octane, OMF, OMF Interchange, OMM, OnDVD, Open Media Framework, Open Media Management, Ozone, Ozonic, Painterly Effects, Palladium, Personal Q, PET, Pinnacle, Pinnacle DistanTV, Pinnacle GenieBox, Pinnacle HomeMusic, Pinnacle MediaSuite, Pinnacle Mobile Media, Pinnacle Scorefitter, Pinnacle Studio,

Pinnacle Studio MovieBoard, Pinnacle Systems, Pinnacle VideoSpin, Podcast Factory, PowerSwap, PRE, ProControl, ProEncode, Profiler, Pro Tools LE, Pro Tools M-Powered, Pro Transfer, Pro Tools, QuickPunch, QuietDrive, Realtime Motion Synthesis, Recti-Fi, Reel Tape Delay, Reel Tape Flanger, Reel Tape Saturation, Reprise, Res Rocket Surfer, Reso, RetroLoop, Reverb One, ReVibe, Revolution, rS9, rS18, RTAS, Salesview, Sci-Fi, Scorch, Scorefitter, ScriptSync, SecureProductionEnvironment, Serv|LT, Serv|GT, Session, Shape-to-Shape, ShuttleCase, Sibelius, SIDON, SimulPlay, SimulRecord, Slightly Rude Compressor, Smack!, Soft SampleCell, Soft-Clip Limiter, Solaris, SoundReplacer, SPACE, SPACESHift, SpectraGraph, SpectraMatte, SteadyGlide, Streamfactory, Streamgenie, StreamRAID, Strike, Structure, Studiophile, SubCap, Sundance Digital, Sundance, SurroundScope, Symphony, SYNC HD, Synchronic, SynchroScope, SYNC I/O, Syntax, TDM FlexCable, TechFlix, Tel-Ray, Thunder, Titansync, Titan, TL Aggro, TL AutoPan, TL Drum Rehab, TL Everyphase, TL Fauxlder, TL In Tune, TL MasterMeter, TL Metro, TL Space, TL Utilities, tools for storytellers, Torq, Torq Xponent, Transfuser, Transit, TransJammer, Trigger Finger, Trillium Lane Labs, TruTouch, UnityRAID, Vari-Fi, Velvet, Video the Web Way, VideoRAID, VideoSPACE, VideoSpin, VTEM, Work-N-Play, Xdeck, X-Form, Xmon, XPAND!, Xponent, X-Session, and X-Session Pro are either registered trademarks or trademarks of Avid Technology, Inc. in the United States and/or other countries.

Adobe and Photoshop are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries. Apple and Macintosh are trademarks of Apple Computer, Inc., registered in the U.S. and other countries. Windows is either a registered trademark or trademark of Microsoft Corporation in the United States and/or other countries. All other trademarks contained herein are the property of their respective owners.

### Footage

Eco Challenge Morocco — Courtesy of Discovery Communications, Inc.  
News material provided by WFTV Television Inc.  
Ice Island — Courtesy of Kurtis Productions, Ltd.

Avid Interplay Engine and Avid Interplay Archive Engine Administration Guide • 0130-07640-03 Rev E • June 2011. This document is distributed by Avid in online (electronic) form only, and is not available for purchase in printed form.



# Contents

	<b>Using This Guide</b> .....	13
	Symbols and Conventions .....	14
	If You Need Help .....	15
	Viewing Help and Documentation on the Interplay Portal .....	15
	Interplay Documentation .....	16
	Avid Training Services .....	17
<b>Chapter 1</b>	<b>Getting Started with the Avid Interplay Administrator</b> .....	19
	Understanding the Interplay Engine and Interplay Workgroups .....	19
	Using the Avid Interplay Administrator .....	23
	Starting the Avid Interplay Administrator .....	24
	Using the Avid Interplay Administrator Window .....	26
	Opening an Interplay Administrator View .....	28
	Opening Interplay Help .....	28
	Exiting the Avid Interplay Administrator .....	29
<b>Chapter 2</b>	<b>Database Settings</b> .....	31
	Creating an Interplay Database .....	31
	Avid Interplay Databases, Folders, and Files .....	33
	Limits on the Number of Assets and Objects in the Interplay Database .....	36
	Creating and Restoring Database Backups .....	36
	Types of Interplay Administrator Backups .....	37
	Recommendations for Backup Configuration .....	38
	Scheduling Automatic Database Backups .....	41
	Starting a Backup Manually .....	45
	Using an Archiving Tool for Backup .....	46
	Restoring an Earlier Version of a Database .....	48
	Restoring a Complete Backup or a Fast Backup .....	50
	Using the InterplayRestore Tool on the Interplay Engine Server .....	53
	Database Restore Session Example .....	56

	Using the BackupArchive Tool to Restore Files . . . . .	57
	Restoring Archived Log Files . . . . .	60
	Performing a Consistency Check . . . . .	60
	Viewing Database Information . . . . .	60
	Locking and Unlocking Databases . . . . .	62
	Managing Databases: Deactivating, Activating, and Migrating . . . . .	63
	Deactivating a Database . . . . .	63
	Activating a Deactivated Database . . . . .	64
	Migrating a Database . . . . .	67
	Moving a Database to Another Server (Non-Clustered Systems) . . . . .	69
	Moving a Database and Users to Another Server (Non-Clustered Systems) . . . . .	71
	Moving a Database to Another Server (Clustered Systems) . . . . .	73
	Moving a Database and Users to Another Server (Clustered Systems) . . . . .	76
	Moving a Database Under Low Disk Space Conditions . . . . .	78
	Renaming a Database . . . . .	79
<b>Chapter 3</b>	<b>Server Settings . . . . .</b>	<b>81</b>
	Changing the Database and Data Locations . . . . .	81
	Viewing Server Information . . . . .	82
	Locking and Unlocking the Server . . . . .	84
	Restarting the Server . . . . .	85
	Managing Licenses . . . . .	86
	Installing a Permanent License . . . . .	88
	License Types and Usage . . . . .	89
	Exporting a License . . . . .	90
	Troubleshooting Licensing Problems . . . . .	90
	Using the License Key Info Tool . . . . .	91
<b>Chapter 4</b>	<b>User Management . . . . .</b>	<b>93</b>
	Understanding the Central Configuration Server . . . . .	93
	Moving the CCS to Another Server . . . . .	94
	Viewing and Changing the CCS for a Server . . . . .	95
	Adding Users to a Central Configuration Server . . . . .	98



Setting User Authentication Providers and Importing Users . . . . .	98
Setting Avid Unity Authentication . . . . .	100
Setting Windows Domain Authentication and Importing Users . . . . .	101
Setting LDAP Authentication and Importing Users . . . . .	103
LDAP Server Configuration Settings . . . . .	105
Managing Users, User Groups, and User Rights . . . . .	108
Understanding Default User Groups, Users, and Roles . . . . .	110
Adding User Groups . . . . .	111
Adding Users Manually . . . . .	111
Viewing and Setting Attributes . . . . .	112
Understanding Standard Roles and Default Rights . . . . .	113
Viewing and Changing Roles . . . . .	114
Viewing and Setting Authentication Providers for Individual Users . . . . .	116
Deleting Users and User Groups . . . . .	117
Removing Users from User Groups . . . . .	117
Managing Database Roles . . . . .	118
Viewing General Role Assignments . . . . .	118
Setting or Changing a General Role Assignment . . . . .	121
Blocking Access by a Group or User . . . . .	124
Managing Special Access Folders . . . . .	124
Guidelines for User Management . . . . .	127
<b>Chapter 5 Site Settings . . . . .</b>	<b>129</b>
Defining Property Layouts . . . . .	129
Setting the Resolutions Available for Display . . . . .	132
Creating Custom Properties . . . . .	134
Adding a Custom Property . . . . .	135
Setting Access Control for Custom Properties . . . . .	138
Working with Lists for Custom Properties . . . . .	140
Creating and Editing a File for Custom Properties . . . . .	140
Removing a List for a Custom Property . . . . .	142
Using Custom Properties in an Extended Search . . . . .	143
Configuring Remote Workgroups . . . . .	144
Configuring Categories . . . . .	146

Adding Categories . . . . .	146
Removing Categories . . . . .	148
Setting Server Hostnames and the Workgroup Name . . . . .	149
Configuring the Interplay Streaming Server . . . . .	151
Interplay Media Services View . . . . .	153
Interplay Transfer Status View . . . . .	154
Interplay Transfer Settings View . . . . .	154
Workgroup Transfer Presets View . . . . .	154
Specifying Remote Servers for Asset Tracking . . . . .	155
Specifying Archive Settings . . . . .	156
Archiving Duplicate Versions of Media . . . . .	156
Adding AAF Metadata to an Archive . . . . .	158
Specifying the Archive Server, Segment Size, and Restore Process . . . . .	158
Setting the Ownership for New Database Folders . . . . .	159
Setting Options for Deletion . . . . .	161
Understanding the Deletion Process . . . . .	161
Scheduling the Deletion of Database Assets . . . . .	166
Setting Options for Deleting Only OMF Media, Only MXF Media, or Both . . . . .	169
Setting Options for Deleting Locked Media . . . . .	169
Viewing and Setting the Metadata Override Status . . . . .	170
<b>Chapter 6 Application Settings . . . . .</b>	<b>173</b>
Application Database Settings View . . . . .	173
Setting Options in the Editing Settings Tab . . . . .	174
Audio Settings for Two NAT or SOT Tracks in Avid Instinct . . . . .	175
Application Database Settings: Editing Settings Tab . . . . .	176
Setting Audio Mixing Defaults for Access and Assist . . . . .	182
Sending a Source to Playback in Interplay Assist . . . . .	184
Setting the Shotlist Start Timecode for Interplay Access and Interplay Assist . . . . .	185
Setting an Automatic Timeout for Interplay Assist and Avid Instinct . . . . .	186
Configuring the Frame Locators Display . . . . .	187
Setting Instinct/Assist User Options . . . . .	188
Instinct/Assist User Settings . . . . .	190

	Pro Tools Plug-Ins Settings. . . . .	195
	Installing the Pro Tools Plug-Ins for Interplay. . . . .	195
	Configuring the Pro Tools Import Plug-In. . . . .	195
	Configuring the Pro Tools Export Plug-In. . . . .	197
	Configuring the Pro Tools User Settings Plug-In . . . . .	198
<b>Chapter 7</b>	<b>Avid Interplay Services . . . . .</b>	<b>199</b>
<b>Chapter 8</b>	<b>Troubleshooting. . . . .</b>	<b>201</b>
	Troubleshooting Login Problems . . . . .	201
	Troubleshooting Client Connection Problems. . . . .	202
	Optimizing Avid Interplay Performance. . . . .	202
	Troubleshooting Firewalls and Avid Interplay . . . . .	203
	Troubleshooting the Server Execution User Account . . . . .	204
	Creating the Server Execution User Account. . . . .	204
	Determining the Server Execution User Name . . . . .	206
	Re-creating the Server Execution User . . . . .	207
	Shutting Down or Locking the Server Process . . . . .	208
<b>Chapter 9</b>	<b>Configuring Interplay for a Split Database . . . . .</b>	<b>209</b>
	Understanding a Split Database . . . . .	210
	Supported Configurations . . . . .	211
	Preparing for a Split Database . . . . .	212
	Splitting a Database for New Interplay Installations . . . . .	213
	Splitting a Database for Existing Interplay Installations . . . . .	215
	Configuring the workgroup.xml File . . . . .	219
	Identifying the Root Folder of the Interplay Server Database . . . . .	220
	Reuniting a Split Database . . . . .	221
	Reuniting a Split Database (AvidWG Only) . . . . .	224
	Reuniting a Split Database (AvidWG and _InternalData). . . . .	227
<b>Appendix A</b>	<b>Installed Components and Services . . . . .</b>	<b>233</b>
	Avid Interplay Engine Directory: Folders and Files . . . . .	233
	Apache Folder . . . . .	234
	Activating Creation of the access.log File . . . . .	235
	Data Folder. . . . .	236
	Logs . . . . .	237

	AvDeletes.log . . . . .	238
	AvMetaDataDelete.log . . . . .	239
	AvMoveEx.log . . . . .	240
	Preview Server Folder . . . . .	240
	Server Folder . . . . .	241
	Required TCP/IP Ports . . . . .	241
	Avid Interplay Engine Servers and Services . . . . .	241
	Avid Interplay Engine Server . . . . .	242
	Avid Workgroup HTTP Server . . . . .	243
	Avid Workgroup Server Browser Service . . . . .	244
	Avid Workgroup Preview Server Service . . . . .	244
	Avid Workgroup TCP/COM Bridge Service . . . . .	248
	Avid Workgroup VSS Service . . . . .	249
	Avid Workgroup Engine Monitor Service . . . . .	250
<b>Appendix B</b>	<b>Interplay Engine Configuration Files . . . . .</b>	<b>253</b>
	Configuring the Server Event Manager . . . . .	253
	Config.xml File . . . . .	253
	Supported Actions in Config.xml . . . . .	255
	Supported Events in Config.xml . . . . .	257
	Server Event Configuration Example . . . . .	259
	LogWatch.xml . . . . .	260
	Sending E-mail Notifications from LogWatch.xml . . . . .	261
	Configuring Client Access . . . . .	262
	Setting the Filetransfer Server . . . . .	265
<b>Appendix C</b>	<b>Valid and Invalid Characters in Avid Interplay . . . . .</b>	<b>267</b>
<b>Appendix D</b>	<b>System Metadata Properties . . . . .</b>	<b>269</b>
<b>Appendix E</b>	<b>Server Error Codes . . . . .</b>	<b>281</b>
<b>Appendix F</b>	<b>Consistency Check Codes . . . . .</b>	<b>297</b>
	Consistency Check Critical Errors . . . . .	297
	Consistency Check Errors . . . . .	298
	Consistency Check Warnings . . . . .	300
	<b>Index . . . . .</b>	<b>301</b>

# Using This Guide

Congratulations on your purchase of Avid® Interplay®, a powerful system for managing media in a shared storage environment. This guide describes how to use Avid Interplay Administrator, an Interplay client application that provides tools to configure the Avid Interplay Engine and to manage the database on the server.

This guide is intended for all Avid Interplay administrators who are responsible for installing, configuring and maintaining an Avid Interplay Engine or Avid Interplay Archive Engine (database, server, and all related client connections and user rights) in an Interplay workgroup. This guide includes a detailed description of each of the Avid Interplay Administrator task groups and how you can use them to administer your server and databases. Some of the settings that you are able to change affect the server itself, while others only affect the database stored on the server.

The Interplay Administrator is supported on both the Microsoft® Windows® and the Mac OS® X platforms. When necessary, the guide describes platform-specific differences.



*The documentation describes the features and hardware of all models. Therefore, your system might not contain certain features and hardware that are covered in the documentation.*






*Limited number of client applications per user per machine: A user can run only one Interplay Access session and one Interplay Administrator session on one machine. This software does not support terminal/server sessions.*

# Symbols and Conventions

Avid documentation uses the following symbols and conventions:

---

Symbol or Convention	Meaning or Action
	A note provides important related information, reminders, recommendations, and strong suggestions.
	A caution means that a specific action you take could cause harm to your computer or cause you to lose data.
	A warning describes an action that could cause you physical harm. Follow the guidelines in this document or on the unit itself when handling electrical equipment.
>	This symbol indicates menu commands (and subcommands) in the order you select them. For example, File > Import means to open the File menu and then select the Import command.
▶	This symbol indicates a single-step procedure. Multiple arrows in a list indicate that you perform one of the actions listed.
(Windows), (Windows only), (Macintosh), or (Macintosh only)	This text indicates that the information applies only to the specified operating system, either Windows or Macintosh OS X.
<b>Bold font</b>	Bold font is primarily used in task instructions to identify user interface items and keyboard sequences.
<i>Italic font</i>	Italic font is used to emphasize certain words and to indicate variables.
<b>Courier Bold font</b>	Courier Bold font identifies text that you type.
Ctrl+key or mouse action	Press and hold the first key while you press the last key or perform the mouse action. For example, Command+Option+C or Ctrl+drag.

---

## If You Need Help

If you are having trouble using your Avid product:

1. Retry the action, carefully following the instructions given for that task in this guide. It is especially important to check each step of your workflow.
2. Check the latest information that might have become available after the documentation was published:
  - If the latest information for your Avid product is provided as printed release notes, they are shipped with your application and are also available online.
  - If the latest information for your Avid product is provided as a ReadMe file, it is supplied on your Avid installation CD or DVD as a PDF document (README\_*product*.pdf) and is also available online.

**You should always check online for the most up-to-date release notes or ReadMe because the online version is updated whenever new information becomes available.** To view these online versions, select ReadMe from the Help menu, or visit the Knowledge Base at [www.avid.com/readme](http://www.avid.com/readme).

3. Check the documentation that came with your Avid application or your hardware for maintenance or hardware-related issues.
4. Visit the online Knowledge Base at [www.avid.com/onlinesupport](http://www.avid.com/onlinesupport). Online services are available 24 hours per day, 7 days per week. Search this online Knowledge Base to find answers, to view error messages, to access troubleshooting tips, to download updates, and to read or join online message-board discussions.

## Viewing Help and Documentation on the Interplay Portal

You can quickly access the Interplay Help, PDF versions of the Interplay guides, and useful external links by viewing the Interplay User Information Center on the Interplay Portal. The Interplay Portal is a web site that runs on the Interplay Engine.

You can access the Interplay User Information Center through a browser from any system in the Interplay environment. You can also access it through the Help menu in Interplay Access and the Interplay Administrator.

The Interplay Help combines information from all Interplay guides in one Help system. It includes a combined index and a full-featured search. From the Interplay Portal, you can run the Help in a browser or download a compiled (.chm) version for use on other systems, such as a laptop.

### To open the Interplay User Information Center through a browser:

1. Type the following line in a web browser:

```
http://Interplay_Engine_name
```

For *Interplay\_Engine\_name* substitute the name of the computer running the Interplay Engine software. For example, the following line opens the portal web page on a system named docwg:

```
http://docwg
```

2. Click the “Avid Interplay Documentation” link to access the User Information Center web page.

### To open the Interplay User Information Center from Interplay Access or the Interplay Administrator:

- ▶ Select Help > Documentation Website on Server.

## Interplay Documentation

The following documents describe how to use Avid Interplay:

- *Avid Interplay Best Practices* — provides an overview of the major Interplay components, shows sample configuration diagrams, and describes several of the key features, such as setting up a user database and using the Avid Interplay Archive Engine.
- *Avid Interplay Software Installation and Configuration Guide* — describes how to use the Avid Interplay Installer DVD to install and configure software on the various systems that make up a Interplay environment.
- *Avid Interplay Engine Failover Guide* — describes how to set up a cluster configuration for the Avid Interplay Engine and the Avid Interplay Archive engine.
- *Avid Interplay Engine and Avid Interplay Archive Engine Administration Guide* — describes how to administer your Avid Interplay Engine or Avid Interplay Archive Engine and Avid Interplay database.
- *Avid Interplay Access User’s Guide* — describes how to use Interplay Access to browse, search, and work with assets in the Avid Interplay database.
- *Avid Interplay Assist User’s Guide* — describes how to use Interplay Assist for logging, archiving, and sending to Playback material in an Interplay environment.
- *Avid Instinct User’s Guide* — describes how to use the Avid Instinct application to write iNEWS stories and put together simple audio and video sequences.
- *Avid Interplay Media Services Setup and User’s Guide* — Avid Interplay Media Services lets you control and automate Transcode, Archive, and ProEncode services.



- *Avid Interplay Transfer Setup and User's Guide* — describes how to use Interplay Transfer to transfer media to and from another workgroup, send finished sequences to a configured playback device, ingest media from a configured ingest device, and perform standalone transfers between workstations.
- *Avid Service Framework User's Guide* — describes how to use the logging, monitoring, and management features of the Avid Service Framework applications.
- *Avid Low Res Encode Setup and Configuration* — describes how to set up and configure an Avid Low Res Encode system. Includes information on updating the bootset, root disk image, and configuring a Low Res Encode system to work with CaptureManager.
- *Avid Interplay Capture User's Guide* — describes how to use Interplay Capture, a newsroom ingest tool that enables automated recordings.
- *Avid Interplay Capture Administrator's Guide* — describes administrative concepts, tasks, and reference material for Avid Interplay Capture.
- *Avid CaptureManager User's Guide* — describes how to use CaptureManager™ in a newsroom environment to coordinate video feeds, schedule feed captures at both high and low resolutions, and record late breaking events instantly.
- *Avid CaptureManager Installation and Configuration Guide* — describes how to set up and configure CaptureManager.

All documents are available in PDF form on the Interplay Portal and also on the Avid Knowledge Base at [www.avid.com/onlinesupport](http://www.avid.com/onlinesupport).

## Avid Training Services

Avid makes lifelong learning, career advancement, and personal development easy and convenient. Avid understands that the knowledge you need to differentiate yourself is always changing, and Avid continually updates course content and offers new training delivery methods that accommodate your pressured and competitive work environment.

For information on courses/schedules, training centers, certifications, courseware, and books, please visit [www.avid.com/support](http://www.avid.com/support) and follow the Training links, or call Avid Sales at 800-949-AVID (800-949-2843).



# 1 Getting Started with the Avid Interplay Administrator

The Avid Interplay Administrator provides database administrators and maintenance engineers with the tools required to configure the Avid Interplay Engine and to manage the database on the server.

The following topics provide basic information for using the Interplay Administrator:

- [Understanding the Interplay Engine and Interplay Workgroups](#)
- [Using the Avid Interplay Administrator](#)
- [Starting the Avid Interplay Administrator](#)
- [Using the Avid Interplay Administrator Window](#)
- [Opening an Interplay Administrator View](#)
- [Opening Interplay Help](#)
- [Exiting the Avid Interplay Administrator](#)

For an overview of all Avid Interplay components, see the *Avid Interplay Best Practices Guide*.

## Understanding the Interplay Engine and Interplay Workgroups

The Avid Interplay Engine forms the backbone of the Interplay environment. The Interplay Engine is a server that combines an asset database with workflow management software, both of which are integrated with Avid shared storage and Avid archive solutions. This topic provides basic information about the functions and components of the Interplay Engine.

### **One Interplay Engine, One Interplay Database, One Shared Storage Network**


The Interplay Engine is one component of an Interplay workgroup. At a minimum, an Interplay workgroup is composed of one Interplay Engine, one Interplay database, one Avid shared-storage network (Avid ISIS<sup>®</sup>, Avid Unity<sup>™</sup> MediaNetwork, or Avid Unity LANshare), and associated software and services.

## 1 Getting Started with the Avid Interplay Administrator

An Interplay database consists of two parts:

- A metadata database, which holds information about the assets, or *metadata*.
- Source files for the assets, for example, graphics files and Avid media files. The source files for file assets can be stored on the Interplay Engine or on an Avid shared-storage system. The source files for Avid assets are always stored on shared storage.

The following illustration shows the metadata database and the source files for file assets stored on the internal drive of the Interplay Engine server and the source files for Avid assets stored on an Avid shared storage workspace.



For information about all Interplay components and detailed sample configurations, see *Avid Interplay Best Practices*.

### Avid Assets, File Assets, and Splitting the Database


Interplay manages two different kinds of assets. *Avid assets* are assets that are created by Avid applications through capture, ingest, import, or transfer. Avid assets include:


- Master clips
- Subclips
- Sequences
- Effects
- Motion effects
- Rendered effects
- Group clips

*File assets* are any assets that are not created by an Avid application. Any file you can create on your workstation, through applications such as Adobe Photoshop or Microsoft Word, can be added to the Interplay database and managed by Interplay as a file asset.

Media files for Avid assets are always stored on an Avid shared-storage system. Source files for file assets can be stored on the Interplay Engine or on an Avid shared-storage workspace. The location that holds file assets is called the *file repository*.

When you first install Interplay Engine software, the installation program requires you to set one root folder for the database on a local drive. By default, this root folder holds both the metadata database and files for file assets. If the Interplay Engine server does not have adequate local storage for your Interplay database (for example, if your facility stores a large number of file assets in the Interplay database), you can configure the Interplay Engine to store only the metadata database on the Interplay Engine. All other database files and folders can be stored on an Avid shared-storage workspace. This configuration is called a *split database*. The following illustration shows a split database.



 *In a split database, source files for file assets and streamed properties for Avid assets (head frames and AAF information) are stored on a shared storage workspace. Media files for Avid assets, such as .mxf files, are always stored on a shared storage workspace.*

For more information, see [“Configuring Interplay for a Split Database”](#) on page 209.

## Multiple Workgroups


A large production facility can have more than one Interplay workgroup. Each workgroup must have its own Interplay Engine, database, and shared storage network. Users on Interplay Access can view and access assets from more than one workgroup and can transfer them from one to another using a file copy procedure for file assets and Avid Interplay Transfer for Avid assets. You can also use the Interplay Delivery service to transfer Avid assets.

## 1 Getting Started with the Avid Interplay Administrator

### Interplay Archive Engine

A facility might also include an Interplay Archive Engine. An Interplay Archive Engine is configured similarly to an Interplay Engine. An Archive Engine is integrated with a third-party archive system. An Interplay Archive database is always named AvidAM. An Interplay database is always named AvidWG.

An Interplay Archive database and an Interplay database use different icons, as shown in the following illustration from Interplay Access. The archive database is represented by a safe, and archive folders are represented by boxes.



For more information about the Interplay Archive Engine, see *Avid Interplay Best Practices*.



*In this guide, references to the Interplay Engine also refer to the Archive Engine, unless otherwise noted.*

### **Central Configuration Server**

If a production facility includes more than one Interplay workgroup, you can specify one Interplay Engine as the *Central Configuration Server* (CCS). The CCS is an Interplay Engine module that stores information that is common to all other Interplay Engines. The CCS provides a means to manage user accounts across multiple workgroups. For more information, see [“Understanding the Central Configuration Server” on page 93](#).

### **Server Execution User**

The Server Execution User is a Windows operating system user that runs the Interplay Engine processes. You specify the user name and password for the Server Execution User when you install the Interplay Engine on the server. The Server Execution User needs local administrator rights on the operating system for the Interplay Engine server and read/write access to the Avid shared-storage file system.

For more information, see [“Troubleshooting the Server Execution User Account” on page 204](#).

### **Avid Interplay as a Client-Server Application**

Avid Interplay is designed as a client-server application. The Interplay Engine is configured to run on a central machine that is accessible to all users through a network. An Avid Interplay application that runs on a client machine is a client of the Avid Interplay Engine server. Avid Interplay client applications, such as Interplay Access, Interplay Assist, Avid Instinct<sup>®</sup>, and Avid editing applications that use the Interplay Window can access and browse multiple databases. The Interplay Administrator is also a client application.

Avid Interplay uses TCP/IP and related protocols for its network communication. Therefore, TCP/IP must be installed on all machines. Since TCP/IP is used to access the Internet, most users already have this component installed. See [“Required TCP/IP Ports” on page 241](#) for more information.

## **Using the Avid Interplay Administrator**

The Avid Interplay Administrator is a client application that you use to manage either the Interplay Engine or the Interplay Archive Engine. The Interplay Administrator is installed at the same time that you install Interplay Access. You can install the Interplay Administrator as a client on any computer in your network and then use it to manage any Interplay Engine

## 1 Getting Started with the Avid Interplay Administrator

or Interplay Archive Engine that is available on the network. For information on installing Interplay Access and the Interplay Administrator, see the *Avid Interplay Software Installation and Configuration Guide*.

The Interplay Administrator provides you with the tools you need for the following major tasks:

- Setting up a new database. See [“Creating an Interplay Database” on page 31](#).
- Backing up the database. Backing up the database regularly protects your data, allowing you to restore the database to a saved state in the event of failure. See [“Creating and Restoring Database Backups” on page 36](#).
- Maintenance tasks, such as locking, unlocking, and restarting the server. See [“Server Settings” on page 81](#).
- Creating, editing, and deleting user accounts and managing user authorization. See [“User Management” on page 93](#).
- Configuring client applications and the workgroup. See [“Site Settings” on page 129](#).
- Configuring the Interplay Archive Engine. See [“Specifying Archive Settings” on page 156](#). For more information on archiving, see *Avid Interplay Best Practices* and the *Avid Interplay Media Services Setup and User’s Guide*.
- Configuring Application Settings and Avid Interplay Services. See [“Application Settings” on page 173](#) and [“Avid Interplay Services” on page 199](#).


## Starting the Avid Interplay Administrator

**To start the Avid Interplay Administrator:**

1. Do one of the following:
  - ▶ Click the Start button and then select All Programs > Avid > Avid Interplay Access Utilities > Avid Interplay Administrator.
  - ▶ From Interplay Access, select Tools > Open Interplay Administrator.


The Avid Interplay Administrator Server Login screen appears.





The first time you open the Interplay Administrator, the Server text box is empty. If you have already logged into a server, the text box shows the last server you logged in to.

2. Select the server you want to work with by doing one of the following:
  - ▶ Accept the server that is displayed.
  - ▶ Type the name of the server that you want to log in to. You can also use an IP address.
  - ▶ Click the arrow for the Server list and select the server name from the list.



The first part of the list shows recent servers, the second part of the list shows servers that were added manually (not on a local area network), and the third part shows servers available on your local area network.

- ▶ Click the arrow for the server list and select Add Server. Type a new server name.

## 1 Getting Started with the Avid Interplay Administrator

3. Type a user name and password for an account with administration rights.

On the first start after installing the Avid Interplay Engine, only the user Administrator exists. Type “Administrator” in the dialog box. The password is empty by default. Change the password of the Administrator as soon as possible (see [“Viewing and Setting Attributes”](#) on page 112).



*The Interplay Administrator account is different from the Server Execution User account. The Interplay Administrator account is used to manage users and the database. The Server Execution User account is used to run the Interplay Engine processes.*


4. Click Connect.

The Interplay Administrator window opens.

If you have any problems logging in, see [“Troubleshooting Login Problems”](#) on page 201.

## Using the Avid Interplay Administrator Window

The Avid Interplay Administrator window is divided into six groups: Database, Server, User Management, Site Settings, Application Settings, and Avid Interplay Services. The name of the Interplay Engine server you are connected to is displayed in the upper right of the window.



Each group contains views for managing components of the Avid Interplay Engine. Each group is described in a separate section of this guide:


- [“Database Settings”](#) on page 31
- [“Server Settings”](#) on page 81
- [“User Management”](#) on page 93
- [“Site Settings”](#) on page 129
- [“Application Settings”](#) on page 173
- [“Avid Interplay Services”](#) on page 199

## Opening an Interplay Administrator View

**To open an Interplay Administrator view:**

- ▶ In the Interplay Administrator window, click an icon.

The view you select replaces the Interplay Administrator window. Each view includes a path that shows the relative location of that view. The following illustration shows part of the Create Database view. In this example, the path shows that the Create Database view is included in the Database section of the Interplay Administrator window (In the path, the Interplay Administrator window is represented as the Interplay Server).



**To return to the Interplay Administrator window:**

- ▶ Click the Menu button in the upper left of the view.

## Opening Interplay Help

The Interplay Help system is installed when you install the Interplay Engine. The Interplay Help system provides all user and administrator information that is contained in the Interplay manuals. The Interplay Administrator Help menu provides five entry points: one for the Welcome screen and four that correspond to four Interplay applications:

- Interplay Administration Help
- Interplay Media Services Help
- Interplay Transfer Help
- Interplay Installation Help

You can access the entire Help system, including the Search and Index tabs, from any of those entry points.

**To access Interplay Help:**

- ▶ Select Help, and then select the desired application.

- ▶ Select Documentation Website on Server.

The Avid Interplay User Information Center page opens. You can open the Help, PDF versions of the Interplay user guides, and other useful links. See [“Viewing Help and Documentation on the Interplay Portal”](#) on page 15

## Exiting the Avid Interplay Administrator

When you are finished using the Avid Interplay Administrator, you should log out or close the application. Logging out can be convenient if you want to log in to a different database.

### **To log out:**

- ▶ Click the Log out button in the upper right of the Interplay Administrator window.  
The application remains open, with the login screen displayed.

### **To close the Interplay Administrator, do one of the following:**

- ▶ Select File > Exit.
- ▶ Click the close button in the upper right of the window.  
The Interplay Administrator window closes.

## 1 Getting Started with the Avid Interplay Administrator

## 2 Database Settings

The Database settings allow you to create, configure, and manage the Interplay database. The following topics describe how to use these settings:

- [Creating an Interplay Database](#)
- [Avid Interplay Databases, Folders, and Files](#)
- [Limits on the Number of Assets and Objects in the Interplay Database](#)
- [Creating and Restoring Database Backups](#)
- [Performing a Consistency Check](#)
- [Viewing Database Information](#)
- [Locking and Unlocking Databases](#)
- [Managing Databases: Deactivating, Activating, and Migrating](#)
- [Moving a Database to Another Server \(Non-Clustered Systems\)](#)
- [Moving a Database and Users to Another Server \(Non-Clustered Systems\)](#)
- [Moving a Database to Another Server \(Clustered Systems\)](#)
- [Moving a Database and Users to Another Server \(Clustered Systems\)](#)
- [Moving a Database Under Low Disk Space Conditions](#)
- [Renaming a Database](#)

### Creating an Interplay Database

The Create Database view lets you name and create a new Interplay database. You need to create an Interplay database after you install the Interplay Engine and Interplay Access software.



**Avid supports only one database for each Interplay Engine. The database must be named AvidWG, or for an Archive Engine database, AvidAM.**

The root folder for a new database is set during the installation of the Interplay Engine software. By default, the installation program creates one shared folder for both the metadata database and the source files for file assets (the file repository). The default location is the

## 2 Database Settings

D:\Workgroup\_Databases folder (or S:\Workgroup\_Databases on a cluster system). This folder is represented by the administrative share name WG\_Database\$. The \$ indicates a hidden share.



*To identify the actual folder, open a Command Prompt window and type `net share`.*

If the Interplay Engine server does not have adequate local storage for your Interplay database (for example, if your facility stores a large number of file assets in the Interplay database), you can configure the Interplay Engine to store only the metadata database on the Interplay Engine. The file repository and all other database files and folders can be stored on an Avid shared-storage workspace. This configuration is called a *split database*.

If you are going to use a split database configuration, the most efficient approach is to specify how to divide the database before you create it. You specify the locations in the Server Settings view (see [“Changing the Database and Data Locations” on page 81](#)) and then create the database in the Create Database view.

The following illustration shows the Create Database view with two locations specified:

- The metadata database will be installed in \\DOCWG\WG\_Database\$, which represents a folder on the Interplay Engine (by default, D:\Workgroup\_Databases).
- The file repository will be installed in \\AAC-ISIS\File\_Assets\, which is a shared storage workspace that you need to set in the Server Settings view.

The screenshot shows the 'Avid Interplay Administrator' window with the 'Create Database' view active. The 'New Database Information' section contains the following fields:

- Database Name: AvidWG
- Description: Main production server
- Create default Avid Interplay structure

The 'New Database Location (Meta Data)' section contains:

- Root Folder: \\DOCWG\WG\_Database\$
- Custom Folder: [Empty field] [Browse...]

The 'New Data Location (Assets)' section contains:

- Root Folder: \\AAC-ISIS\File\_Assets\
- Custom Folder: [Empty field] [Browse...]

A 'Create' button is located at the bottom center of the dialog.



For complete information on configuring a split database, see [“Configuring Interplay for a Split Database” on page 209](#).

**To create an Interplay database:**

1. In the Database section of the Interplay Administrator window, click the Create Database icon.

The Create Database view opens.

2. In the New Database Information area, leave the default “AvidWG” in the Database Name text box. For an archive database, leave the default “AvidAM.” These are the only two supported database names.
3. Type a description for the database in the Description text box, such as “Main Production Server.”
4. Select “Create default Avid Interplay structure.”

After the database is created, a set of default folders within the database are visible in Interplay Access and other Interplay clients. For more information about these folders, see the *Avid Interplay Access User’s Guide*.

5. Keep the root folder for the New Database Location (Meta Data).

The metadata database must reside on the Interplay Engine server.

6. Keep the root folder for the New Data Location (Assets).

If you are creating a split database, this entry should show the Avid shared-storage workspace that you set in the Server Settings view (see [“Changing the Database and Data Locations” on page 81](#)).

7. Click Create to create directories and files for the database.

The Interplay database is created. For information about the folders and files that compose the database, see [“Avid Interplay Databases, Folders, and Files” on page 33](#).

## Avid Interplay Databases, Folders, and Files

When the Interplay Engine creates a database, it creates a set of directories and files in the locations you specified in the Create Database view (see [“Creating an Interplay Database” on page 31](#)).

The Interplay Engine also creates a user database, which is located on the server that you designated as the Central Configuration Server during the installation (see [“Understanding the Central Configuration Server” on page 93](#)).

### Database File Structure

The database file structure is based on the administrative share that was set during the Interplay Engine installation. By default, this administrative share is named `WG_Database$` and is associated with the folder `D:\Workgroup_Databases` (`S:\Workgroup_Databases` for cluster systems). The “\$” indicates a hidden share. To identify the actual folder, open a Command Prompt window and type `net share`.

This folder contains either the AvidWG or the AvidAM folder. If the server is functioning as the Central Configuration server, the folder also includes the `_InternalData` folder. The following table describes these folders:

Database	Description
<code>_Internal Data</code>	User database: Contains Central Configuration Server information such as users and roles.
AvidWG	Interplay Engine database: Contains metadata for Avid assets and file assets, and source files for file assets.
AvidAM	Interplay Archive Engine database: Contains archived metadata for Avid assets and file assets, and source files for file assets.

### Split Database

If you configured your system to create a split database (either when creating a database or after installation), an AvidWG folder exists on both the Interplay Engine server and the shared storage workspace. Only the `_Database` folder is located on the Interplay Engine server. The other folders are located on the shared storage workspace. For more information about working with a split database, see [“Configuring Interplay for a Split Database” on page 209](#).

### Database Folders and Files


The following table lists the folders that are included in the AvidWG or AvidAM folders. During normal work, users or administrators do not need to work directly with these folders and files. All access for normal work is through Avid Interplay products. You need to work with these files when splitting a database or possibly when troubleshooting a problem.



**You should exclude the `_Database` and `_PropertyStore` folders of each database from any kind of virus checking because virus checking tools might try to lock the database files).**

---

**Database Directories and Files**

Directory or File	Directory or File Description
_Database	<p>The main database directory, which contains database files and the database journal. These files contain the database structure and all metadata. All files within this folder contain binary information and cannot be viewed or edited with a text editor.</p> <p>If you are working with a split database, this directory is located on the Interplay Engine server and other directories are located on a shared storage workspace.</p>
_Master	<p>The main data directory, which contains the source files for file assets that are managed by the database (the file repository). This directory contains source files for all versions of the file assets.</p> <p> <i>Source files for Avid assets are always stored in Avid media folders on shared storage. If you are working with a split database, this directory is located on a shared storage workspace.</i></p>
Handover Directories: _Import, _CheckIn, _PropertyHandover, _Handover	<p>Whenever a file is copied from the client to the server, the file is first copied into one of these directories, depending on what operation (check in, import, and so on) was performed. The server then moves the file from these handover directories into the _Master directory.</p>
_PropertyStore	<p>The database directory that contains files holding the contents of streamed properties. <i>Streamed properties</i> include metadata about Avid assets, such as head frames and AAF information.</p>
_Backup	<p>The data folder that contains backup versions of the database that are created through the automated backup process (see <a href="#">“Scheduling Automatic Database Backups” on page 41</a>).</p>
AvidWG.pro, AvidAM.pro	<p>A cookie file representing the database. It contains no vital information, but it is needed to activate a deactivated database (see <a href="#">“Activating a Deactivated Database” on page 64</a>).</p>
Folderlocations.xml	<p>A file that informs the server about the location of the _Database directory. If you set a new location for the file assets, you might need to edit this file. See <a href="#">“Splitting a Database for Existing Interplay Installations” on page 215</a>.</p>
_Buckets	<p>Not currently used.</p>

---

# Limits on the Number of Assets and Objects in the Interplay Database

The Avid Interplay database supports up to 5 million database objects and a smaller number of database assets. The number of assets is smaller because some assets, such as master clips and sequences, are associated with multiple objects.

The following list shows some of the things that can increase the number of objects in the database:

- The number of audio and video tracks associated with master clips. For example, a master clip with two audio tracks and one video track has four database objects: one for the master clip and one for each audio and video track.
- The number of copies of master clips and sequences in different folders in the database. Each copy represents a copy of the related database objects.
- The number of versions of sequences. For example, each version of a sequence contains separate database objects for the sequence, its master clips, and related tracks.

For information about determining the size of the Interplay database, see [“Viewing Database Information” on page 60](#).

## Creating and Restoring Database Backups

There are two basic approaches to backing up an Interplay database:

- Using a combination of backups scheduled through the Interplay Administrator (automatic backups) and manual backups of other parts of the database. This approach should be used as part of a regular backup strategy.
- Using a professional backup tool to do a complete backup to offline media. This backup should include both the Interplay backup and the folders that Interplay backup process does not include.

Creating a complete copy of the complete database using Robocopy or 7-Zip is useful before doing a major system upgrade. These tools can be used in place of a professional backup tool. However, keep in mind that performance and stability might suffer.

The following topics provide information about creating and restoring database backups:

- [“Types of Interplay Administrator Backups” on page 37](#)
- [“Recommendations for Backup Configuration” on page 38](#)
- [“Scheduling Automatic Database Backups” on page 41](#)
- [“Starting a Backup Manually” on page 45](#)

- [“Using an Archiving Tool for Backup” on page 46](#)
- [“Restoring an Earlier Version of a Database” on page 48](#)

## Types of Interplay Administrator Backups

The Interplay Administrator lets you run create two different kinds of metadata backups: a Complete metadata backup and a Fast metadata backup. You can schedule backups to run automatically or you can run a backup manually. The following table describes the different types of backups.

Backup Type	Description
Complete (Full) backup	Creates copies of database files in the <code>_Database</code> folder and streamed properties files in the <code>_PropertyStore</code> folder. Streamed properties include metadata about Avid assets, such as head frames and AAF information. This is the preferred backup.
Fast backups:	
- Incremental	Creates copies of database files and streamed properties files that were added to the database since the last Complete Backup, the last Incremental Backup, or the last Differential Backup.
- Differential	Creates copies of database files and streamed properties files that were added to the database since the last Complete Backup. In most cases, this backup takes longer to perform than an Incremental backup.
- Metadata Only	(Manual backup only) Creates copies of database files in the <code>_Database</code> folder, but not streamed properties files in the <code>_PropertyStore</code> folder. This type of Fast backup is less useful than an Incremental or Differential backup. See <a href="#">“Starting a Backup Manually” on page 45</a> .



**The `_PropertyStore` folder is critical if you need to completely restore Avid assets. Avid recommends that you schedule a Complete backup once a week and a Fast backup (either Incremental or Differential) daily.**

For information on how to restore a database, see [“Restoring a Complete Backup or a Fast Backup” on page 50](#).

### Recommendations for Backup Configuration

Automatic backups, as scheduled through the Interplay Administrator, do not back up the entire database, so they are only one component of a complete backup strategy.

The following table lists the different types of backups needed to completely back up the Interplay database. For an Interplay archive, substitute AvidAM for AvidWG.

Type of Backup	Folders or Files Backed Up
Fast Metadata Only backup	AvidWG\_Database
Complete (Full) backup	AvidWG\_Database
Fast Incremental backup	AvidWG\_PropertyStore
Fast Differential backup	
Automatic Full Backup	WG_Database\$\_InternalData This folder is automatically backed up once a week at 1 a.m. on Sunday.
Manual backup	AvidWG\_Master AvidWG\AvidWG.pro AvidWG\FolderLocations.xml  See <a href="#">“Avid Interplay Databases, Folders, and Files” on page 33</a> for descriptions of these folders and files. It is not necessary to back up AvidWG\_Backup unless you want to make a backup of automated backups. Other folders in AvidWG do not need to be backed up because they are temporary folders that are automatically recreated.

This type of manual backup might involve tape backup or another kind of backup process.



**The `_Master` folder, which holds source files for file assets, is not included in the automatic backup, which includes only metadata. It must be backed up by another backup method regularly. Also be aware that the automatic backup process does not back up Avid media files on shared storage workspaces.**

It is extremely important to use the automatic backup process available through the Interplay Administrator instead of just a tape backup for backing up the `_Database` and `_PropertyStore` folders. Tape backups can be:

- **Inconsistent:** A tape backup of the `_Database` folder while the server is running can lead to inconsistent backup files because the server might not have applied all the transactions to the database yet.
- **Inconvenient:** Because it is not safe to make tape backups of the `_Database` folder while the server is running, the server must be completely shut down during tape backup, causing inconvenience.
- **Unpredictable and dangerous:** The backup might lock the database files. This prevents the server from reading and writing those files. The database could become damaged.

Automatic backup ensures database consistency.

### Recommended Backup Configuration

Avid recommends the following backup configuration:

- **Enable a daily Avid Interplay database backup.** The backup should be set to run once daily at night, when the server is not being used or usage is lowest. See [“Scheduling Automatic Database Backups” on page 41](#).
- **Decide whether to schedule the daily backup as a Complete backup or Fast backup.** If you have a very large database, you can save time by scheduling a Fast backup daily and a Complete backup every few days. However, keep in mind that a Complete backup is needed to restore Avid assets. Because Complete backups can affect system performance, schedule Complete backups when the server is not being used or when usage is lowest. See [“Types of Interplay Administrator Backups” on page 37](#).
- **Check the “number of backups to keep” setting.** The Avid Interplay Engine always keeps the last Complete backup and any later Fast backups. If you want to keep more than one Complete backup, change the “number of Backups to keep” setting to be larger than the number of scheduled Fast backups. The default setting is 10.

The number of backups to keep includes Complete and Fast backups. When the number of backups to keep is exceeded, the system deletes the oldest backup after the last Complete backup. For example, if you schedule Complete backups once a week and schedule Fast backups every day, the number of backups to keep must be larger than 6. Otherwise, on the sixth day the system will delete the second-to-last Complete backup.

- **Determine where to store the automatic backups.** By default, the `_Backup` folder is located in the `Workgroup_Databases` folder. Depending on the size of the database, you might need to change the location to store backups. If you select a custom location, you can rename the folder from `_Backup` to another name.

## 2 Database Settings

**Non-cluster systems:** The default path is

- D:\Workgroup\_Databases\AvidWG\\_Backup

If you are working with a split database, by default the \_Backup folder is located with the file repository on the shared-storage workspace, for example:

- \\SharedStorageServer\WorkspaceName\AvidWG\\_Backup

Storing backups on shared storage is an acceptable configuration, either as part of a split database or as a custom location.



*Prior to Interplay Engine v1.2.4, storing backups on shared storage was not recommended because of the large number of small files included in the backup. However, the backup mechanism included with Interplay Engine v1.2.4 or later significantly reduces the number of files created in the \_PropertyStore folder, which reduces the amount of storage required.*

Alternatively, you can store the backups on an external file server. You need to use a UNC path when you specify the location. Make sure the Server Execution User has read/write access to this external file server and the backup folder. See [“Troubleshooting the Server Execution User Account” on page 204](#).

**Cluster systems:** The default path is

- S:\Workgroup\_Databases\AvidWG\\_Backup

On cluster systems, Avid recommends that you specify \\?\d:\backup as the path for Interplay backups. (This syntax, with a question mark, is known as a Long UNC or UNCW path, and allows for more characters than the 260-character limitation of the short UNC path.) This path will create backups on the local drive of the active node, rather than the Infortrend, thus avoiding a single point of failure.



*SR2400 systems were shipped with 73 GB drives, which are too small for regular backups. These systems should be upgraded to include larger drives.*

- **Ensure that the backups are working and actually creating backups.** To test the backup, check that the backup subfolders *dbname\_date\_time* are being created at the specified times (according to the backup configuration) and that these subfolders are not empty. Every backup should create its own subfolder.

For example, on a non-cluster system, your backup folders might be created in the following location:

- D:\Workgroup\_Databases\AvidWG\\_Backup

A backup subfolder might be named AvidWG\_2007-05-22\_03-00.



- **Enable a different backup mechanism, such as tape backup, for all folders except the `_Database` and `_PropertyStore` folders (see the table at the beginning of this topic).** The `_Master` folder of each database is the most important for the tape backup. Do not include the `_Database` and `_PropertyStore` folders of each database in the tape backup.
- **After a Complete backup, copy the backup folder to offline media to prevent data loss.** You can do this as a separate step or as part of a backup of the complete database to offline media (see the next bullet). Use a backup tool (such as Robocopy or 7-Zip) that can handle long path names and does not use excessive bandwidth, to avoid slowing down activity on the Interplay Engine. (See [“Using an Archiving Tool for Backup” on page 46](#)).
- **Perform a backup of the complete database to offline media.** Avid recommends a complete backup to offline media using a professional backup tool. Archive tools such as Robocopy or 7-Zip are useful before doing a major system upgrade. They can be used in place of a professional backup tool. However, performance and stability might suffer.
- **If you schedule a regular restart of the engine, set it after the regular backup is created.** If you restart the Interplay Engine, you cannot create a backup until at least one client connects to the engine. This could be a problem if you schedule a restart and backup at a time when there is little or not activity, such as the middle of the night.



**The `_Database` and `_PropertyStore` folders of each database should be excluded from any kind of virus checking (virus checking tools might try to lock the database files).**

## Scheduling Automatic Database Backups

The Schedule Backups view in the Interplay Administrator lets you schedule the type and frequency of your automatic backups. You can schedule two kinds of backups: Complete and Fast. You can schedule one of two different Fast backups: Incremental or Differential. For a description of the different types of backups, see [“Types of Interplay Administrator Backups” on page 37](#).

The Interplay Engine performs an automatic backup without locking or shutting down the server, and users can continue to work with the database. During a backup operation, all actions on the engine are cached to ensure a fully consistent backup. As a result, the performance of the Interplay Engine is slower. You should not schedule large-scale deletions during a backup operation.

Automatic backups create copies of metadata files, but do not create copies of the assets. You need to use a different process, such as tape backup, to back up your assets, as described in [“Recommendations for Backup Configuration” on page 38](#).

## 2 Database Settings



**Only `_Database` and `_PropertyStore` are backed up through the Interplay Administrator backup process. Other directories, such as `_Master`, need to be backed up through a different process.**



**The `_PropertyStore` folder is critical if you need to completely restore Avid assets. Avid recommends that you schedule a Complete backup once a week and a Fast backup (either Incremental or Differential) daily.**

By default, backups are stored in the following folder:

`\\InterplayEngine\workgroup_Databases\AvidWG\_Backup`


You can specify another location, including shared storage. Make sure the Server Execution User has read/write access this location. For more information, see [“Recommendations for Backup Configuration” on page 38](#).

For information on restoring a database, see [“Restoring a Complete Backup or a Fast Backup” on page 50](#).

### **To schedule database backups:**

1. In the Database section of the Interplay Administrator window, click the Schedule Backups icon.

The Schedule Backups view opens.



2. In the list on the left side of the view, select the database for which you want to view or specify automatic backup settings. The current settings are displayed.
3. (Option) In the Backup Information area, change your preferences if necessary.

“Backup only if modified” is selected by default to save space and avoid duplicate identical copies. The default number of versions to keep is 10. The Avid Interplay Engine always keeps the last Complete backup and later Fast backups. For more information, see [“Recommendations for Backup Configuration” on page 38.](#)

## 2 Database Settings

4. (Option) In the Backup Location preference, change the path if desired.
  - a. Select Custom.
  - b. Click Browse, and navigate to the location you want. For a shared storage location, you might need to type the path.

The custom location must be specified as a UNC path. You can also change the name of the folder from \_Backup to another name. See [“Recommendations for Backup Configuration” on page 38](#).

5. (Option) In the Fast Metadata Backup area, select “Fast Metadata Backup Enabled” (disabled by default).
6. (Option) If Fast Metadata Backup is enabled, you can change the Fast backup frequency. The default is set to Daily. You can select any number of days on which you would like to perform Fast backups or you can set a Fast backup for one day a month.
7. (Option) If Fast Metadata Backup is enabled, you can change the Fast backup time by doing one of the following:
  - Select Once at and change the hour and minutes (within 10 minute intervals) on which it occurs using the up and down arrows.
  - Select Every and set the backup to occur at regular intervals starting at midnight. Use the down arrow to select the interval.
  - Select Custom and specify custom backup times. Use the up and down arrows to select the time, and then select Add. Repeat to add more times to perform the backup. Select a time and then Remove to cancel a backup.

The Backup time is the Interplay Engine server's local time.

8. In the Complete Metadata Backup area, make sure the option “Complete Metadata Backup Enabled” is selected (default).

Avid recommends that you schedule a Complete backup once a week.
9. (Option) Change the Complete backup frequency. Because Complete backups can take a long time and affect system performance, Avid recommends that you perform Complete backups when the server is not being used or when usage is lowest. The default is set to Sunday. You can select any number of days you would like to perform Complete backups.
10. (Option) Change the Backup time by selecting one of the following:
  - ▶ Select Once at and change the hour and minutes (within 10 minute intervals) on which it occurs using the up and down arrows.
  - ▶ Select Every and set the backup to occur at regular intervals starting at midnight. Use the down arrow to select the interval.

- ▶ Select Custom and specify custom backup times. Use the up and down arrows to select the time, and then click Add. Repeat to add more times to perform the backup. Select a time and click Remove to cancel a backup.

11. Click the Apply Changes button.

## Starting a Backup Manually


You can start an Interplay Administrator Backup manually, rather than waiting for a scheduled automatic backup or changing the existing backup schedules.

### To start a backup manually:

1. In the Database section of the Interplay Administrator window, click the Schedule Backups icon.

The Schedule Backups view opens.

2. In the list on the left side of the view, select the database for which you want to view or specify automatic backup settings. The current settings are displayed.
3. At the bottom of the view, click the “Start Backup Now...” button.



4. Select the kind of backup you want to create. For a description of the different types of backups, see [“Types of Interplay Administrator Backups”](#) on page 37.
5. Click OK

The backup is created in the location you specified. If you navigate to the location, and the backup is still being created, the folder name includes the words “backup in progress.”

### Using an Archiving Tool for Backup

In some circumstances, such as performing a system upgrade, you might want to use an archive tool to create a backup copy of the complete database folder (AvidWG or AvidAM) and the user database folder (\_InternalData). For information on the location and contents of the databases, see [“Avid Interplay Databases, Folders, and Files” on page 33](#).

If you create a backup archive, keep in mind that a complete backup can take several hours, during which the Interplay database is locked and deactivated. Also, you need to use a backup tool that can handle long path names (longer than 256 characters). For example, use Robocopy (contained in rktools.exe, available on Microsoft.com) or 7-Zip (an open source utility) to create the archive. You can save backup time by removing old backups from the \_Backup folder.

#### **To make a backup copy of the database on a non-cluster system:**

1. Open the Interplay Administration tool.
2. Use the following steps to lock the database:
  - a. Click Lock/Unlock Databases.
  - b. Select the database in the Unlocked Databases list.
  - c. Click Lock Database.
3. Click Menu and click Manage Databases.
4. Select the AvidWG database and click Deactivate. Select AvidAM for an Archive Engine.
5. Click Menu and click the Restart Server view.
6. Click Restart Server and close the Interplay Administration tool.
7. Use a backup tool to make a copy of the following folders and record their location. The following tables show the default locations.

#### **Interplay Engine or Interplay Archive Engine**

<b>Folder Name</b>	<b>Default Location</b>
AvidWG (Interplay Engine database)	D:\Workgroup_Databases\AvidWG
AvidAM (Archive Engine database)	D:\Workgroup_Databases\AvidAM
_InternalData (user database if engine is a Central Configuration Server)	D:\Workgroup_Databases\_InternalData

**Interplay Engine (Split Database)**

<b>Folder Name</b>	<b>Default Location</b>
AvidWG (_Database folder only)	D:\Workgroup_Databases\AvidWG
AvidWG (all other database folders)	\\SharedStorageServer\WorkspaceName\AvidWG
_InternalData (user database if engine is a Central Configuration Server)	D:\Workgroup_Databases\_InternalData

**To make a backup copy of the database on a cluster system:**

1. Open the Interplay Administration tool.
2. Use the following steps to lock the database:
  - a. Click Lock/Unlock Databases.
  - b. Select the database in the Unlocked Databases list.
  - c. Click Lock Database.
3. Click Menu and click Manage Databases.
4. Select the AvidWG database and click Deactivate. Select AvidAM for an Archive Engine.
5. Close the Interplay Administration tool.
6. Click Start and select Programs > Administrative Tools > Cluster Administrator.
7. Open the Groups folder.
8. Select the Avid Workgroup Server group.
9. Select the Avid Workgroup Engine Monitor resource and take it offline.
10. If you performed the previous step correctly, drive S: should still be accessible within the Windows environment. If it is not available, use the Cluster Administration tool to put drive S: online by clicking on the disk resource within the “Avid Workgroup Server Group” and selecting online.

## 2 Database Settings

11. Use a backup tool to make a copy of the following folders and record their location.

### Interplay Engine or Interplay Archive Engine

Folder Name	Default Location
AvidWG (Interplay Engine database)	S:\Workgroup_Databases\AvidWG
AvidAM (Archive Engine database)	S:\Workgroup_Databases\AvidAM
_InternalData (user database if engine is a Central Configuration Server)	S:\Workgroup_Databases\_InternalData

### Interplay Engine (Split Database)

Folder Name	Default Location
AvidWG (_Database folder only)	S:\Workgroup_Databases\AvidWG
AvidWG (all other database folders)	\\SharedStorageServer\WorkspaceName\AvidWG
_InternalData (user database if engine is a Central Configuration Server)	S:\Workgroup_Databases\_InternalData



*On cluster systems, Avid recommends that you specify \\?\d:\backup as the path for Interplay backups. See “Recommendations for Backup Configuration” on page 38.*

## Restoring an Earlier Version of a Database

Restoring a backup version of the \_Database and \_PropertyStore folders returns a database to the state it was in when the backup was created. Before restoring a database, make sure that it is really necessary, because changes since the backup will be lost.

To restore a backup, you need to run the InterplayRestore tool in a Command Prompt window. The InterplayRestore tool is installed in the following folder:

C:\Program Files\Avid\Avid Interplay Engine\Server

The tool includes in-line help that describes all options for using the tool.

The following topics provide instructions for restoring an earlier version of a database:

- “Restoring a Complete Backup or a Fast Backup” on page 50
- “Using the InterplayRestore Tool on the Interplay Engine Server” on page 53



- [“Database Restore Session Example” on page 56](#)
- [“Using the BackupArchive Tool to Restore Files” on page 57](#)
- [“Restoring Archived Log Files” on page 60](#)

You cannot restore parts of a backup, for example, a specific sequence or folder. You can restore only a Complete backup or a Fast backup.

### How the Restore Tool Works with Streamed Properties Files

Beginning with Interplay Engine v1.2.4, the Interplay backup mechanism consolidates the streamed properties files (all files in the `_PropertyStore` folder) into large “archive” files. These files are written into the `_PropertyStore` folder of the corresponding backup folder. The archive files are named `streamed_propx.bar`, where `x` is replaced with an increasing number starting with 1. The files are about 1 GB each, except for the last one (with the highest suffix number), which can be smaller. The exact file size varies depending on the size of the individual streamed property files, because a single streamed property file is never split up between two `.bar` files. The backup mechanism also writes a file named `streamed_prop.bin` in the same folder. This file contains a directory of all streamed property files contained in the backup and is used only by the BackupArchive tool (see [“Using the BackupArchive Tool to Restore Files” on page 57](#)). The `.bin` file is not required by the InterplayRestore tool.

The InterplayRestore tool is able to work with both the consolidated streamed property files as well as a backup created by an earlier version of the Interplay Engine. The tool looks for the `streamed_prop1.bar` file in the `_PropertyStore` folder of the backup. If this file does not exist, it assumes that the backup was created by an earlier version of the engine and resumes with the restore procedure in the same way as earlier versions of the restore tool. Otherwise, it restores the streamed properties from the consolidated `.bar` files.

### How the Restore Tool Renames Folders

When the tool begins the restore, it locks the database and then renames the existing folder `_Database` to `_Database.1`. If you are performing a restore from a Complete backup, the tool also renames `_PropertyStore` to `_PropertyStore.1`.

If a folder `_Database.1` already exists, the tool creates `_Database.2`, and so on up to `_Database.9`. The tool uses the first free number between 1 and 9 when it renames the `_Database` and `_PropertyStore` folders. If no number is free, you need to delete some of the previously renamed folders so that the tool can run.

If the backup restore is not completed (if you kill the process, if the system crashes, if you get an error message, and so on), you can restore the system to its previous state by deleting the `_Database` folder (and possibly the `_PropertyStore` folder) that the tool created and renaming `_Database.1` to `_Database` (and `_PropertyStore.1` to `_PropertyStore`).

## 2 Database Settings

After you verify that the backup ran successfully and your database is working correctly, you can save storage space by deleting the numbered backup folders ( `_Database.x` and `_PropertyStore.x`) created during the restore process.

### Restoring a Complete Backup or a Fast Backup

To restore a database, you need to restore a Complete backup, a Fast backup, or both, depending on the type of backups available. (see [“Types of Interplay Administrator Backups” on page 37](#) for a description of each type of backup).

- A Complete backup contains a `_Database` folder and a `_PropertyStore` folder. A Complete backup is needed if the complete database needs to be restored, for example, if a hard disk crashes.
- A Fast Incremental Backup and a Fast Differential Backup also contain a `_Database` folder and a `_PropertyStore` folder. If you restore a Differential or Incremental backup, all backups it depends on must be in the same backup location.

The following backups must be in the same folder:

- For a Differential backup, the last Complete backup before the backup you are restoring.
- For an Incremental backup, the last Complete backup and the necessary Incremental or Differential backups between the last Complete backup and the backup you are restoring.

You do not need all backups between the last Complete backup and the backup you are restoring. You need the most recent Complete backup, the most recent Differential backup (if any), and any Incremental backups since the last Complete or Differential backup.

For example, if a sequence of backups looks like this: `c(complete)1 -> i(incremental)1 -> i2 -> d(differential)1 -> i3 -> i4 -> d2 -> i5 -> i6`, to restore `i6` the backups you need in the same folder are `c1`, `d2`, `i5`, and `i6`. You need these files because `i6` contains the changes since `i5`, which contains the changes since `d2`, which contains the changes since `c1`.

Deleted streamed properties remain in the `_PropertyStore` folder until the next Complete backup.


- A Fast Metadata Only backup contains only a `_Database` folder, and can only be run manually. A Fast Metadata Only backup is limited in its usefulness. You can use it to restore the database structure if it becomes corrupted, but it does not restore the contents of the `_PropertyStore` folder. To restore the contents of the `_PropertyStore` folder, you need to restore the most recent Complete backup, Incremental backup, or Differential backup, as described above.

The `InterplayRestore` tool automatically identifies the type of backup that you select.


## Distinguishing Between Types of Backups

To distinguish between a Fast Metadata Only backup and the other types of backups, open the backup folder and check if a `_PropertyStore` folder exists. A Fast Metadata Only backup does not contain a `_PropertyStore` folder.

Fast Metadata Only  
backup folder




Complete,  
Fast Incremental, or  
Fast Differential  
backup folder



To distinguish between Complete, Fast Incremental, and Fast Differential backups, open the backup folder and then open the `inventory.xml` file in Notepad or another text editor. The type of backup is listed, along with other information.

## 2 Database Settings

Fast Incremental  
backup type



```
<?xml version="1.0" encoding="UTF-8"?><Backup
name="AvidwG_2010-11-23_09-25"
destination="//Docwg\WG_Database$\AvidwG\_Backup"
type="increment" to="129349959114473113"
timestamp="129349959617598113" starttimeLocal="23-11-2010
09:26:01" duration="00:00:00" seqno="0">
<DependsOn name="AvidwG_2010-11-21_01-00"
destination="//Docwg\WG_Database$\AvidwG\_Backup"
type="full" timestamp="129347928235727563"
starttimeLocal="21-11-2010 01:00:23" duration="00:00:08"
seqno="0"/>
<DependsOn name="AvidwG_2010-11-23_09-24"
destination="//Docwg\WG_Database$\AvidwG\_Backup"
type="difference" to="129347928235727563"
timestamp="129349959114473113" starttimeLocal="23-11-2010
09:25:11" duration="00:00:00" seqno="0"/>
<DatabaseFiles>
<File>AvidwG.dps</File>
<File>AvidwG.jdf</File>
<File>AvidwG.mor</File>
<File>AvidwG0.mtr</File>
```

### Example of a Complete Restore Process

Imagine that you have a backup schedule of a Complete backup on Saturday and a Fast Differential backup every other day of the week. If there is a failure on Friday in which the \_Database folder, the \_PropertyStore folder, and other Interplay folders are lost or corrupted, you need to perform the following steps:

1. Use the InterplayRestore tool to restore the latest Fast Differential backup (from Thursday).
2. To add metadata missing from the \_PropertyStore folder, check in bins created for projects since the Thursday backup.
3. Use the InterplayRestore tool to restore the \_InternalData folder.
4. Restore the \_Master folder and other folders through whatever mechanism you use for backup.
5. Resynchronize media files with shared storage workspaces. In Interplay Access, right-click the database name and select Resync. For more information, see “Resyncing Media Files with Avid Shared-Storage Workspaces” in the Avid Interplay Access User’s Guide or the Interplay Access Help.

## Using the InterplayRestore Tool on the Interplay Engine Server

To restore a backup, you need to run the InterplayRestore tool in a Command Prompt window. There are two ways to run the tool:

- Without parameters, in which case the tool prompts you for the necessary entries (interactive mode).
- With parameters, in which case the tool runs without prompting, depending on the number of parameters included. You can use these parameters to create a batch file that partially automates the restore process.



*You can use the InterplayRestore tool to restore the AvidAM or the \_InternalData folder. In the following procedure, substitute AvidAM or \_InternalData for AvidWG.*

### To restore an earlier version of a database from a backup using interactive mode:

1. On the Interplay Engine server, click Programs and select Accessories > Command Prompt.
2. At the command line, navigate to the folder that contains InterplayRestore. For example, type:

```
cd C:\Program Files\Avid\Avid Interplay Engine\Server
and press Enter.
```

3. Type:

```
InterplayRestore
and press Enter.
```

4. InterplayRestore prompts you for the database root directory. Type the path and press Enter.

You can use a local path or a UNC path. For example:

```
D:\Workgroup_Databases\AvidWG
\\IEServer\WG_Database$\AvidWG
```

You can use the administrative share name WG\_Database\$ only in a UNC path.

5. The next prompt asks if you are restoring a split database configuration.

If you answer yes, the next prompt asks you to enter the Interplay database asset path, which is the path to the AvidWG folder on shared storage. Enter a UNC path, for example:

```
\\SharedStorageServer\WorkspaceName\AvidWG\
```

6. At the next prompt, type the backup home directory and press Enter. For example:

```
D:\Workgroup_Databases\AvidWG\_Backup
```

## 2 Database Settings

If you are working with a split database, this location is probably on the shared storage server. For example:

```
\\SharedStorageServer\WorkspaceName\AvidWG\_Backup
```

7. At the next prompt, select the correct backup from the numbered list of available backups. Complete backups are labeled “full” and Fast backups are labeled “increment” “difference,” or “metadataonly.” After you select the backup, press Enter.

The restore process begins. For an example of the process, see [“Database Restore Session Example” on page 56](#). At the end of the process, a message informs you that you need to restore the \_Master directory manually.

8. Restore your \_Master folder through whatever mechanism you use for backup.



*The \_Master database is not backed up by the automated backup feature of Interplay. See [“Recommendations for Backup Configuration” on page 38](#).*

9. Unlock the database by using the Lock/Unlock Database view in the Interplay Administrator.
10. Check to make sure you can access the restored database from Interplay Access, and that you can preview clip headframes.
11. Delete the \_Database.1 and \_PropertyStore.1 directories, or whatever numbered backup directories were created through the restore process. See [“Restoring an Earlier Version of a Database” on page 48](#).

**To restore an earlier version of a database from a backup by passing parameters to the tool, do one of the following:**

- ▶ For a non-split database, navigate to the folder that holds InterplayRestore, type the following, and press Enter:

```
InterplayRestore /m <database metadata root dir>  
/backupdir <database backup dir>
```

For example:

```
InterplayRestore /m d:\Workgroup_Databases\AvidWG  
/backupdir d:\Workgroup_Databases\AvidWG\_Backup
```

InterplayRestore prompts you to choose from a numbered list of available backups and then restores the earlier version. Continue with steps 8 through 11 above.



*The parameter /m is a short version of the parameter /metadata. You can view information on the complete syntax for the tool by entering `InterplayRestore /help`.*



*Because the paths for the /metadata and /backupdir parameters are unlikely to change, you can create a batch file that includes these values, as in the previous example. To restore the database, run the batch file and select the number of the backup you want to restore.*

- ▶ For a split database, navigate to the folder that holds InterplayRestore, type the following, and press Enter:

```
InterplayRestore /m <database metadata root dir>
/assets <split database asset directory>
/backupdir <database backup dir>
```

For example:

```
InterplayRestore /m d:\Workgroup_Databases\AvidWG
/assets \\isis\workspace1\AvidWG
/backupdir \\isis\workspace1\AvidWG\_Backup
```

InterplayRestore prompts you to choose from a numbered list of available backups and then restores the earlier version. Continue with steps 8 through 11 above.



*Because the paths for the /metadata, /assets, and /backupdir parameters are unlikely to change, you can create a batch file that includes these values, as in the previous example. To restore the database, run the batch file and select the number of the backup you want to restore.*

- ▶ If you know the specific backup you want to restore, navigate to the folder that holds InterplayRestore, type the following, and press Enter:

```
InterplayRestore /m <database metadata root dir> /backupdir <database
backup dir> /backuptorestore <backup folder for restore>
```

For example:

```
InterplayRestore /m d:\Workgroup_Databases\AvidWG
/backupdir d:\Workgroup_Databases\AvidWG\_Backup /backuptorestore
d:\Workgroup_Databases\AvidWG\_Backup\AvidWG_2007-08-20_01-00
```

InterplayRestore restores the earlier version. Continue with steps 8 through 11 above.

## 2 Database Settings

### Database Restore Session Example

The following is an example of an interactive session, which begins with the command for starting the InterplayRestore tool.

```
C:\>"C:\Program Files\Avid\Avid Interplay  
Engine\Server\InterplayRestore"
```

```
*****
```

```
InterplayRestore - Restore Interplay databases from backup
```

```
A non interactive mode is also available.
```

```
Run "InterplayRestore.exe /?" for help
```

```
Enter the Interplay database root or metadata directory:
```

```
D:\Workgroup_Databases\AvidWG
```

```
Is this a split database configuration? <y/n> y
```

```
Enter the Interplay database asset path: \\isis\workspace1\AvidWG
```

```
Enter the backup root directory: \\isis\workspace1\AvidWG\_Backup
```

```
Choose a backup to restore from:
```

```
[1]    Tuesday, June 10, 2010 3:05:00 AM  full
```

```
[2]    Thursday, June 12, 2010 3:04:00 AM  increment
```

```
[3]    Friday, June 13, 2010 3:05:00 AM   full
```

```
[4]    Saturday, June 14, 2010 3:00:00 AM full
```

```
Choose an entry ( 1 - 4 ):
```



Assume you choose 1. The tool locks the project so that no one can access the database and then copies the files:

```
Beginning restore from
\\isis\workspace1\avidwg\_Backup\AvidWG_2010-06-10_03-05\
```

```
This is a Full backup
```

```
Restoring split database. Metadata restored to
d:\Workgroup_Databases\avidwg\. PropertyStore Assets restored to
\\isis\workspace1\avidwg
```

```
Locked project AvidWG
```

```
Copying files into d:\Workgroup_Databases\avidwg\_Database
```

```
Copying file AvidWG.dor
```

```
...
```

It leaves the database locked and gives you the following message:

```
Database AvidWG is still locked because you need to restore _Master
manually, or through your existing tape backup mechanism.
```

When you are done restoring `_Master`, use the Lock/Unlock Database view in Interplay Administrator to unlock the AvidWG database. This will complete your restore operation.


## Using the BackupArchive Tool to Restore Files

The BackupArchive tool is a command-line program that lets you work with files contained in the `_PropertyStore` folder contained in a database backup. The `_PropertyStore` folder holds streamed properties, which are files that include metadata about Avid assets, such as headframes and AAF information. The streamed property files are backed up (as an archive) in one or more `.bar` files in the `_PropertyStore` backup folder. For more information about `.bar` files, see [“Restoring an Earlier Version of a Database” on page 48](#).

You can use the BackupArchive tool to display a list of all streamed properties files in the `_PropertyStore` backup folder. You can also use it in an emergency situation in which the online database is missing and the backup file is corrupt. In this case, you would use the tool to extract as many files as possible from the corrupt backup. It is not a replacement for the InterplayRestore tool.

For example, the following illustration shows the contents of the 0-1999 subfolder in the active `_PropertyStore` folder on the Interplay Engine:


## 2 Database Settings



D:\Workgroup\_Databases\AvidWG\PropertyStore\0-1999

Name	Size	Type	Date Modified	Attributes
1169_StreamedProperty_UserSettings.Global1073742992-2.prp	6 KB	PRP File	4/7/2008 9:31 AM	
1169_StreamedProperty_UserSettings.Server1073742992-2.prp	1 KB	PRP File	4/7/2008 9:31 AM	
1186_StreamedProperty_UserSettings.Global1073743009-30.prp	2 KB	PRP File	4/30/2008 9:48 AM	
1186_StreamedProperty_UserSettings.Server1073743009-29.prp	2 KB	PRP File	4/30/2008 9:48 AM	
1209_StreamedProperty_AAfBinary1073743032-1.prp	49 KB	PRP File	11/14/2007 4:57 PM	A
1209_StreamedProperty_Screenshot1073743032-1.prp	8 KB	PRP File	11/14/2007 4:57 PM	A
1249_StreamedProperty_AAfBinary1073743072-2.prp	49 KB	PRP File	3/7/2008 11:16 AM	
1249_StreamedProperty_Screenshot1073743072-2.prp	6 KB	PRP File	3/7/2008 11:16 AM	

The following illustration shows the corresponding files as they appear in the archive file \AvidWG\\_Backup\AvidWG\_2008-05-04\_01-00\_PropertyStore\streamed\_prop1.bar:



```
C:\Program Files\Avid\Interplay Engine\Server>backuparchive /L \\docisis\workspace3\AvidWG\_B
propertyStore\streamed_prop1
Listing files matching *.* from \\docisis\workspace3\AvidWG\_Backup\AvidWG_2008-05-04_01-00_Prop
\0-1999\1169_StreamedProperty_UserSettings.Global1073742992-2.prp 6 KB streamed_prop1.bar
\0-1999\1169_StreamedProperty_UserSettings.Server1073742992-2.prp 1 KB streamed_prop1.bar
\0-1999\1186_StreamedProperty_UserSettings.Global1073743009-30.prp 2 KB streamed_prop1.bar
\0-1999\1186_StreamedProperty_UserSettings.Server1073743009-29.prp 2 KB streamed_prop1.bar
\0-1999\1209_StreamedProperty_AAfBinary1073743032-1.prp 49 KB streamed_prop1.bar
\0-1999\1209_StreamedProperty_Screenshot1073743032-1.prp 8 KB streamed_prop1.bar
\0-1999\1249_StreamedProperty_AAfBinary1073743072-2.prp 49 KB streamed_prop1.bar
\0-1999\1249_StreamedProperty_Screenshot1073743072-2.prp 6 KB streamed_prop1.bar
\0-1999\1263_StreamedProperty_AAfBinary1073743086-2.prp 50 KB streamed_prop1.bar
```

The .bar file is a file that you can only open by using the BackupArchive tool.



*In previous versions of Interplay, you could use Windows Explorer to view and work with the streamed properties files in the \_PropertyStore backup folder. Because the current backup mechanism uses archive files, you need this tool to view and work with files in the \_PropertyStore backup folder.*

The following procedures describe how to view a list of streamed properties, how to unpack an archive, and how to extract specific files. If you need to restore the streamed properties to a database in an emergency situation, contact Avid support.

The complete syntax for using the BackupArchive tool is provided in the in-line help, which you can display by typing BackupArchive in a Command Prompt window.

### To list all streamed properties files in an archive file:

1. On the Interplay Engine, click Programs and select Accessories > Command Prompt.
2. At the command line, navigate to the folder that contains the BackupArchive tool.

For example, type the following and press Enter:

```
cd C:\Program Files\Avid\Avid Interplay Engine\Server
```

3. Type the following and press Enter:

```
backuparchive /L <archive>
```

Do not use the file extension when typing the name of the archive file. For example,

```
backuparchive /L
\\docisis\workspace3\AvidWG\_Backup\AvidWG_2008-05-04_01-00\_PropertyStore\streamed_prop
```

Make sure to type the command on a single line.



*To direct the output of this command to a text file for easier review, add > textfile.txt to the end of the command.*

#### **To unpack all streamed properties files:**

- ▶ Type the following and press Enter:

```
backuparchive /U <archive> <destination folder>
```

Do not use the file extension when typing the name of the archive file. For example, the following command unpacks all property store files into a temporary folder on the Interplay Engine:

```
backuparchive /U
\\docisis\workspace3\AvidWG\_Backup\AvidWG_2008-05-04_01-00\_PropertyStore\streamed_prop D:\Workgroup_Databases\TempPropertyStore
```

Make sure to type the command on a single line.

#### **To extract and restore specific streamed properties files:**

- ▶ Type the following and press Enter:

```
backuparchive /E /P:<pattern> <archive> <destination folder>
```

Do not use the file extension when typing the name of the archive file. To define a pattern, you can use the standard Windows syntax. For example, the following command extracts all files whose names include Scr (screenshots) into a temporary folder on the Interplay Engine:

```
backuparchive /E /P:*Scr*
\\docisis\workspace3\AvidWG\_Backup\AvidWG_2008-05-04_01-00\_PropertyStore\streamed_prop
D:\Workgroup_Databases\TempPropertyStoreScreenshots
```

Make sure to type the command on a single line.

### Restoring Archived Log Files

In Interplay version 1.6 and later, the Interplay Engine compresses and archives log files older than 7 days. The log compression process runs during project backup. (This process runs at most once per day, even if multiple backups are scheduled on the same day.) Archive files (with the extensions .bar and .bin) are stored in the same directory as the log files for 30 days and then are automatically deleted. You can extract the compressed log files from an archive by using the BackupArchive tool described in [“Using the BackupArchive Tool to Restore Files”](#) on page 57.

## Performing a Consistency Check

The database Consistency Check compares the version of the database or databases on the master directory with the current database file. The Perform Consistency Check view provides a useful tool for checking if all references are correct, seeing if all necessary files are on the disk, and checking other aspects of the database.



**The Consistency Check is for support purposes. You should perform this check only if requested by Avid Technical Support.**

## Viewing Database Information

Use the Database Information view to display information about an Interplay database, including information about the size of the database and the connected users.

The Database Object Statistics section lists total objects for the entire Interplay database, as well as totals for the most common object types. You can use this data to monitor the size of the Interplay database. Currently the Interplay database supports up to 5 million objects (see [“Limits on the Number of Assets and Objects in the Interplay Database”](#) on page 36). Make sure that you have an effective deletion workflow in place to keep the total number of objects from growing too fast.



*Database Object Statistics are displayed only for servers that are running Interplay Engine version 1.6 or later.*

#### **To view the information about a database:**

1. In the Database section of the Interplay Administrator window, click the Database Information icon.

The Database Information view opens.

The screenshot shows the Avid Interplay Administrator window. The main content area is divided into three sections:

**Database Information**

Name: AvidWG  
 Description:   
 Root folder for database (Meta Data): \\Zumo\WG\_Database\$\AvidWG\\_Database\  
 Root folder for data (Assets): \\Zumo\WG\_Database\$\AvidWG

**Database Object Statistics**

Total number of database objects: 30195

Database Object Type	#
masterclip	717
sequence	95
subclip	214
renderedeffect	409
filemob	1544
avid_asset	3391
folder	1865
user	69
other objects	21891

**Connected User Information**

Database	User Name	Connected From	Connected Since	License Class
AvidWG	administrator	mun-leuchtbake	Jan 16, 2009 4:54:09 PM	KEY-M
AvidWG	Administrator	mun-zumo	Jan 16, 2009 5:19:27 PM	KEY-A
AvidWG	Administrator	mun-zumo	Jan 16, 2009 4:56:53 PM	KEY-A

Refresh

## 2. Select the database name from the list.

A summary of information about the database is displayed:

- Name and description: Either AvidWG (Interplay Engine) or AvidAM (Interplay Archive Engine) with a description supplied when the database was first created.
- Root folder for database (Meta Data): See [“Creating an Interplay Database” on page 31](#).
- Root folder for data (Assets): See [“Creating an Interplay Database” on page 31](#).
- Database Object Statistics: See the introduction to this topic.
- Connected User Information: Users currently connected to the Interplay Engine. The License Class column lists the license keys that are used internally by the Interplay Engine. For information about user licenses, see [“Managing Licenses” on page 86](#).


## Locking and Unlocking Databases

Use the Lock/Unlock Databases view to prevent users from connecting to the database. You might need to lock the database if you are upgrading the database or using an archive tool to create a backup of the database. By default, the database is unlocked.

### To lock a database:

1. In the Database section of the Interplay Administrator window, click the Lock/Unlock Database icon.

The Lock/Unlock database view opens.



2. Select the database in the Unlocked Databases list.
3. (Option) Type a Lock comment explaining why you are locking the database. This information appears in the Locked Database Information area for the database.
4. Click Lock Database.

Your user ID and the time at which you locked the database are filled in, and the database is displayed in Locked Databases.

**To unlock a database:**

1. Select the database in the Locked Databases list.
2. Click Unlock Database.

The database is displayed in Unlocked Databases.

## Managing Databases: Deactivating, Activating, and Migrating

Use the Managing Databases view to remove a database from the list of active databases (deactivate) or to restore it to the list (activate). This view also lets you migrate a database to a new Central Configuration Server (CCS) when necessary.

The following topics provide more information about activating, deactivating, and migrating databases:

- [Deactivating a Database](#)
- [Activating a Deactivated Database](#)
- [Migrating a Database](#)

### Deactivating a Database

You might want to prevent users from connecting to a database if the database has been “retired” and the files have been moved elsewhere. In other cases, such as when you are backing up or moving databases, you might need to ensure that no connections can be made to the database to avoid interference. Deactivating the database removes it from the list of active databases.




**Deactivating a database does not delete the database files. It makes the database inactive so that users cannot connect to it until it is activated again. The database data is kept at the location that was specified when the database was created.**

**To deactivate a database:**

1. In the Database section of the Interplay Administrator window, click the Manage Databases icon.

The Manage Databases view opens.

## 2 Database Settings



2. Select the database name in the Databases list.
3. Click Deactivate.

The database name is removed from the Databases list.

### Activating a Deactivated Database

If a specific database is not listed in the Databases view, it means that it is unknown to the Interplay Engine and users cannot connect to it. If the database exists but is not listed, it is probably deactivated. You activate a database by navigating to the database .pro file (AvidWG.pro or AvidAM.pro). This file is located in one of two folders:

- For a standard database, the .pro file is located in the Workgroup\_Databases folder, represented by the administrative share name WG\_Database\$ (see [“Creating an Interplay Database” on page 31](#)).
- For a split database, the .pro file is located in the Avid\_WG folder on the shared storage workspace (see [“Preparing for a Split Database” on page 212](#)).



**To add an existing but inactive database to the list of active databases:**

1. In the Database section of the Interplay Administrator window, click the Manage Databases icon.

The Manage Databases view opens.


2. Do one of the following:

- ▶ In the “Database (.pro) file to activate” text box, type the full UNC path to the .pro file. For example:

```
\\IEServer\WG_Database$\AvidWG\AvidWG.pro
```

- ▶ Click the Browse button, log in if prompted, navigate to the .pro file using a network, select the file, and click Open.

The following illustration shows the path to AvidWG.pro, using the Microsoft Windows smb network and the administrative share WG\_Database\$.




*Avid recommends keeping the default share name WG\_Database\$. If you decide on a different share name, consider that if the name is longer than 12 characters, you cannot browse to it graphically. If a share name is longer than 12 characters, you need to type the complete path in the “Database (.pro) file to activate” text box.*


Make sure to navigate through a network to select the file (for example, do not navigate through a mapped network drive). You must use a UNC path.

## 2 Database Settings

Navigating through a network is also required if you are working with a split database. In this case, the .pro file is located on the shared storage server. The following illustration shows the path to AvidWG.pro, using an Avid ISIS network and the workspace where the AvidWG folder is stored. In an Avid Unity MediaNetwork, the network name is “Avid Unity Network.”



The .pro file is displayed in the Activate Database dialog box.



3. Make sure the option “Load Database on Activation” is selected. Deselect this option only if directed by Avid support.
4. Click Activate.

The database is activated and loaded. The database name is displayed in the Databases list and users can connect to the database. If the option “Load Database on Activation” is selected, the database is automatically unlocked.

## Migrating a Database

You usually need to perform a database migration under the following circumstances:

- When you want to remove all users and group-related data from a database. This allows you to start with new users and groups and maintain the metadata and the data inside the database.
- When you are troubleshooting a problem with customer support. For example, customer support might ask you to provide a copy of your database.
- If you changed the Central Configuration Server (CCS) for a database without first moving the \_InternalData folder. If a database needs to be migrated, the State reads “Database Requires Migration.”

## 2 Database Settings

Do not use a database that requires migration; always migrate a database to a CCS. You cannot administer an unmigrated database.

If a database needs migration, the database icon shows a red box with an X and a yellow arrow. The database icon appears in several views in the Interplay Administrator, including the Manage Database Roles view.



(Red box with X and yellow arrow) Database needs migration.

---



**When you migrate a database, the system deletes all the information inside the database that was stored from the old CCS, including users, user settings and local administration settings.**




**If you plan to migrate an Interplay Engine or Interplay Archive Engine database, turn off the database backup process before you perform the migration. If you do not turn off the backup process and it coincides with the migration, your backup will write out an inconsistent state of the database (half current and half migrated).**

### **To migrate a database to a new CCS:**

1. In the Database section of the Interplay Administrator window, click the Manage Databases icon.

The Manage Databases view opens.



2. In the Manage Databases view, click the name of the database that needs migration. The State reads “Database Requires Migration.”

A warning explains the consequences of a database migration.

3. Click Migrate Database.

After the migration, the State reads “OK.” The database now has the CCS users and administration properties of the new CCS you have set.

## Moving a Database to Another Server (Non-Clustered Systems)

Under special circumstances, you might need to move a database to a different server.

The following procedure refers to Interplay Engine servers that are not configured as failover clusters. For clustered systems, see [“Moving a Database to Another Server \(Clustered Systems\)”](#) on page 73.



**Avid recommends that you have telephone support from Avid during the process in case complications arise.**



If you move a database to a server that points to a different CCS, all the old CCS information that was stored, including users, user settings, and local administration settings for the database, will be lost because you will have to migrate the database (see [“Migrating a Database” on page 67](#)). If you move a database to another server and also move the CCS, however, this information is preserved. To move both a database and a CCS, see [“Moving a Database and Users to Another Server \(Non-Clustered Systems\)” on page 71](#).

### To move a database to another server (non-clustered systems):

1. Install the Interplay Engine on a new server (the target server).

Make sure the configuration is the same on both systems. For example, if you are moving an AvidWG database, create an AvidWG database on the new server. If the original system uses a split database, the new system should also use a split database (see [“Configuring Interplay for a Split Database” on page 209](#)).

2. On the source server, lock the database by using the Lock/Unlock Database view (see [“Locking and Unlocking Databases” on page 62](#)).

All clients are disconnected from the source server.

3. Deactivate the database by using the Manage Databases view (see [“Deactivating a Database” on page 63](#)).

4. Make sure the database is unloaded from the server by opening the Restart Server view and clicking Restart.

5. Locate the database folder on the source server.

The default path is `\\server_name\WG_Database$\AvidWG` (or AvidAM for an Archive Manager). By default, the administrative share `WG_Database$` refers to `D:\Workgroup_Databases`. For more information, see [“Identifying the Root Folder of the Interplay Server Database” on page 220](#).

6. Pack the database folder into a zip file or use Robocopy from the Microsoft Windows Resource Kit for path names longer than 256 characters.

To save time and storage, you do not need to copy all the backups in the `D:\Workgroup_Databases\AvidWG\_Backup` folder. One complete backup and the most recent Fast backup are sufficient.

If you are moving a split database, create two zip files, one for `D:\Workgroup_Databases\AvidWG` and the other for `\\server_name\workspace_name\AvidWG`.

7. Copy the zipped file or files to a network server, removable media, laptop, or directly to the target server.

8. Open the Interplay Administrator, log on to the target server, and deactivate the database (AvidWG or AvidAM) if one is active, using the Manage Databases View.

9. On the target server, rename the existing database folder, for example, rename AvidWG to AvidWG\_old.
10. If you are copying a non-split database, copy the zipped file to the target server and unzip the file to the Workgroup\_Databases folder. Make sure the path on the target server matches the path on the source server.  
  
If you are copying a split database, copy and unzip both zipped files to the correct locations. Then edit the FolderLocations.xml file to show the correct paths. See [“Splitting a Database for Existing Interplay Installations” on page 215](#).
11. Activate the database by using the Manage Databases view (see [“Activating a Deactivated Database” on page 64](#)).
12. On an Interplay Access client, log in to the new server and verify that all data is available.  
  
If all data is available, the new database is ready for use.  
  
If necessary, remove the old database from Interplay Access by right-clicking the database name and then clicking Remove Databases.
13. (Option) On the source server, rename the original database folder to avoid unwanted future access.

## Moving a Database and Users to Another Server (Non-Clustered Systems)

Under special circumstances, you might need to move a database and users to a different server.

The following procedure refers to Interplay Engine servers that are not configured as failover clusters. For cluster systems, see [“Moving a Database and Users to Another Server \(Clustered Systems\)” on page 76](#).



**Avid recommends that you have telephone support from Avid during the process in case complications arise.**



**If you move a database to a server that points to a different CCS, all the old CCS information that was stored, including users, user settings, and local administration settings for the database, will be lost because you will have to migrate the database (see [“Migrating a Database” on page 67](#)). If you move a database to another server and also move the CCS, however, this information is preserved. To move both a database and a CCS, use this procedure. For more information about a CCS, see [“Understanding the Central Configuration Server” on page 93](#).**

## 2 Database Settings

### To move a database and users to another server (non-clustered systems):

1. Install the Interplay Engine on a new server (the target server).

Make sure the configuration is the same on both systems. For example, if you are moving an AvidWG database, create an AvidWG database on the new server. If the original system uses a split database, the new system should also use a split database (see [“Configuring Interplay for a Split Database” on page 209](#)).
2. On the source server, lock the database by using the Lock/Unlock Database view (see [“Locking and Unlocking Databases” on page 62](#)).
3. Deactivate the database by using the Manage Databases view (see [“Deactivating a Database” on page 63](#)).
4. Make sure the database is unloaded from the server by opening the Restart Server view and clicking Restart.
5. Lock the server using the Lock Server view (see [“Locking and Unlocking the Server” on page 84](#)).
6. Locate the database folder on the source server.

The default path is `\\server_name\WG_Database$\AvidWG` (or `AvidAM` for an Archive Manager). By default, the administrative share `WG_Database$` refers to `D:\Workgroup_Databases`. For more information, see [“Identifying the Root Folder of the Interplay Server Database” on page 220](#).
7. Pack the database folder into a zip file or use Robocopy from the Microsoft Windows Resource Kit for path names longer than 256 characters.

To save time and storage, you do not need to copy all the backups in the `D:\Workgroup_Databases\AvidWG\Backup` folder. One complete backup and the most recent Fast backup are sufficient.

If you are moving a split database, create two zip files, one for `D:\Workgroup_Databases\AvidWG` and the other for `\\server_name\workspace_name\AvidWG`.
8. Locate the user folder `_InternalData` on the source server.

The default path is `D:\Workgroup_Databases\_InternalData`.
9. Copy the zipped file or files and the `_InternalData` folder to a network server, removable media, laptop, or directly to the target server.
10. Open the Interplay Administrator, log in to the target server, and deactivate the database (AvidWG or AvidAM) using the Manage Databases View.
11. On the target server, rename the existing database folder, for example, rename `AvidWG` to `AvidWG_old`.
12. Make sure all databases are unloaded from the server by opening the Restart Server view and clicking Restart.



13. Lock the server by using the Lock Server view (see [“Locking and Unlocking the Server” on page 84](#)).
14. Rename the existing \_InternalData folder to \_InternalData\_old.
15. If you are copying a non-split database, copy the zipped file to the target server and unzip the file to the Workgroup\_Databases folder. Copy the \_InternalData folder to the Workgroup\_Databases folder. Make sure the path on the target server matches the path on the source server.  
  
If you are copying a split database, copy and unzip both zipped files to the correct locations. Then edit the FolderLocations.xml file to show the correct paths. See [“Splitting a Database for Existing Interplay Installations” on page 215](#). Copy the \_InternalData folder to the Workgroup\_Databases folder.
16. Unlock the server using the Lock Server view.
17. Verify that all users are on the system by opening the User Management view and viewing the lists of user groups.
18. Activate the database by using the Manage Databases view (see [“Activating a Deactivated Database” on page 64](#)).
19. On an Interplay Access client, log in to the new server and verify that all data is available.  
  
If all data is available, the new database is ready for use.  
  
If necessary, remove the old database from Interplay Access by right-clicking the database name and then clicking Remove Databases.
20. (Option) On the source server, rename the original database folder to avoid unwanted future access.

## Moving a Database to Another Server (Clustered Systems)

Under special circumstances, you might need to move a database to a different server.

The following procedure refers to Interplay Engine servers that are configured as failover clusters. For non-clustered systems, see [“Moving a Database to Another Server \(Non-Clustered Systems\)” on page 69](#).



**Avid recommends that you have telephone support from Avid during the process in case complications arise.**

## 2 Database Settings



If you move a database to a server that points to a different CCS, all the old CCS information that was stored, including users, user settings, and local administration settings for the database, will be lost because you will have to migrate the database (see [“Migrating a Database” on page 67](#)). If you move a database to another server and also move the CCS, however, this information is preserved. To move both a database and a CCS, see [“Moving a Database and Users to Another Server \(Clustered Systems\)” on page 76](#).

### To move a database to another server (clustered systems):

1. Install the Interplay Engine on a new server (the target server).  
Make sure the configuration is the same on both systems. For example, if you are moving an AvidWG database, create an AvidWG database on the new server. If the original system uses a split database, the new system should also use a split database (see [“Configuring Interplay for a Split Database” on page 209](#)).
2. On the source server, lock the database by using the Lock/Unlock Database view (see [“Locking and Unlocking Databases” on page 62](#)).  
All clients are disconnected from the source server.
3. Deactivate the database using the Manage Databases view (see [“Deactivating a Database” on page 63](#)).
4. Make sure the database is unloaded by using the Cluster Administrator on one of the cluster nodes:
  - a. Select Programs > Administrative Tools > Cluster Administrator.
  - b. Open the Avid Workgroup Server resource group.
  - c. In the list of resources, select Avid Workgroup Engine Monitor and change the state to “Offline.”



**Make sure that you change the state to offline for the Avid Workgroup Engine Monitor resource only, not the entire Avid Workgroup Server group.**

- d. Close the Cluster Administrator.
5. Locate the database folder on the active node of the source server.  
The default path is `\\virtual_cluster_name\WG_Database$\AvidWG` (or AvidAM for an Archive Manager). By default, the administrative share WG\_Database\$ refers to S:\Workgroup\_Databases. For more information, see [“Identifying the Root Folder of the Interplay Server Database” on page 220](#).



*If the S drive is not available on the machine, either this is the offline node or the entire Avid Workgroup Server group was taken offline instead of only the resource.*

6. Pack the database folder into a zip file or use Robocopy from the Microsoft Windows Resource Kit for path names longer than 256 characters.

To save time and storage, you do not need to copy all the backups in the S:\Workgroup\_Databases\AvidWG\\_Backup folder. One complete backup and the most recent Fast backup are sufficient.

If you are moving a split database, create two zip files, one for S:\Workgroup\_Databases\AvidWG and the other for \\server\_name\workspace\_name\AvidWG.

7. Copy the zipped file or files to a network server, removable media, a laptop, or directly to the target server.
8. Open the Interplay Administrator, log on to the target server, and deactivate the database (AvidWG or AvidAM) using the Manage Databases View.
9. On the target server, rename the existing database folder, for example, rename AvidWG to AvidWG\_old.
10. If you are copying a non-split database, copy the zipped file to the target server and unzip the file to the Workgroup\_Databases folder. Make sure the path on the target server matches the path on the source server.

If you are copying a split database, copy and unzip both zipped files to the correct locations. Then edit the FolderLocations.xml file to show the correct paths. See [“Splitting a Database for Existing Interplay Installations” on page 215](#).

11. Activate the database by using the Manage Databases view (see [“Activating a Deactivated Database” on page 64](#)).
12. On an Interplay Access client, log in to the new server and verify that all data is available.

If all data is available, the new database is ready for use.

If necessary, remove the old database from Interplay Access by right-clicking the database name and then clicking Remove Databases.

13. (Option) On the source server, rename the original database folder to avoid unwanted future access.

Use the Cluster Administrator to bring the source server back online. Right-click the Avid Workgroup Server group (not the resource) and select Bring Online.

# Moving a Database and Users to Another Server (Clustered Systems)

Under special circumstances, you might need to move a database and users to a different server.

The following procedure refers to Interplay Engine servers that are configured as failover clusters. For non-clustered systems, see [“Moving a Database and Users to Another Server \(Non-Clustered Systems\)”](#) on page 71.



**Avid recommends that you have telephone support from Avid during the process in case complications arise.**



**If you move a database to a server that points to a different CCS, all the old CCS information that was stored, including users, user settings, and local administration settings for the database, will be lost because you will have to migrate the database (see [“Migrating a Database”](#) on page 67). If you move a database to another server and also move the CCS, however, this information is preserved. To move both a database and a CCS, use this procedure. For more information about a CCS, see [“Understanding the Central Configuration Server”](#) on page 93.**

### **To move a database and users to another server (clustered systems):**

1. Install the Interplay Engine on a new server (the target server).  
Make sure the configuration is the same on both systems. For example, if you are moving an AvidWG database, create an AvidWG database on the new server. If the original system uses a split database, the new system should also use a split database (see [“Configuring Interplay for a Split Database”](#) on page 209).
2. On the source server, lock the database by using the Lock/Unlock Database view (see [“Locking and Unlocking Databases”](#) on page 62).  
All clients are disconnected from the source server.
3. Deactivate the database using the Manage Databases view (see [“Deactivating a Database”](#) on page 63).
4. Lock the server using the Lock Server view (see [“Locking and Unlocking the Server”](#) on page 84).
5. Make sure the database is unloaded by using the Cluster Administrator on one of the cluster nodes:
  - a. Select Programs > Administrative Tools > Cluster Administrator.
  - b. Open the Avid Workgroup Server resource group.

- c. In the list of resources, select Avid Workgroup Engine Monitor and change the state to “Offline.”



**Make sure that you change the state to offline for the Avid Workgroup Engine Monitor resource only, not the entire Avid Workgroup Server group.**

- d. Close the Cluster Administrator.
6. Locate the database folder on the source server.

The default path is `\\virtual_cluster_name\WG_Database$\AvidWG` (or AvidAM for an Archive Manager). By default, the administrative share `WG_Database$` refers to `S:\Workgroup_Databases`. For more information, see [“Identifying the Root Folder of the Interplay Server Database”](#) on page 220.



*If the S drive is not available on the machine, either this is the offline node or the entire Avid Workgroup Server group was taken offline instead of only the resource.*

7. Pack the database folder into a zip file or use Robocopy from the Microsoft Windows Resource Kit for path names longer than 256 characters.  
To save time and storage, you do not need to copy all the backups in the `S:\Workgroup_Databases\AvidWG\_Backup` folder. One complete backup and the most recent Fast backup are sufficient.  
If you are moving a split database, create two zip files, one for `S:\Workgroup_Databases\AvidWG` and the other for `\\server_name\workspace_name\AvidWG`.
8. Locate the user folder `_InternalData` on the source server.  
The default path is `S:\Workgroup_Databases\_InternalData`.
9. Copy the zipped file and the `_InternalData` folder to a network server, removable media, laptop, or directly to the target server.
10. On the target server, rename the existing database folder, for example, rename `AvidWG` to `AvidWG_old`.
11. Open the Interplay Administrator, log on to the target server, and deactivate the database (AvidWG or AvidAM) using the Manage Databases View.
12. Lock the server using the Lock Server view (see [“Locking and Unlocking the Server”](#) on page 84).
13. Rename the existing `_InternalData` folder to `_InternalData_old`.
14. If you are copying a non-split database, copy the zipped file to the target server and unzip the file to the `Workgroup_Databases` folder. Copy the `_InternalData` folder to the `Workgroup_Databases` folder. Make sure the path on the target server matches the path on the source server.

## 2 Database Settings

If you are copying a split database, copy and unzip both zipped files to the correct locations. Then edit the FolderLocations.xml file to show the correct paths. See [“Splitting a Database for Existing Interplay Installations” on page 215](#). Copy the \_InternalData folder to the Workgroup\_Databases folder.

15. Unlock the server using the Lock Server view.
16. Verify that all users are on the system by opening the User Management view and viewing the lists of user groups.
17. Activate the database by using the Manage Databases view (see [“Activating a Deactivated Database” on page 64](#)).
18. On an Interplay Access client, log in to the new server and verify that all data is available.

If all data is available, the new database is ready for use.

If necessary, remove the old database from Interplay Access by right-clicking the database name and then clicking Remove Databases.

19. (Option) On the source server, rename the original database folder to avoid unwanted future access.

Use the Cluster Administrator to bring the source server back online. Right-click the Avid Workgroup Server group (not the resource) and select Bring Online.

## Moving a Database Under Low Disk Space Conditions

If disk space on the server is critically low, the Interplay Engine refuses client connections and displays an error message. In this situation, the administrator cannot log in and shut down the server, and move a database by normal means (as described in [“Moving a Database to Another Server \(Non-Clustered Systems\)” on page 69](#) and [“Moving a Database and Users to Another Server \(Non-Clustered Systems\)” on page 71](#)). In the Server installation directory (by default, C:\Program Files\Avid\Avid Interplay Engine\Server), there are tools provided to solve such problems:

- NxNServerLock.exe
- NxNServerUnlock.exe
- NxNServerShutdown.exe



**Before beginning this procedure, be sure to make a backup of the database. See [“Creating and Restoring Database Backups” on page 36](#) for information on running a backup. Temporarily change the Backup time field to “Once at” and enter or select from the list the time in the future closest to the current time.**

**To move a database under low disk space conditions:**

1. Lock the server using NxNServerLock.exe.
2. Shut down the server using NxNServerShutdown.exe, if necessary.
3. Move the database folder (AvidWG or AvidAM) to another drive or free up some disk space.
4. Unlock the server by doing one of the following:
  - ▶ Use the Interplay Administrator's Lock Server view (see [“Locking and Unlocking the Server” on page 84](#)).
  - ▶ Use NxNServerUnlock.exe.
5. Deactivate the moved database using the Manage Databases view (see [“Deactivating a Database” on page 63](#)).
6. Activate the moved database in the correct location using the Manage Databases view (see [“Activating a Deactivated Database” on page 64](#)).

## Renaming a Database

Under some circumstances you might need to rename a database. For example, if you need to create a new database with the same name, you can rename the original database. You can keep the original database as an archive for searching.



**Before beginning this procedure, be sure to make a backup of the database. See [“Creating and Restoring Database Backups” on page 36](#) for information on running a backup. Temporarily change the Backup time field to “Once at” and enter or select from the list the time in the future closest to the current time.**

**To rename a database:**

1. In the Database section of the Interplay Administrator window, click the Manage Databases icon.  
The Manage Databases view opens.
2. Select the database and click the Deactivate Database button to ensure that the database is not in use.

## 2 Database Settings

3. On the server or at the database location, use the Windows desktop to rename the database folder, .pro file, and .nif directory, and all files within the \_Database folder, that is, replace the old <DatabaseName> with the new name for all files fitting the following mask:

<DatabaseName>\<DatabaseName>.pro

<DatabaseName>\<DatabaseName>.nif

<DatabaseName>\<DatabaseName>\\_\*.pro.jrn

<DatabaseName>\\_Database\<DatabaseName>.\*

<DatabaseName>\\_Database\<DatabaseName>\_\*.jrn

Do not forget to rename the .jrn files correctly: make sure there are no typos in the database name, and that they are followed by the underscore and the numeric ID.

4. In the Interplay Administrator, click the Manage Databases icon and activate the database (see [“Activating a Deactivated Database” on page 64](#)).



## 3 Server Settings

The Server settings enable you to configure and change server settings and shutdown and restart the server. The following topics describe how to use these settings:

- [Changing the Database and Data Locations](#)
- [Viewing Server Information](#)
- [Locking and Unlocking the Server](#)
- [Restarting the Server](#)
- [Managing Licenses](#)

### Changing the Database and Data Locations

The Server Settings view lets you change the default locations for a new database.



**Do not change the location for the metadata database. The metadata database must be stored directly on the local Interplay Engine server because permanent access to these files is required. This is the only supported setup. You have the option of storing the source files for file assets on an Avid shared-storage workspace. This configuration is known as a split database.**

Changing the root folder for file assets is part of the process of creating a split database. For more information and instructions, see [“Configuring Interplay for a Split Database” on page 209](#).

The root folder for a new database is set during the installation of the Interplay Engine software. By default, the installation program creates a shared folder that functions as the root folder for both the metadata database and the source files for file assets (the file repository). The default location is the D:\Workgroup\_Databases folder, which is represented by the administrative share name WG\_Database\$. The \$ indicates a hidden share.



*To identify the actual folder, open a Command Prompt window and type `net share`.*


If you need to create a new database, changing these settings does not affect any existing databases.

### 3 Server Settings

#### To change the root folders for a new database:

1. In the Server section of the Interplay Administrator window, click the Server Settings icon.

The Server Settings view opens.



2. For the root folder of the database (metadata), keep the folder that was set during the installation of the server (the default is \\IEServer\WG\_Database\$).
3. For the root folder of the data (file assets), change the folder to a workspace on Avid shared storage (see [“Configuring Interplay for a Split Database” on page 209](#)). Type a UNC path or browse through the Avid Unity Network or Avid ISIS Network to the workspace.

You might need to provide proper credentials to browse and access the shared storage workspaces.

4. Click Apply Changes to change the setting for new databases.
5. If you changed the root folder for the file assets, complete the tasks described in [“Splitting a Database for New Interplay Installations” on page 213](#) or [“Splitting a Database for Existing Interplay Installations” on page 215](#).

## Viewing Server Information

The Server Information view has two areas:

- The Server Information area displays information about the following:
  - The version of the Avid Interplay Engine software
  - The number of connected clients (through Interplay Access and other client applications)
  - The number of databases on the server

- The Connected User Information area displays information about the following:
  - Which database users are connected to
  - Which user is connected to which database
  - Which machine the user is connected from
  - What time a user has been connected since
- The type of licenses in use (see [“License Types and Usage”](#) on page 89)

**To view information about the Interplay Engine server:**

- ▶ In the Server section of the Interplay Administrator window, click the Server Information icon.

The Server Information view opens.

**Server Information**

Version: 1.1.1.5867

Number of Connected Clients: 4

Databases: 1

**Connected User Information**

Database	User Name	Connected From	Connected Since	License Class
AvidWG	Administrator	doctm	Jun 27, 2007 2:39:36 PM	KEY-X
AvidWG	Administrator	techpubs_JE	Jun 28, 2007 9:03:43 PM	KEY-XI
AvidWG	Composer1	techpubs_JE	Jun 28, 2007 8:37:47 PM	KEY-XI
AvidWG	Administrator	DocWG	Jun 28, 2007 8:39:49 PM	KEY-X

Refresh

# Locking and Unlocking the Server

The Lock Server view allows the administrator to lock the Interplay Engine server for a specific period of time by shutting down the server process. Locking the server is useful when carrying out tasks such as:

- Server maintenance or upgrading the server software.
- Maintaining or rebooting the Avid shared-storage server (File Manager or System Director). Whenever a database or data location is unavailable, you should lock the database or the server.

If the database becomes corrupt, the server might be locked automatically.


When the server is locked, all the clients that are connected to it are disconnected, the database is saved, and the server process is shut down so that no data is lost. While the server remains locked, users are unable to connect to the database that is stored on that server.



*If possible, use the database lock instead of the server lock. Use the server lock if you want to do maintenance on the server machine itself or the shared storage system. Use the database lock if you need to do maintenance on a database or its related files (for example, moving a database to another server). Using the database lock provides more security and is also preferable since it avoids making the entire server inaccessible. See “Locking and Unlocking Databases” on page 62.*

**To lock the server:**

1. In the Server section of the Interplay Administrator window, click the Lock Server icon.  
The Lock Server view opens.



2. Select one of the following for the locking duration:
  - Indefinitely: An indefinite shutdown. This is a good choice when shutting down the server to carry out any vital maintenance, for example replacing hard drives, or making the first backup of a new database. The server needs to be manually unlocked after maintenance work.
  - Minutes: Allows you to stipulate when to restart the server (short time frame). It is useful when you are making routine backups and you know how much time you need. Specify the time period by clicking the Up and Down arrows.
  - Lock until: Allows you to stipulate when to restart the server (longer time frame). Specify the time period by clicking the Up and Down arrows.
3. In the Lock Details text box, type a comment as to why you are locking the server. This comment is displayed when clients try to connect to the server.
4. Click Lock Server.

The Lock Server view changes to display lock information. You cannot return to the Interplay Administrator window by clicking the Menu button. You can log out of the Interplay Administrator tool and then log in again.

**To manually unlock the server:**

1. If necessary, log in to the Interplay Administrator.  
The Lock Server view opens.
2. Click Unlock Server.  
The Server Login window opens.
3. Log in to the Interplay Administrator.

## Restarting the Server

Restarting the server disconnects any clients and shuts down the database before the server process is restarted. You rarely need to restart the server. Typically, you restart the server if you want to disconnect all clients and want to make sure no one is connected to the server so that you can perform maintenance. For example, you might restart the server and then lock the database as part of the process of moving the database.

Restarting only restarts the server process and not the server machine itself.




**Depending on the size of the database, this process can take several minutes. Do not attempt to reboot the server under any circumstances before this process is completed.**

### 3 Server Settings

#### To restart the server process:

1. In the Server section of the Interplay Administrator window, click the Restart Server icon.  
The Restart Server view opens.
2. Click Restart.



## Managing Licenses

Avid Interplay needs valid licenses in order to function. A license consists of a hardware ID and a license key. The hardware ID is sometimes associated with the physical application key, or *dongle*. The license key is created by a license file and includes information about the license types for individual applications.


The Licenses view has two areas:

- The License Types area displays information about the following:
  - Your current license types (see [“License Types and Usage”](#) on page 89).
  - Number of license types available.
  - License types used.
  - Time limit (days): the total days included in the license. If you have more than one license loaded that includes the same license type, only one time limit is stored for each type.
  - Days remaining: the number of days until expiration. If you have more than one license loaded that includes the same license type, only one value for the days remaining is stored for each type.
- The Server Information area displays information about the following:
  - Customer ID. The customer name or ID number.
  - The permitted number of databases.

- Hardware ID, obtained from the physical application key (dongle). The Hardware ID is required to obtain technical support.
- License mode: All Interplay licenses are nodelocked.
- Lock timeout: The lock timeout is the time the server freezes a license on the server before it is freed for use by another user or machine. All Interplay licenses use a setting of 0 hours, 0 minutes, and 0 seconds.

**To view information about your licenses:**

- ▶ In the Server section of the Interplay Administrator window, click the Licenses icon. The Licenses view opens.



For information about importing a license file, see [“Installing a Permanent License” on page 88](#). For information about exporting a license file, see [“Exporting a License” on page 90](#).

## Installing a Permanent License

During Interplay Engine installation a temporary license for one user is activated automatically so that you can administer and install the system. There is no time limit for this license. A permanent license is provided by Avid in the form of a file (\*.nxn) on a USB flash drive.

If you purchase additional licenses, the licenses are additive. For example, one license key with 2 Access and 2 Assist users and an additional license key with 2 Access and 3 Assist users yields a total of 4 Access and 5 Assist clients.

A license for an Interplay Engine failover cluster includes two hardware IDs. You only need to install the license on one node of the cluster.

#### **To install a permanent license:**

1. Start and log in to the Interplay Administrator.
2. Make a folder for the license file on the root directory (C:\) of the Interplay Engine server or another server. For example:  
C:\Interplay\_Licenses
3. Insert the USB flash drive into any USB port.



*You can access the license file from the USB flash drive. The advantage of copying the license file to a server is that you have easy access to installer files if you should ever need them in the future.*

If the USB flash drive does not automatically display:

- a. Double-click the computer icon on the desktop.
  - b. Double-click the USB flash drive icon to open it.
4. Copy the license file (\*.nxn) into the new folder you created.
  5. In the Server section of the Interplay Administrator window, click the Licenses icon.
  6. Click the Import license button.
  7. Browse for the \*.nxn file.
  8. Select the file and click Open.

You see information about the permanent license in the License Types area.



## License Types and Usage

The following table describes the license types displayed in the Licenses view. Each license type is associated with a particular license key.

---

### License Types Used for Avid Applications

Key	Product
KEY_AM	Interplay Archive Engine
KEY_C	Interplay Streaming Server
KEY_X	Interplay Access
KEY_XL	Interplay Assist
KEY_XE	Avid Editing Applications
KEY_XI	Avid Instinct
KEY_XP	Digidesign™ Pro Tools® Integration

---

One Interplay Streaming Server license (KEY\_C) is required for each streaming server in an Interplay workgroup.

If you have an editing application running, then no additional license is needed to run Access at the same time. For example, if an Avid editing application has been started, KEY-XE also covers Interplay Access on the same machine. If the editing application is started after Interplay Access is started, KEY-X is released and KEY-XE is used instead. The same behavior applies to licenses for Interplay Assist, Avid Instinct, and Digidesign Pro Tools Integration.

When you close an application, its license is released and can be used by another client.

## Exporting a License

You might need to export your license information for support purposes.



*Export functionality is intended for Avid support purposes. You might not be able to reimport an exported license.*

### To export your license to a file:

1. Click the Export license button in the Licenses view.
2. Type or browse to a .nxn file name.
3. Select Save.

## Troubleshooting Licensing Problems

If you previously attached one application key (dongle) and loaded the registration file for that dongle, and then attach a different dongle and try to load a new registration file, the registration file will not load. You need to delete the Windows registry key for the dongle.

### To delete the registry key for a dongle:

1. Click Start, then click Run.
2. In the Open text box, type `regedit` and click OK.  
The Registry Editor view opens.
3. Locate the registry key for the original dongle, found here:
  - (32-bit OS) `HKEY_LOCAL_MACHINE\SOFTWARE\Avid Technology\Workgroup\Avid Workgroup Server\FeatureKeys\Permanent`
  - (64-bit OS) `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Avid Technology\Workgroup\Avid Workgroup Server\FeatureKeys\Permanent`
4. Delete the Permanent folder.
5. Close the Registry Editor window.
6. Reload the new registration file as described in [“Installing a Permanent License” on page 88](#).

## Using the License Key Info Tool

You can use the LicenseKeyInfo tool to display and print out the license information for an Interplay Engine or Interplay Archive Engine. This tool is primarily a support tool. It is useful when you have only a license file available (and not a server), or you want to know the enabled features of a license without installing it.

### **To examine the license key information for an Interplay Engine:**

1. Navigate to the following folder:  
C:\Program Files\Avid\Avid Interplay Engine\Server
2. Double-click LicenseKeyInfo.exe  
The Interplay License Info dialog box opens.
3. Click Get License Info.
4. Select the License file and click OK.  
The system displays the license info.
5. (Option) Click Save License Info or Print License Info and follow the on-screen instructions.

### 3 Server Settings

## 4 User Management

An administrator controls access to Avid Interplay through user accounts and user roles. The following topics provide information about how to manage user accounts and access to the database:

- [Understanding the Central Configuration Server](#)
- [Adding Users to a Central Configuration Server](#)
- [Setting User Authentication Providers and Importing Users](#)
- [Managing Users, User Groups, and User Rights](#)
- [Managing Database Roles](#)
- [Guidelines for User Management](#)

For specific examples of how to manage user roles, see “Setting Up a Folder Structure and a User Database” in the *Avid Interplay Best Practices*.

### Understanding the Central Configuration Server

The Central Configuration Server (CCS) is an Interplay Engine with a special module that is useful if you are working in an environment that includes more than one Interplay Engine (including an Interplay Archive Engine). The CCS uses this module to store information that is common to all other Interplay Engines. Cross-database management of administrative tasks is possible because all of the Interplay Engines under the CCS inherit its settings by default. A Central Configuration Server is especially useful for user management tasks.

You set a CCS whenever you install an Interplay Engine. At that time, you can set the CCS as the server on which you are installing, or you can specify a previously installed Interplay Engine, including an Interplay Archive Engine. The Interplay Engine acts as the CCS as soon as it is started after the installation. Each Interplay Engine must be associated with a CCS. An Interplay Engine can be its own CCS.

## 4 User Management

Depending on the number of Interplay Engines that are installed, several CCS configurations are possible:

- One Interplay Engine: Configure this server as the CCS.
- Several Interplay Engines: Usually you configure only one Interplay Engine as the CCS. The use of more than one CCS in a company might be useful if there are several independent domains, departments, or sites where there is no need to share users or other settings in Avid Interplay. In the case where several sites are located in different locations, having one CCS for each site could be practical.

If necessary, you can use the Central Configuration Server view to change the CCS that you set during the Interplay Engine installation.



**Do not reset the CCS unless there is real need to do so, such as a space issue. All the information that was stored on the old CCS, including users and local administration settings, is lost when the CCS is changed to another server unless you first move the `_InternalData` folder to the server that will be used as the new CCS. If you do not or cannot move the `_InternalData` folder to the new CCS, and you set the new CCS for the database, you must migrate the database through the Manage Databases view. In this case, all previous CCS-related information will be lost.**

The following procedures describe how to change the CCS:

- [“Moving the CCS to Another Server”](#) on page 94
- [“Viewing and Changing the CCS for a Server”](#) on page 95.

Specifying an incorrect CCS can prevent login. See [“Troubleshooting Login Problems”](#) on page 201.

### Moving the CCS to Another Server



**Before beginning the following procedure, be sure to make a backup of the database. See [“Creating and Restoring Database Backups”](#) on page 36 for information on running a backup. You can use the Start Backup Now feature to start a backup immediately.**

The following procedure is based on these assumptions:

- Server A is the CCS.
- You want to keep the CCS settings and user information that exist on server A, but move them to server B.
- You do not want to keep the original CCS information that exists server B.



**Server B should be created by a clean installation and should serve as its own CCS. No other database should point to Server B as a CCS, because any existing user data on Server B will be lost.**

**To move a CCS to another server:**

1. Back up the database. See [“Creating and Restoring Database Backups” on page 36](#).
2. Make sure that the Interplay Engine on both servers is the same version. See [“Viewing Server Information” on page 82](#).
3. Start Interplay Administrator and log in to server A (which is the current CCS).
4. Lock server A. See [“Locking and Unlocking the Server” on page 84](#).
5. In Interplay Administrator, log out of server A.
6. Log in to server B.
7. Lock server B.
8. Log out of server B.
9. Use Windows Explorer to delete the \_InternalData folder on server B.  
The folder is located by default in \\IEServer\WG\_Database\$ (usually D:\Workgroup\_Databases\). See [“Identifying the Root Folder of the Interplay Server Database” on page 220](#).
10. Copy the \_InternalData folder from server A to the default database location of server B.
11. In Interplay Administrator, log in to server A, unlock the server, and log out.
12. Log in to server B and unlock the server.
13. Make sure the CCS for server B is set as server B itself. If necessary, complete [“Viewing and Changing the CCS for a Server” on page 95](#).
14. Log out of server B.
15. On server A, change the CCS for server A to server B using [“Viewing and Changing the CCS for a Server” on page 95](#).

## Viewing and Changing the CCS for a Server



**Before beginning the following procedure, be sure to make a backup of the database. See [“Creating and Restoring Database Backups” on page 36](#) for information on running a backup. You can use the Start Backup Now feature to start a backup immediately.**

## 4 User Management


The following procedure is based on these assumptions:

- Server A is the CCS.
- You want server B to be the CCS for server A. You want to use the settings and user information that exists on server B.
- You do not want to keep the CCS information that exists on server A.

### To change the CCS for a server:

1. Back up the database. See [“Creating and Restoring Database Backups” on page 36](#).
2. Make sure that server A and server B are the same version, otherwise the CCS does not reset. See [“Viewing Server Information” on page 82](#).
3. Start the Interplay Administrator on server A, and log in to Server A.
4. In the User Management section of the Interplay Administrator window, click the Central Configuration Server icon.

The Central Configuration Server view opens.




5. Use the arrow in the Central Configuration Server list to select server B to use as the CCS.

A warning appears explaining the consequences if you have not followed the procedure [“Moving the CCS to Another Server” on page 94](#) and moved the `_InternalData` folder to server B.

Moving the `_InternalData` folder is usually recommended. If you do not, all users and local administration settings are lost.





6. Do one of the following:
  - ▶ To keep the original CCS, click Cancel.
  - ▶ To change to a new CCS, click Change CCS.
7. If you have not moved the original CCS server (see [“Moving the CCS to Another Server” on page 94](#)), you need to migrate the database to the new CCS and all of your CCS-related data (such as users and local administration) are lost. Unmigrated databases should not be used; databases should always be migrated to a CCS. Unmigrated databases cannot be administered. For more information, see [“Migrating a Database” on page 67](#).

# Adding Users to a Central Configuration Server

There are several ways to add users to a Central Configuration Server:

- Automatically adding Avid Unity (shared-storage) users. These users are added to the CCS the first time they log in. They log in using their Avid Unity username and password. For more information, see [“Setting Avid Unity Authentication” on page 100](#).
- Importing users from a Windows domain or LDAP directory. You need to use the User Authentication Providers view to import these users. They log in using their Windows or LDAP username and password. For more information, see [“Setting Windows Domain Authentication and Importing Users” on page 101](#) and [“Setting LDAP Authentication and Importing Users” on page 103](#).
- Individually creating users. You need to use the User Management view to create individual users. They log in using the username and password that you set. For more information, see [“Adding Users Manually” on page 111](#).

## Setting User Authentication Providers and Importing Users


The User Authentication Providers view lets you set the type of authentication users need to provide when logging in to Avid Interplay. You can select one or more of the following authentication providers:

- Avid Unity
- Windows Domain
- LDAP

Selecting these providers lets users log in without requiring them to use an additional username and password for Avid Interplay. You still have the option of creating individual users specifically for Avid Interplay (see [“Adding Users Manually” on page 111](#)).

The User Authentication Providers view lets you import users from a Windows domain or LDAP server. You do not need to explicitly import Avid Unity users; they are imported at the time they log in.


Information from this view is saved in the CCS (see [“Understanding the Central Configuration Server” on page 93](#)).



*All special characters are allowed in user names except for \ (backslash), / (forward slash), | (vertical bar), and quotes (" and '). When LDAP and Windows Domain users are imported, these characters are replaced with “\_”. If two users have different user names that are mapped to the same converted name (for example, dann/o and dann\o become dann\_o), only one converted user name is imported. These users currently cannot be authorized through LDAP or Windows Domain; they can only be imported.*

The users are added to the Imported Users folder in the User Management page, under the respective subfolder for LDAP, Microsoft, or Avid Unity. Users are also added to the Everyone folder. The following illustration shows these subfolders with the LDAP folder selected.

## 4 User Management



These types of user authentication and how users are imported are described in the following topics:

- [“Setting Avid Unity Authentication” on page 100](#)
- [“Setting Windows Domain Authentication and Importing Users” on page 101](#)
- [“Setting LDAP Authentication and Importing Users” on page 103](#)
- [“LDAP Server Configuration Settings” on page 105](#)

### Setting Avid Unity Authentication

If you select the Unity Authentication option, a user can log in to the Avid Interplay database using a valid Avid Unity password. The authentication mechanism always checks this User Authentication Provider first.

This method of authorization is implicit. In other words, there is no active import of users at the time the Avid Unity authentication is enabled. Instead, the first time that an Avid Unity user logs in to Avid Interplay, the user is added to the UNITY user group subfolder. By default, this user group has Read rights.

### To enable Avid Unity authentication:

1. In the User Management section of the Interplay Administrator window, click the User Authentication Providers icon.

The User Authentication Providers view opens.

2. Click Avid Unity Authentication.
3. Type the Avid Unity server name with which the CCS should cross-check for authentication.

In an Avid Unity MediaNetwork environment, type the name of the File Manager. In an Avid ISIS environment, type the name of the System Director.

4. Click Apply.

When an Avid Unity user logs into Interplay, the user is added to the CCS as part of the UNITY user group under Imported Users, with Read rights by default.

### To reassign an Avid Unity user's Interplay rights:

- ▶ Move the user to a different user group later if you want to give the user a different role.

For more information, see [“Managing Database Roles” on page 118](#).

## Setting Windows Domain Authentication and Importing Users

If you activate Windows Domain authentication, a user is able to log in to an Avid Interplay database with a Windows domain user name and password. Any time a user tries to access an Avid Interplay database, the CCS (Central Configuration Server) can use the Windows login information to authenticate the user and in turn to check which databases the user can access.

To use this feature, the Interplay Engine Server Execution User must be a member of the domain from which you import users and against which you want to authenticate users. If the user is logged in to a supported Windows machine, and logged into the same domain as the Interplay Engine, the user can log in using the domain user name and password.

An administrator needs to assign suitable roles to the imported users before they can access the database. By default, imported users do not have access rights to the database, which will cause a login to fail even if a user is properly authenticated by the domain. In this case, the following error message is displayed:

## 4 User Management




Note also that for Interplay to import users from an Active Directory, these users must be placed in groups. Interplay does not support importing of single users. To facilitate administration, Avid recommends that you align the Interplay group structure with the Active Directory group structure.



*Some large organizations might use a hierarchical domain structure called a “forest root domain.” For example, an organization with a domain named “company.com” might choose to place its Interplay production system in a sub-domain named “avid.company.com.” In Windows, users from different parts of this organization can be managed in groups (for example, a “Universal Group”) and can be authenticated across the entire forest. Interplay domain authentication does not support this structure. If you select a domain for authentication, users from other forest domains will be stripped from the group during the import process.*

### To enable Windows domain authentication:

1. In the User Management section of the Interplay Administrator window, click the User Authentication Providers icon.  
The User Authentication Providers view opens.
2. Select the Windows Domain Authentication option.



3. Click Import Windows Domain Users.  
The Import User Groups dialog box opens.
4. Do one of the following:
  - ▶ Select the user groups you want to import into the Avid Interplay system.
  - ▶ Click Select All to import all the user groups into the Avid Interplay system.
5. Click OK.



*Depending on the size and complexity of the import, the import operation might prevent users from logging on, browsing, checking in, or doing on work on the server*

Upon import, Interplay creates a new user group and subfolder called MICROSOFT under Imported Users in the User Management view. It imports all the users authenticated on the Windows domain that are not currently in the Avid Interplay user database. These users are imported to the MICROSOFT group and have the default role of No Access. Users can then be moved to different groups to gain a new user role. See [“Managing Database Roles” on page 118](#).

Users that are already in the Avid Interplay user database during a Windows Domain User import are added to the MICROSOFT group again but retain the group placement and role they already had.



*New users added to the Windows domain are not continually imported to the CCS. You need to add them manually. See [“Adding Users Manually” on page 111](#).*

## Setting LDAP Authentication and Importing Users

If you select the LDAP Authentication option, a user can log in to Avid Interplay databases with an LDAP user name and password. Avid Interplay supports LDAP Version 2 and LDAP Version 3.

To properly configure LDAP authentication, you must know the schema of the LDAP database. Two common schemas are


- Microsoft Active Directory LDAP implementation
- A freely available LDAP service such as OpenLDAP

The configuration you specify depends on the LDAP schema against which you are authenticating. The following illustration shows some differences between Active Directory and OpenLDAP.

## 4 User Management

### Active Directory LDAP


Logged in as: cn=Administrator,cn=Users



- dc=company, dc=com (10)
  - CN=Builtin (17)
  - CN=Computers
  - CN=ForeignSecurityPrincipals (4)
  - CN=Infrastructure
  - CN=LostAndFound
  - CN=NTDS Quotas
  - CN=Program Data (1)
  - CN=System (24)
  - CN=Users (37)
    - Create new entry here
    - CN=Administrator
    - CN=AlertRecipients
    - CN=AVID\_WORKGROUP\_USER
    - CN=Cert Publishers
    - CN=DHCP Administrators
    - CN=DHCP Users
    - CN=DnsAdmins
    - CN=DnsUpdateProxy
    - CN=Domain Admins
    - CN=Domain Computers
    - CN=Domain Controllers
    - CN=Domain Guests

### OpenLDAP

Logged in as: cn=admin



- dc=company, dc=com
  - cn=admin
  - cn=ldapuserrole
  - cn=ldapusers
  - cn=Test
  - uid=ldapuser



*Details on the LDAP schema objects can be found in RFC1274, “The Cosine and Internet X.500 Schema.”*

### To import LDAP users and enable LDAP authentication:

1. In the User Management section of the Interplay Administrator window, click the User Authentication Providers icon.

The User Authentication Providers view opens.

2. Select the LDAP Authentication option.
3. Type the information in the edit fields that specifies the individual LDAP settings of your LDAP server.

The settings are described in [“LDAP Server Configuration Settings” on page 105](#).

4. Click Apply.
5. Click Import LDAP Users to add all the LDAP users to the user group “LDAP Users” for the Interplay CCS.

The Import LDAP Users dialog box opens.



6. Select the users that you want to import.
7. Click OK.

Interplay creates a new user group and subfolder called LDAP under Imported Users and imports all the users from the LDAP server that match the filter criteria in the LDAP configuration, and are not currently available in the Avid Interplay user database. These users are imported to the LDAP group and have the default role of No Access. Users can then be moved to different groups to gain a new user role. See [“Managing Database Roles” on page 118](#).


Users that are already in the Avid Interplay user database during an LDAP User import are added to the LDAP group again but retain the additional group placement and role they already have.



*New users added to the LDAP server are not continually imported to the CCS. You need to add them manually. See [“Adding Users Manually” on page 111](#).*

## LDAP Server Configuration Settings

The following table describes the LDAP server settings that are needed for authentication and import.

Setting	Description
LDAP Server	IP address of the LDAP server.
LDAP Port	Port for the LDAP service. For Standard LDAP, accept the default port 389. For Active Directory Global Catalog LDAP, specify port 3268. For LDAP enabled over SSL (LDAPS), specify port 636
Use SSL	Select this option if the LDAP uses Secure Sockets Layer (SSL) technology.   <i>Secured LDAP requires an X.509 certificate infrastructure. For more information, see the Microsoft article <a href="#">“How to enable LDAP over SSL with a third-party certification authority.”</a></i>
User DN for Searches	User DN for a user who has the right to query the directory. This DN will be used for logging on to the LDAP directory and performing a search for importable objects after you click the Import LDAP Users button.
Password for Searches	Password for a user who has the right to query the directory. This password will be used for logging on to the LDAP directory after you click the Import LDAP Users button.

## 4 User Management

Setting	Description
Search Root DN	DN root for searches in the LDAP database. This DN specifies the search root that will be used after you click the Import LDAP Users button. This DN typically points to the branch of the LDAP tree where the user objects are located. Typical examples are “CN=queryuser,CN=Users,DC=company,DC=com” for Windows Active Directory LDAP, or “CN=queryuser,DC=company,DC=com” for OpenLDAP.
User Object Class	Object class attribute of a User. This value will be used as a search filter after you click the Import LDAP Users button. Interplay will perform an <i>ldap_search</i> request on the directory, and all returned objects that match <i>User Object Class</i> will be imported. A typical setting for Microsoft AD LDAP would be <i>organizationalPerson</i> . For OpenLDAP, a typical object class would be <i>simpleSecurityObject</i> .
User Name Attribute	Attribute that stores the user name to use for LDAP-authenticated logins. The content of this attribute becomes the imported user name in Interplay and defines the user name for LDAP-authenticated login attempts. This attribute might vary according to the LDAP schema, and there might be multiple attributes storing different varieties of the user name. For Microsoft Active Directory LDAP and OpenLDAP, the most standard attribute is “cn,” the <i>common name</i> as defined in RFC 4519. Other attributes such as <i>displayName</i> or <i>mailNickname</i> (in an Exchange-enabled environment) might also exist.
User DN Suffix	Suffix that must be appended to the user name to form a valid Distinguished User Name (DN). The resulting DN will be used whenever a user tries to authenticate through LDAP: Interplay will issue a <i>simple ldap_bind</i> request to the directory service, using a DN constructed according to the rule given above, and the clear text password as given by the user.  For example, if the user name specified during login is “journalist” and the User DN Suffix is “CN=Users,DC=company,DC=com,” Interplay will try to bind to the LDAP service using a DN of “CN=journalist,CN=Users,DC=company,DC=com.” Access will be granted if the bind request is allowed by the LDAP service. Depending on the LDAP service implementation, there might be other possible ways of constructing a DN valid for binding to the LDAP service. In Active Directory LDAP, for example, a DN suffix of “@company.com,” resulting in a DN of “journalist@company.com” might also work.

The following illustration shows an example of settings for an Active Directory LDAP implementation.

**LDAP Authentication** Import Group Location: [Users/ImportedUsers/LDAP/](#)

**LDAP Server Configuration Settings**

LDAP Server:	lengine.company.com
LDAP Port:	389
	<input type="checkbox"/> Use SSL
User DN for Searches:	CN=Administrator,CN=Users,DC=company,DC=com
Password for Searches:	****
Search Root DN:	CN=Users,DC=company,DC=com
User Object Class:	organizationalPerson
User Name Attribute:	cn
User DN Suffix:	CN=Users,DC=company,DC=com

**Initiates the importing of users from the LDAP server into the Avid Interplay Engine.**

The following illustration shows an example of settings for an OpenLDAP implementation.

**LDAP Authentication** Import Group Location: [Users/ImportedUsers/LDAP/](#)

**LDAP Server Configuration Settings**

LDAP Server:	lengine.company.com
LDAP Port:	389
	<input type="checkbox"/> Use SSL
User DN for Searches:	CN=admin,DC=company,DC=com
Password for Searches:	****
Search Root DN:	DC=company,DC=com
User Object Class:	simpleSecurityObject
User Name Attribute:	cn
User DN Suffix:	DC=company,DC=com

**Initiates the importing of users from the LDAP server into the Avid Interplay Engine.**

# Managing Users, User Groups, and User Rights

The User Management view lets you create, modify, manage and delete users and user groups. It also lets you define user roles and authentication protocols. If you are working in an environment that includes more than one Interplay Engine, you should manage users through a CCS (see [“Understanding the Central Configuration Server” on page 93](#)). Managing users through a CCS lets you manage users across multiple workgroups.

If you work at a relatively small site where all editors and assistants have access to all the current projects, then you can set all user roles by user groups. If you work at a site where you need to limit access to some projects, you can set roles for users on specific folders. See [“Managing Database Roles” on page 118](#).

For more information about managing user roles, with specific examples, see “Setting Up a Folder Structure and a User Database” in the *Avid Interplay Best Practices Guide*.

The following illustration shows the User Management view with the Administrators group selected. In this example, there are three custom user groups: Assistants, Editors, and Graphic Artists.

**Avid Interplay Administrator**

File Help

Menu Interplay Server User Management User Management Docwg Log out

Create User Create User Group Remove User Delete User/Group Central Configuration Server: Docwg

**Users**

- Users
  - Administrators
  - Assistants
  - Default
  - Editors
  - Everyone
  - Graphic Artists
  - ImportedUsers
  - Migrated Users

**Attributes**

Name: Administrators

Description: Group for users with Administrator role (defined by the administrator)

Password:

Password (conf):

Email:

**Roles**

- Administrator
- Read/Write/Delete
- Read/Write
- Read
- No Access

**Note**  
For users the accumulated inherited role is shown.

**Authentication Providers**

- Avid Unity Authentication
- Internal Authentication
- LDAP Authentication
- Windows Domain Authentication

**Additional Roles**

Can modify properties in Access  Inherited  Yes  No

**Part of Group(s)**


Group	Role	Path
Users	No Access	

Apply Revert

### Understanding Default User Groups, Users, and Roles

The User Management view displays all user groups and users. The user groups created during the server installation are as follows:

- **Administrators**, with the user Administrator: Users with administrator rights. When you first log in after the first installation, if you have not yet imported Windows Domain or LDAP server users, the only user displayed is the user “Administrator” with administrator rights. This user cannot be deleted, nor can the user rights be restricted in any way.
- **Everyone**: All users. This group contains the master user for every user in all the other groups. The master user in the Everyone group is the original user object. Instances of a user in other groups are linked to the master user. By default, the group role is set to No Access. The following illustration shows the master user for Administrator in the Everyone group and a link to the master user in the Administrators group. The icon for the linked user includes a link symbol.



- **Imported Users**: Users imported from Avid Unity, Windows Domain or LDAP (see [“Setting User Authentication Providers and Importing Users” on page 98](#)). By default, the group roles are set as follows:
  - LDAP: No Access.
  - MICROSOFT: No Access.
  - UNITY: Read Access.
- **Migrated Users**: The group for users migrated from an Avid Unity MediaManager environment to an Avid Interplay environment. By default, the group role is set to No Access. For more information on migrating users from an Avid Unity MediaManager environment to an Interplay environment, see your Avid representative.

## Adding User Groups

Interplay creates default user groups during the server installation. You can create additional groups so that you can more easily manage access to the database. For example, you might have a group of editors that should always have Read/Write/Delete privileges on all files. You might also have a group of assistants that should have Read/Write privileges. In this case you can set up two user groups that have different sets of privileges: one named Editors, and one named Assistants.

### To create a user group:

1. In the User Management section of the Interplay Administrator window, click the User Management icon.

The User Management view opens.

2. In the Users pane, select the group into which you want to add a the new user group. To create a group at the top level, select Users.

3. Do one of the following:

- ▶ Press Ctrl+G for a new user group.
- ▶ Click the Create User Group button.

4. Add a name and a description for the new group.

By default, the description is inherited from the group in which you created the group.

All special characters are allowed in user and group names except “\”, “/”, “|” and quotes (" and '). For more information, see [“Viewing and Setting Attributes” on page 112](#).

5. (Option) Select a role for the new group.

Roles are inherited from the group in which you create the group. For more information, see [“Viewing and Changing Roles” on page 114](#).

6. Click Apply.

## Adding Users Manually

You need to add users manually if you do not automatically add them through Unity (shared-storage) authentication. Even if you import Windows Domain or LDAP users, you need to add users manually if they are added to the Windows domain or LDAP server.

### To add a user manually:

1. In the User Management section of the Interplay Administrator window, click the User Management icon.

The User Management view opens.

## 4 User Management

2. In the Users pane, select the group into which you want to add a user.
3. Do one of the following:
  - ▶ Press Ctrl+U for a new user.
  - ▶ Click the Create User button.
4. Add attributes for the new user: name, description (inherited from the user group by default), password, password confirmation, and email.

All special characters are allowed in user and group names except “\”, “/”, “[” and quotes (” and ’). For more information, see [“Viewing and Setting Attributes” on page 112](#).

5. (Option) Select a role for the new user.

Roles are inherited from the group in which you create the user. For more information, see [“Viewing and Changing Roles” on page 114](#).
6. Select an authentication provider.

For more information, see [“Viewing and Setting Authentication Providers for Individual Users” on page 116](#).
7. Click Apply.

## Viewing and Setting Attributes


### To view attributes for a user group or a user:

- ▶ In the Users list of the User Management view, select the user group or user.

Attributes for the selected group or user are displayed in the Attributes pane.

If you select a group, the name and description are displayed. For an existing group, you can add or edit a description.

If you select a user, the name is displayed, plus a description (inherited from the user group by default), password, password confirmation, and email address, if you have entered them.



The screenshot shows a form titled "Attributes" with the following fields:

Name:	Editor1
Description:	
Password:	*****
Password (conf.):	*****
Email:	



By default, the password field in the Attributes text box shows asterisks. If you choose to allow the user to log in to the server with Internal Authentication, then you need to set the password in the Attributes text box. For users that log in through other providers, you do not need to specify the password. For more information, see [“Viewing and Setting Authentication Providers for Individual Users”](#) on page 116.



*The password should only include characters from the ASCII the character set. Multibyte passwords might cause login problems, and the administrator then has to reset the password.*

**To set the internal password:**

1. In the Users list, select a user.
2. Type the password and the confirmation in the text box.
3. Click Apply.

The user can change his or her password anytime in the login dialog box.



**If you select the Internal Authentication option and do not set a password, anyone can log in with that user name and no password.**

## Understanding Standard Roles and Default Rights

After you have created the user groups and individual users, you can review and if necessary change their roles. The *role* determines the rights or permissions that the user groups and individual users have. If you assign a role to a user group, all the users in that group inherit the group rights. If you add a user to a user group, the user inherits the group rights.

A user might have different roles, depending on the group in which the user belongs. The overall *accumulated inherited role* for a user is the highest role (the role with the most rights) that the user has in any one user group. This is the role that is displayed in the User Management view. See [“Guidelines for User Management”](#) on page 127 for an example of an accumulated inherited role.

The five standard roles and their default rights are as follows:

- **Administrator:** An Administrator has Read/Write/Delete rights plus the right to carry out administrative tasks such as logging on to the Interplay Administrator, adding users, managing groups, and so on. Only Administrators can see all items in the Deleted Items folder in Interplay Access.
- **Read/Write/Delete:** Users are allowed to view, import, edit, delete, rename, and move any item in the database. They can view items they have deleted themselves in the Deleted Items folder in Interplay Access.
- **Read/Write:** This role allows users to view, import, and edit items in the database.

## 4 User Management

- **Read:** These users can copy files to their local disk, but cannot delete, edit or import any item into the database. Read-only users cannot change properties.
- **No Access:** This role takes away all user rights, but the user is not removed. This is useful if you want to control access on a folder basis, for example, if you do not want a particular set of users to be able to view selected folders in the database. This is the default role for users in the Everyone, Imported Users, and Migrated Users folders.

You can assign rights for specific users on specific folders in the Manage Database Roles view (see [“Managing Database Roles” on page 118](#)).

### Viewing and Changing Roles

By default, all users in a group inherit the role assigned to the group. You cannot assign rights to specific users in the User Management view. If you want to change a user’s rights, you can move the user to a different group.

For more information about setting up roles correctly, see [“Managing Database Roles” on page 118](#).

For information about the right to modify properties in Access (displayed in the Additional Roles pane), see [“Setting Access Control for Custom Properties” on page 138](#).


#### **To view the role of a group or user:**

- ▶ In the Users list of the User Management view, select the group or user.

The role is displayed in the Roles pane. If a user has more than one role, the User Management view displays the accumulated inherited role, the highest role (the role with the most rights) that the user has in any one user group.

The groups to which a user or group belongs are shown in the Part of Group(s) pane. These entries also display the role inherited from each group.

The following illustration shows information about the user Composer1. This user has Read/Write/Delete access that is inherited from the Editors group.



**To navigate to the Users tree from the Part of Group(s) pane:**

1. Select the user group in the Part of Group(s) pane.
2. For any user group other than the Users group, right-click and select one of the following:
  - ▶ Select “Go To” to switch the focus of the Users tree to the group you selected.
  - ▶ Select “Go to user in this group” to switch the focus of the Users tree to the selected user in the selected user group. The Part of Group(s) dialog box focus does not update.

**To change the role for a user group:**

1. In the Users list of the User Management view, select the user group for which you want to change the role.
2. In the Roles area, select the appropriate role.

## 4 User Management

3. Click Apply.

**To change the role for a user, do one of the following:**

- ▶ Right-click the user and select Cut, select the group, right-click the group and select Paste. This action moves the user from one group to another. You can also drag the user from one group to another.
- ▶ Right-click the user and select Copy, select the group, right-click the group and select Paste. This action removes the user from one group and adds it to another. You can also hold down the Ctrl key and drag the user from one group to another.

## Viewing and Setting Authentication Providers for Individual Users

You set an authentication method in the User Authentication Providers view and these settings carry over to all users by default. See [“Setting User Authentication Providers and Importing Users” on page 98](#) for details.

You can change the methods by which individual users can be authenticated. The method must be enabled in the User Authentication Providers view (a *global authentication method*) before it is available for the individual user. If you set an authentication method for an individual user, and later change the global authentication method, the individual user does not inherit the global settings.

You can select more than one authentication provider. The list of providers is checked on logon and if one provider authenticates the user, the user can log on.

The following table provides information about the authentication providers you can select:


Type of Authentication	Description
Avid Unity Authentication	The user can log in to the Interplay database using a valid Avid Unity password.
Internal Authentication	The user can log in to the Interplay database using the password you set in the User Management view. By default, the password field in the Attributes pane is empty. The user can change this password anytime in the Interplay login dialog box.
LDAP Authentication	The user can log in to the Interplay database using an LDAP user name and password.
Windows Domain Authentication	The user can log in to the Interplay database using a Windows domain user name and password.



**If you do not select an authentication method for a user, the user cannot log in.**

**To change or add an authentication provider:**

1. In the Users list of the User Management view, select the user.
2. In the Authentication Providers pane of the User Management view, select the appropriate options.



3. Click Apply to make the change, or Revert to discard your changes.

## Deleting Users and User Groups

You can delete any user except Administrator and you can delete any user group except Administrators, Migrated Users, and Everyone.

Avid recommends that a user check in all files and log off before you delete the user.



**Deleting a user or user group deletes it from all groups in the Users list and from the Central Configuration Server.**

**To delete a user group or a user:**

1. Select the user group or user in the Users pane.
2. Click the Delete User/Group button.



A user remains in all other user groups it is in, if any.


## Removing Users from User Groups

You can remove any user except Administrator from any user group except the Everyone group. Removing a user does not delete the user from other groups.

## 4 User Management

### To remove a user from a user group:

1. Select the user in the group from which you want it removed.
2. Do one of the following:
  - ▶ Press the Delete key.
  - ▶ Click the Remove User button.



## Managing Database Roles

You set and manage global roles for users in the User Management view (see [“Managing Users, User Groups, and User Rights” on page 108](#)). You have the option of limiting or granting rights for specific users on specific folders. Use the Manage Database Roles view to manage rights on specific folders.

For example, you might have editors and graphic artists that are working on different projects. To avoid confusion, you might want to prevent editors on one project from having write and delete rights on projects that they are not working on. For information about the five standard roles, see [“Understanding Standard Roles and Default Rights” on page 113](#).

There are two different ways to assign roles to folders:

- General role assignments (see [“Viewing General Role Assignments” on page 118](#) and [“Setting or Changing a General Role Assignment” on page 121](#))
- Special access folders (see [“Managing Special Access Folders” on page 124](#))


For more examples of setting up rights on folders, see [“Setting Up a Folder Structure and a User Database”](#) in the *Avid Interplay Best Practices Guide*.

## Viewing General Role Assignments


### To view assigned roles for users of the database or a folder:

1. In the User Management section of the Interplay Administrator window, click the Manage Database Roles icon.

The Manage Database Roles view opens.



2. Select the General Role Assignment option.






General Role Assignment option

3. In the Database pane, select the database or a folder for which you want to view roles.

## 4 User Management

If the database icon has a red X, you are not connected. Click the database icon to connect. The database icon shows a green check mark when you are connected. The following table describes three different states of the database icon.

Icon	Meaning
	(Green circle with check mark) Database you are connected to.
	(Red box with X) Database you are not connected to.
	(Red box with X and yellow arrow) Database needs migration. See <a href="#">“Migrating a Database” on page 67</a> .


4. In the User/Group pane, select the user or group.
  - ▶ To view roles for all users of the selected folder, select All Users and Groups.
  - ▶ To view roles for a particular user or user group of the selected folder, select that user or user group.
5. In the Roles pane, select the role you want to view:
  - ▶ To view all roles for the selected users of the selected folder, select “All roles.”
  - ▶ To view particular roles for the selected users of the selected folder, select a role.

The path in the middle of the view displays a formula for what is displayed in the lower panel.

The Node (item in the database), User, and corresponding role are displayed in the lower panel. Roles that are inherited from a group are grayed out. Roles that have been assigned directly are black.

The following illustration shows the Projects folder, the Editors group, and All roles selected. All roles are listed in the lower panel.





## Setting or Changing a General Role Assignment

Use the Manage Database Roles view to set or change rights to a particular folder. Note the following:

- To delete items, the user must have deletion rights for the folder, even if the user is the owner of the item to be deleted.
- To move items, the user must have write rights on the object, the folder the object is being moved out of, and the target folder.
- All users are automatically assigned the Read role for the folder Unchecked-in Avid Assets (but not the contents), and the Read/Write/Delete role for their private folder within the Unchecked-in Avid Assets folder. All users are automatically assigned the No


## 4 User Management

Access role for Orphan Clips. Administrators have full access to all folders. For more information about the Unchecked-in Avid Assets folder and the Orphan Clips folder, see the *Avid Interplay Access User's Guide*.

### To set or change a role for users of the database or a folder:


1. In the User Management section of the Interplay Administrator window, click the Manage Database Roles icon.  
The Manage Database Roles view opens.
2. Select the General Role Assignment option.
3. In the Database pane, select the database or a folder for which you want to set a role.
4. In the User/Group column, select the user or user group.
5. In the Roles column, select the role you want to set.

The formula in the middle of the view shows your selection. For example, in the following illustration, you are going to give Editors the Read role (read-only access) for the Antarctica folder.



## 6. Click Set Role.

The role appears in the lower panel.

**To change a role:**

- ▶ Select the entry in the lower pane, right-click, and select Set Role > *role name*.

**To remove a role for users of the database or a folder:**

1. Select the database or a folder in the Database column.
2. Select an entry in the list in the lower pane.
3. Do one of the following:
  - ▶ Click the Remove Role button.
  - ▶ Right-click and select Remove Role.

The role for the users on that item is inherited from the parent user group again.

### Blocking Access by a Group or User

When you are trying to block access by a whole group, it is not sufficient to change the user rights for the user group to NoAccess; individual users who have rights assigned to them specifically or through memberships in other user groups could still log in.

#### **To block members of an entire group:**

1. In the Manage Database Roles view, in the Database pane, select the project from which you want to block users.
2. In the User/Group pane, expand the group.
3. Select each user, and in the Roles pane select No Access.
4. Click Set Role.

#### **To prevent a user from accessing all databases:**

- ▶ In the User Management view, deselect all authentication providers available to a user.


### Managing Special Access Folders

If necessary, you can allow a user to access a specific folder that they otherwise would not have access to. For example, if a new user is assigned the No Access role for the Projects folder, you can allow access to a particular project within the folder.

#### **To allow access to a Special Access folder:**

1. In the Manage Database Roles view, set the No Access role for the specific user on the top-level folder that you want to be hidden (see [“Setting or Changing a General Role Assignment” on page 121](#)).
2. On the item for which the user needs access, set the role to Read (or higher).

The “Folder is not visible” dialog box opens, telling you how applying the role to the selected location will affect the user’s rights on other folders.




3. Click the Apply button for the option “Mark as Special Access Folder: Grant path access and allow to view path.”

This option allows users to log in to the database and navigate to the specified location. The tree structure above the folder will be visible, but not the contents of the other folders in the structure. The first option makes the contents of the tree structure accessible as well (not recommended).

After you set the special access, when users connect to the database, they see the structure of the database above the special access folder, but not the contents of the individual folders. Only the contents of the folder for which they have Read or higher rights are available.

**To view who has been assigned access to Special Access folders:**

1. Select the Special Access Folders option.




2. In the Database pane, select the entire database or the folder for which you want to check for Special Access folder rights.
3. In the User/Group pane, select All Users to see all users who have special access to the folders you selected, or select a specific user.

## 4 User Management

4. The bottom panel displays the users who have special access according to your selections.

The following illustration shows that the user jeditor has special access to the folder /Outside Productions/Graphics. To view what specific role jeditor has, select the folder in the Database pane.



### To remove a role assigned for Special Access folders:

1. Click the Special Access Folders option.
2. Select the appropriate folder.
3. Select the user in the list in the lower pane.
4. Do one of the following:
  - ▶ Click Remove Role.
  - ▶ Right-click the user and select Remove Role.

The role for the user on that item is inherited from the parent user groups again.

# Guidelines for User Management

This topic provides information and suggestions that can help you manage users and access. For more information about managing user roles, with specific examples, see “Setting Up a Folder Structure and a User Database” in *Avid Interplay Best Practices*.

- The fundamental rule of user management is that explicit rights override inherited rights, and database rights (set in the Database Management view) override CCS rights (set in the User Management view and stored in the CCS). The exception to this rule is the user who is a global Administrator set through the User Management view. This Administrator always has Administrative rights on all folders, even if rights are set otherwise in the Manage Database Roles view.
- By default, the root group Users is assigned the NoAccess role. That means that all user subgroups (Everyone, Imported Users, Migrated Users and any other groups you add) except for the Administrators and UNITY (under the Imported Users) have the role NoAccess through inheritance. NoAccess means that a user cannot even log in to the server. (The Administrators group is assigned the Administrator role and the UNITY group is assigned the Read role.)

To override the NoAccess role, create another user group with a different role and copy the user into that group.



**Changing the role for the Users group or the Everyone group (from No Access to Read, for example) makes it impossible to take away this role from individual users. Avid recommends that you do not change the role of the Users group or the Everyone group.**

- You can assign a user to more than one user group (see “[Setting or Changing a General Role Assignment](#)” on page 121) and each group can have a different role. As a result, the user inherits different roles, which can be useful if a user contributes to different projects in different ways.
- In the User Management view, you can set only group roles. You can set roles for individual users in the Manage Database Roles view. See “[Managing Database Roles](#)” on page 118.

## How the Interplay Engine Determines Access

The following steps describe how the Interplay Engine server determines access to an object (usually a folder). This process can help you understand how to assign roles and access:

1. The server checks on the object in question to see if explicit rights are set. If a user is assigned a role on the object, the evaluation stops and the server grants the user only the role allowed and the accompanying rights, if any.
2. If no explicit permissions were found on the object, the server checks the inherited rights on the object in question.

## 4 User Management

3. If there are no inherited permissions, the server checks the global user rights. In this case, the server determines what role the user has from the CCS settings.
4. In case of a conflict where the evaluation sees a user with multiple roles, for example:
  - the user has the read role through one group
  - the user has the read/write role through another groupthen the highest ranking role wins. In this case, the user gets the read/write role.

This is an example of an *accumulated inherited* role. The user's overall role for the database is the *highest* role he or she is assigned to in any group, unless otherwise specified in the Manage Database Roles view. For example: If User A is in Group 1 (which is assigned a Read role) and User A is also in Group 2 (which is assigned a No Access role), then User A has the accumulated inherited role Read. When you select User A in the User Management view, this role is displayed in the Roles pane.



## 5 Site Settings

Site settings include configuration options for various Interplay components. The following topics provide information about site settings:

- [Defining Property Layouts](#)
- [Setting the Resolutions Available for Display](#)
- [Creating Custom Properties](#)
- [Configuring Remote Workgroups](#)
- [Configuring Categories](#)
- [Setting Server Hostnames and the Workgroup Name](#)
- [Interplay Media Services View](#)
- [Interplay Transfer Status View](#)
- [Interplay Transfer Settings View](#)
- [Workgroup Transfer Presets View](#)
- [Specifying Archive Settings](#)
- [Setting the Ownership for New Database Folders](#)
- [Setting Options for Deletion](#)
- [Viewing and Setting the Metadata Override Status](#)

### Defining Property Layouts

Administrators can use the System Properties tab in the Property Layout view to specify which properties are available for display in the following client applications:

- Interplay Access
- Interplay Assist
- Avid Instinct
- Avid editing systems (Interplay Window)


## 5 Site Settings

These properties are sometimes referred to as *system metadata*. However, it is only part of the metadata included in an Avid Interplay database. For a description of available properties, see [“System Metadata Properties” on page 269](#).

For Interplay Access, administrators select which properties are displayed by default in the Content tab and Object Inspector Property tabs. Users can then add other available properties to these tabs. They can also use available properties in an extended search. For the other client applications, the default properties are preset, and users can add other available properties as columns in the Research panel.

By default, a set of properties categorized as Broadcast is selected and displayed. You can customize this set or you can display an alternative set of properties, either Post or Film, and then customize this set.

The following illustration is an example of properties displayed in the Properties tab of the Interplay Access Object Inspector.




The administrator can also use the Property Layout view to do the following:

- Create custom columns. See [“Creating Custom Properties” on page 134](#).
- Control the resolutions that are available for display. See [“Setting the Resolutions Available for Display” on page 132](#)

### To set the properties displayed in Interplay Access:

1. In the Site Settings section of the Interplay Administrator window, click the Property Layout icon.

The Property Layout view opens.



2. Select the database for which you want to set properties.
3. Click the System Properties tab.
4. From the Active Layout options, select one of the following layouts:
  - Broadcast
  - Post
  - Film

This option determines which set of properties is displayed in the client applications.

5. Select and deselect properties as follows:

## 5 Site Settings

- ▶ (Option) To make a property available for users to add into displays on their own, and to use in an Extended Search in Interplay Access, select the property in the Available column. To make a property unavailable, deselect it.
- ▶ (Option) To include a property in the Interplay Access Content tab, select the property in the Content Default Column. To remove a property from the Content tab, deselect it.
- ▶ (Option) To include a property in the Interplay Access Object Inspector's Properties tab, select properties in the Inspector Default column. To remove a property from the Object Inspector's Properties tab, deselect it.



*You must select a property in the Available column if you want to display the property in the Object Inspector or the Content tab.*

6. (Option) Click Revert to reset properties to the defaults.
7. Click Apply to save the changes.

The changes appear the next time you log in to Interplay Access.


## Setting the Resolutions Available for Display

Administrators can use the Resolutions tab in the Property Layout view to specify which resolutions are available for display in the following client applications:

- Interplay Access
- Interplay Assist
- Avid Instinct
- Avid editing systems (Interplay Window)

Lists of available resolutions appear in various places in these clients. For example, Interplay Access includes a Resolutions dialog box that lets you select which resolutions to display as columns in the Content view (available when you click the Presets button). Interplay Assist and Avid Instinct include a dialog box that lets you select the columns you want to display in the Research panel.

The Resolutions tab in the Property Layout view displays a list of all current Avid resolutions. By default, the available resolutions that are currently used in the database are selected and are displayed in bold.



In some circumstances you might want to make additional resolutions available for display. For example, if you are using Interplay Access to view the status of assets on remote workgroups, and the database for the local workgroup does not include resolutions used on the remote workgroup, you can select those resolutions for display in the local version of Interplay Access.

By default, the option “Enable used resolutions automatically” is selected. If you add an asset associated with a previously unused resolution to the Interplay database, this option automatically adds it to the default list. It also prevents you from deselecting currently used resolutions (check boxes are grayed out). If you want to remove a currently used resolution from the list for display, deselect this option.

#### To set the resolutions that are available for display:

1. In the Site Settings section of the Interplay Administrator window, click the Property Layout icon.

The Property Layout view opens.


2. Select the database for which you want to set resolutions.
3. Click the Resolutions tab.

Resolutions that are used in the database are selected by default.

4. To add a resolution, select its check box in the Available column.

The check box for the selected resolution is colored green. The name of the resolution is not in bold face.

## 5 Site Settings



Resolution in local database:  
grayed-out check box,  
name in bold face

Resolution not in local database:  
grayed-out check box,  
name not in bold face

5. To remove a resolution, deselect its check box in the Available column.

If you want to remove a default resolution, deselect “Enable used resolutions automatically” and then deselect the resolution’s checkbox. Keep in mind that any new resolutions added to the database will not be automatically selected as available for display.

6. Click Apply to save your changes.

The changes you made appear the next time you open a list of available resolutions in the client. If a new resolution is available, a user needs to select it for display. If a resolution was displayed as a column, the column might remain until the next time you log into the client.

## Creating Custom Properties

Administrators can create custom properties and specify how they are displayed in the following clients:

- Interplay Access
- Interplay Assist

- Avid Instinct
- Avid editing systems (Interplay Window)

By default, the user needs to type the value for a custom property. Administrators can import an XML file that creates a list of values from which the user can select a value.

The following topics describe how to create and use custom properties:

- [“Adding a Custom Property” on page 135](#)
- [“Setting Access Control for Custom Properties” on page 138](#)
- [“Working with Lists for Custom Properties” on page 140](#)

## Adding a Custom Property

You can add a custom property (custom metadata) that requires text to be entered as a value. The same set of custom properties are available in all layouts (Broadcast, Post, and Film).

An entry in a custom property field is limited to 31 characters. If you use multi-byte characters, this limit is lowered in a variable way.


You can also add a list of values from which users can choose (see [“Working with Lists for Custom Properties” on page 140](#)).

### **To add a custom property:**

1. In the Site Settings section of the Interplay Administrator window, click the Property Layout icon.  
The Property Layout view opens.
2. Select the database for which you want to set properties.
3. Click the Custom Meta Data tab.  
Any previously defined custom properties are displayed.
4. In the Add Custom Meta Data Field text box, type a name for the custom property.
5. Click the green plus sign (+).

After a few seconds, the custom property appears in the list, with the Available column selected. The following illustration shows a new Custom Property named “Teams.”

## 5 Site Settings



When the Available column is selected, the custom property is available for users to add into the application displays, and to use in an Extended search. If the user performs an All Custom search, only the available custom properties are used in the search.




*Deselect the property in the Available column to turn off custom properties that you do not want displayed in the properties lists. You cannot delete custom properties for this release but you can turn off their display.*

6. Select whether to include the property in the Content tab or the Object Inspector's Properties tab, as needed (Access only).
7. (Option) If you created an XML file for a list of values:
  - a. Click the Import button for the Custom Property.

The Import Custom Attribute Values dialog box opens.
  - b. Navigate to the XML file and click Open.


The Values and Default Value appear in the Custom Meta Data tab. The following illustration shows the custom property "Teams" with a list of values and the default value displayed.






- 8. Click Apply to save the added custom property and new layout.
- 9. (Option) If you want to prevent a user or group from supplying a value for a custom property, change the role in the User Management view (see [“Setting Access Control for Custom Properties”](#) on page 138).

The next time a user starts Interplay Access and logs in, the new custom property is displayed. The following illustration shows the custom property “Teams” and its list of values, with the default value highlighted.



## 5 Site Settings

To select a value, click an item in the list, then click Apply. In this example, a user associated the value Team A to the folder.



Users can add a custom property as a column in Interplay Assist, Avid Instinct, and the Interplay Window.


### Setting Access Control for Custom Properties

You can control which users can supply a value for a custom property. This setting applies to both typing a value and selecting one from a list. By default, users are allowed to supply a value.

#### To set access control for custom properties:

1. In the User Management section of the Interplay Administrator window, click the User Management icon.

The User Management view opens.



2. In the Users pane, select a group or user.
3. In the Additional Roles pane, select an option for “Can modify properties in Access”:
  - Inherited: Allows the selected user or group to inherit the role of the parent group
  - Yes: Allows users to type a value or to select from a menu.
  - No: Prevents users from typing or selecting from a menu. Users can see the property and its text box, but cannot supply a value for it.

If the options are grayed out, click the Edit button.

4. Click Apply.

### Working with Lists for Custom Properties

You can create a custom property that includes a list of values from which users can choose (see [“Creating Custom Properties” on page 134](#)). These lists are sometimes referred to as *dictionaries* or *taxonomies*. The following topics provide more information about working with lists for custom properties:

- [“Creating and Editing a File for Custom Properties” on page 140](#)
- [“Removing a List for a Custom Property” on page 142](#)
- [“Using Custom Properties in an Extended Search” on page 143](#)


### Creating and Editing a File for Custom Properties

If you want to provide users with a list of values they can choose from, you need to create an XML file and then import it into the Interplay Administrator. You can create a simple list of options, or you can create a hierarchy of options and suboptions. For example, if a user wants to label clips of sports teams, you can create a file so that the user can select a league, and then select a team from that league. You can specify a default selection that is highlighted in the list.

The following example shows an XML file that creates a single level set of choices, with Team A as the default value. Substitute the values you want for the description (which appears in the Values column of the Custom Meta Data tab) and team names. Use the quotation marks as shown.

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE values SYSTEM "custom_attributes.dtd">
<values description="Teams">
    <value name="Team A" default="true"/>
    <value name="Team B"/>
    <value name="Team C"/>
    <value name="Team D"/>
</values>
```

The choices will appear in Interplay Access as shown in the following illustration:



The following example shows an XML file that creates a two-level hierarchy, with “League 1 Team A” as the default value.

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE values SYSTEM "custom_attributes.dtd">
<values description="Teams">
    <value name="League 1">
        <value name="Team A" default="true"/>
        <value name="Team B"/>
    </value>
    <value name="League 2">
        <value name="Team C"/>
        <value name="Team D"/>
    </value>
</values>
```

The choices will appear in Interplay Access as shown in the following illustration:

## 5 Site Settings



*A custom property with a list of values is blank until you select a value. After you select a value, you cannot return the field to a blank state. If appropriate for your custom property, you can include a value in the list called “No Value” or something similar. To clear a value and completely remove a list, see “Removing a List for a Custom Property” on page 142.*

### **To create an XML file of values for a custom property:**

1. Use a text editor or XML editor to create a file that matches one of the formats presented above.
2. Name and save the file.
3. In the Custom Meta Data tab, create a custom property and import the file, as described in “Adding a Custom Property” on page 135.

### **To edit a list of values:**

1. Do one of the following:
  - ▶ Edit the original file.
  - ▶ Export the existing file by clicking Export in the Custom Properties tab and then edit it.
2. Save the file.
3. In the Custom Meta Data tab, select the custom property and import the file.

## **Removing a List for a Custom Property**

To remove a list of values for a custom property, you need to create and import a valid but empty XML file.

**To remove a list of values for a custom property:**

1. Use a text editor or XML editor to create a file that matches the following format. Use quotation marks as shown:


```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE values SYSTEM "custom_attributes.dtd">
<values/>
```

2. Save the file.
3. In the Custom Meta Data tab, select the custom property and import the file, as described in [“Adding a Custom Property” on page 135](#).

**Using Custom Properties in an Extended Search**

Users can select a value for a custom property in the Access Extended Search tab. If a user selects a custom property that uses a list of values, and selects “is,” “is not,” “starts with,” or “does not start with” as an operator, the list of values is displayed.

The following illustration shows a list of values for a search that uses the property “Team.”



For more information on searching in Access, see the *Avid Interplay Access User’s Guide* or the Access Help.

## Configuring Remote Workgroups

A large site can include more than one workgroup. When a workflow requires searching across remote workgroups or performing workgroup-to-workgroup transfers through Interplay Access, you must set up the local workgroup so that a user can access a remote workgroup. You set up this access in the Configure Remote Workgroups view. You can add an Interplay Archive Engine as a remote workgroup.

After access to a workgroup is properly configured, an Interplay Access user can select from a list of remote workgroups when performing a search or a transfer. For example, databases for properly configured remote workgroups are listed in the Interplay Access Send to Workgroup dialog box.



*Configuring a remote workgroup in this view is not needed for transfer from Interplay Assist, Avid Instinct, or Avid editing systems.*

For complete information on transferring Avid assets, see the *Avid Interplay Transfer Setup and User's Guide* or the Interplay Transfer Help.



*You can configure a maximum of 10 hostnames. For example, you can configure for searching five remote workgroups and five Nearchive servers for a total of 10.*

### **To set up access to a remote workgroup:**


1. For transfers, make sure the Transfer Engines for both workgroups are correctly configured.
2. Make sure the list of users for the remote workgroup includes the user name and password of users in the local workgroup who require access to the remote workgroup. For transfers, make sure the user name and password match exactly, and that Administrator passwords also match exactly.

In Interplay Access, if the local user's account is not included in the remote user database, a login screen appears. If you log in with an account on the remote workgroup, you can add the remote workgroup to the accessible remote servers list but you cannot transfer to the workgroup.

3. In the Site Settings section of the Interplay Administrator window, click the Configure Remote Workgroups icon.

The Configure Remote Workgroups view opens.





4. Select a database from the Available Databases list.
5. In the New server pane, add information about the remote workgroup you want to access.
  - a. Select the Host Type:
    - Interplay Server/Remote Search—to add access to a remote Interplay workgroup
    - TransferManager—to add access to a Workgroup 4 TransferManager
    - MediaManager—to add access to a Workgroup 4 workgroup or Nearchive™ system
    - Interplay Server / 3d Party Search—to add access for a third-party plug-in. The plug-in needs to be properly installed before you can configure it. See “Using Third-Party Search Plug-Ins” in the *Interplay Access User’s Guide* or Help.
  - b. Type information for the remote workgroup. The fields vary, depending on the Host Type you selected.
    - For the Server, you can type the remote workgroup’s IP address instead of the host name.
    - For Database, select AvidWG for an Interplay Engine or AvidAM for an Interplay Archive Engine.

## 5 Site Settings

- The Nickname is displayed in the Interplay Access Remote Search list and must be less than 255 characters. If you do not supply a Nickname, the Interplay Engine creates one that combines the host name and the database.
- c. Click Add.


The Server name and other information about the remote workgroup appears in the list of accessible remote servers.

### To remove a remote workgroup from the accessible list:

1. Click the name of the remote workgroup in the list.
2. Click Remove.

## Configuring Categories

Categories provide a grouping mechanism for the data that is stored in the database. Categories are displayed in Interplay Access, Interplay Assist, and Avid Instinct. A user can assign database items to these categories and use these categories in a search. You can double-click a category to view a list of the category's items.



By default, no categories are configured in the Interplay Administrator.




**There is no option to rename a category. The database items identify the categories they belong to by the category name, so this name cannot be changed once it is used.**

## Adding Categories

### To make categories available in Interplay Access:


1. In the Site Settings section of the Interplay Administrator window, click the Configure Categories icon.

The Configure Categories view opens.



2. Select a database from the Available Databases list.
3. In the New Categories text box, type one name for a category, or type a comma-separated list (commas and spaces are automatically removed).
4. Click Add, and then click Apply.


After refreshing Interplay Access, the categories you specified are visible in the Categories pane.



When performing a search, you can use a Category name to locate items that belong to that category.

### Removing Categories

Removing a category only removes it from the Configured Categories list in the Interplay Administrator. Objects in the database that have this category keep it, even if it is not listed anymore. If an item was assigned to a category but you removed that category in the Interplay Administrator, users are informed that the category is not valid anymore in the Interplay Access Categories tab.



#### To remove a category:

1. In the Interplay Administrator, click Configure Categories.
2. In the Configure Categories view, from the Configured Categories list, select the category you want to delete from the Configured Categories list.
3. Click Remove.
4. Click Apply to save the changes, or Revert to discard your changes.

You must refresh Interplay Access to see that the category is no longer available.

# Setting Server Hostnames and the Workgroup Name

The Server Hostname Settings view lets you set the following information:


- The computer name of the Interplay Media Services Engine. You must register the Interplay Media Services Engine before you can run the Interplay Media Services view (see [“Interplay Media Services View” on page 153](#)) or use any Interplay Media Services. For more information, see the *Avid Interplay Media Services Setup and User’s Guide*.
- The hostname and port for the Interplay Delivery Receiver service. You must enter the name of the system where the Interplay Delivery Receiver service is installed before you can receive transfers from the Delivery service. By default the port is 33321. For more information, see the *Avid Interplay Media Services Setup and User’s Guide*.
- The name of the Interplay workgroup. You must enter the name of the workgroup so that Interplay Access, Interplay Assist, and Avid Instinct can locate the Media Indexer, which is used to monitor shared storage. For more information, see the *Avid Service Framework User’s Guide*.



**The Workgroup Name field is case sensitive and the name must exactly match the workgroup name used by the Avid Service Framework. You can view or change this workgroup name in the Avid Interplay Workgroup Properties, which is an application that is part of the Avid Service Framework.**

- The computer name of the fallback shared-storage server. This name is automatically entered after the first connection from the Interplay Engine to the shared storage system, so in most cases you do not need to enter this computer name. Usually the Interplay Engine gets the name of the shared-storage server from the Media Indexer. If this is not possible, the Interplay Engine gets the name of the shared-storage server from the Fallback Shared-Storage Server setting. Use this setting in case you need to change the name of the shared-storage server.
- The computer name of the server that is running the Interplay Streaming Server, a Windows service that is used to play clips for WAN browsing. You need to enter this computer name after you install the Interplay Streaming Server software. See [“Configuring the Interplay Streaming Server” on page 151](#).

## 5 Site Settings



### To register the Interplay Media Services Engine:

1. In the Site Settings section of the Interplay Administrator window, click the Server Hostname Settings icon.  
The Server Hostname Settings view opens.
2. In the Interplay Media Services Settings area, type the name of the Interplay Media Services Engine server in the text box.
3. Click Apply Changes.

### To set the Interplay Delivery Receiver host and port:

1. In the Interplay Media Services Settings area, type the name of the host and the port number. By default, the port number is 33321.
2. Click Apply Changes.

**To set the workgroup name and check Media Indexer:**

1. In the Workgroup and Media Indexer Settings area, type the workgroup name.



**The Workgroup Name field is case sensitive and the name must exactly match the workgroup name used by the Avid Service Framework.**

2. Click Apply Changes.
3. Click Check Media Indexer to check whether the Media Indexer that monitors shared storage is running.

If the Media Indexer is running, the system displays the message “Connected to Media Indexer successfully” in the Notifications area at the bottom of the Interplay Administrator window.

If there is a problem, an error message is displayed, such as “No lookup service found for workgroup.” See “Configuring Avid Interplay Media Indexers” in the *Avid Interplay Best Practices Guide*.

**To change the name of the shared-storage server:**

1. Clear the field by deleting the name of the previously used shared-storage server.
2. Click Apply Changes.

The name is automatically entered after the first connection from the Interplay Engine to the shared-storage system.

## Configuring the Interplay Streaming Server

After you install the Interplay Streaming Server software, you need to enter the name of the computer on which you installed the software. For installation information, see *Avid Interplay Software Installation and Configuration*.



**After installation, exclude the folder C:\Program Files (x86)\Avid\Avid Interplay Streaming Server from scanning by any virus protection software. Scanning for virus protection could cause severe disruptions to the Interplay Stream Server and could cause it to shut down.**

You can add one or more additional Interplay Streaming Servers to a workgroup. See *Avid Interplay Software Installation and Configuration*.

## 5 Site Settings



*In Interplay v2.4, the Interplay Stream Server was re-engineered to play MPEG-4/H.263 and H.264 proxy media. There is no longer any need to use the Publishing service or Workflow Engine to create QuickTime reference movies. Double-click a clip that uses supported proxy media and the clip plays in the Monitor.*

*For Interplay v2.4, the name of the stream server on the Avid Server Installation USB flash drive is “Avid Interplay Streaming Server” and the name of the installed Windows service is “Avid Interplay Streaming Server Service.” For Interplay v2.3 and earlier, the name was “Avid Interplay Stream Server.”*


### To add an Interplay Streaming Server to a workgroup:

1. In the Site Settings section of the Interplay Administrator window, click the Server Hostname Settings icon.

The Server Hostname Settings view opens.

2. In the Stream Server Settings area, click the Add button.

The Add Stream Server and Share dialog box opens.




3. Type the computer name of the system that is running the Interplay Stream Server. You do not have to type \\ before the name of the server.
4. Click OK.

The computer name is displayed in the Server Hostname Settings view.



*The share name listed does not apply to the Interplay Streaming Server v2.4 (it was used in the Interplay Stream Server v2.3 and earlier). The installer for the Interplay Streaming Server v2.4 does not create this share. However, you cannot remove this share name.*





**To rename an Interplay Streaming Server:**

1. In the Stream Server Settings area, click the Rename button.  
The Rename Stream Server and Share dialog box opens.
2. Type the computer name of the system that is now running the Interplay Streaming Server. You do not have to type \\ before the name of the server.
3. Click OK.  
The computer name is displayed in the Server Hostname Settings view.

**To delete an Interplay Streaming Server:**

1. In the Stream Server Settings area, click the Remove button.
2. Click OK.  
The Interplay Stream Server is deleted.

## Interplay Media Services View

The Interplay Media Services view is a tool for administering the Interplay Media Services Engine and monitoring job status. This view provides settings for the following tasks:

- Filtering jobs to monitor
- Registering providers
- Installing services
- Setting up users
- Setting up profiles



*These options are also available from the Admin Tool in the Avid Interplay Media Services application dialog box.*

Before you can use the Interplay Media Services view, the Interplay Media Services Engine for the workgroup must be configured in the Server Hostname Settings view. For details, see [“Setting Server Hostnames and the Workgroup Name” on page 149](#). Also, the Interplay Media Services Engine must be running.

If the Interplay Media Services connection to the Interplay Media Services Engine fails, the login panel is displayed to let you manually attempt to login again.

For details on installing and using the Interplay Media Services Engine, see *Avid Interplay Media Services Setup and User's Guide*.

## Interplay Transfer Status View

The Interplay Transfer Status view is used for monitoring the progress of transactions being handled by one or more Interplay Transfer Engines in the workgroup. It allows administrators to quickly view all the relevant details for each transaction. You can choose to have the status window open at all times in their control center.



*The list of Interplay Transfer Engines available from the Interplay Transfer Status filter is created from the Interplay Transfer Settings. For details, see “Interplay Transfer Settings View” on page 154.*

For descriptions of the various filters and configuration settings, see the *Avid Interplay Transfer Setup and User's Guide*.

## Interplay Transfer Settings View

The Interplay Transfer Settings view lets an administrator configure the names and locations of the Interplay Transfer Engines in the workgroup. The settings determine which cache server monitors which Transfer Engines and Transfer Engine enabled devices. The Interplay Transfer Status view uses these settings to access the Transfer Engines in the workgroup.

For procedures that explain these settings, see the *Avid Interplay Transfer Setup and User's Guide*.

## Workgroup Transfer Presets View

When performing workgroup transfers, you can use presets to select a predefined destination for the transferring files. Transfer presets provide the name of the remote workgroup, a destination workspace, and a destination folder for the metadata. You can also choose whether to display the preset in the Send to Workgroup dialog box.



*Users with Administration rights can change the configuration to another destination in the Send to Workgroup dialog box in Interplay Access.*

For procedures that explain the Workgroup Transfer Presets view, see the *Avid Interplay Transfer Setup and User's Guide*.

## Specifying Remote Servers for Asset Tracking

If your facility includes more than one workgroup, you can use Interplay Access to display information for assets that are shared by different workgroups. For example, you can determine if assets stored in one workgroup are correctly archived in an archive workgroup.


In the Interplay Administrator, you need to specify the name of the Interplay Engine server for the remote workgroup.

For complete information about asset tracking, see the *Avid Interplay Access User's Guide*.

### To specify a remote server for asset tracking:

1. In the Site Settings section of the Interplay Administrator window, click the Asset Tracking/Archive Settings icon.

The Asset Tracking/Archive Settings view opens.



2. If you want to track assets in a non-archive server, in the Online server name text box, type the computer name of the Interplay Engine server and click Add.

The server name is added to the list of configured hosts.

## 5 Site Settings

3. If you want to track assets on an archive server, in the Archive Server name text box, type the computer name of the Interplay Archive Engine.
4. Click Apply Changes.

# Specifying Archive Settings

The Asset Tracking/Archive Settings view lets you select options for how the Interplay Engine operates with the Interplay Archive Engine and the Archive Provider. The view displays different settings, depending on where you are logged in.

If you are logged into an Interplay Archive Engine, the settings include:

- Allow duplicate media files )
  - This option lets you choose whether the Archive Provider archives duplicate versions of the media.
- Allow Metadata Archive
  - This option lets you choose whether the AAF metadata for Avid assets is sent to the tape archive along with the media.

If you are logged into an Interplay Engine, the settings include:

- Archive server name
- Archive Segment size
- Use best effort restore

These settings are described in the following topics. For more information about using an Interplay Archive Engine, see *Avid Interplay Best Practices* and the *Avid Interplay Media Services Setup and User's Guide*.

## Archiving Duplicate Versions of Media

By default, the Archive Provider does not archive duplicate versions of media, however, you can choose to have it do so.

When you archive a master clip, subclip, or sequence for the first time, the Archive Provider automatically archives all the associated media. If you are archiving another subclip or sequence that refers to the original master clip, the Archive Provider does not automatically archive a duplicate version of the associated media. The Archive Provider archives all of the metadata associated with the new subclip or sequence but it does not archive duplicate versions of the media. Selecting “Allow duplicate media file(s)” tells the Archive Provider to create multiple versions of the media files.

The Interplay Archive Engine avoids duplication by default. If you prefer to have the Archive Engine archive duplicate media files, you can use the Interplay Administrator to change the setting.

This setting appears only when you log in to an Archive Engine database.


**To change whether archive operations create duplicate media:**

1. Open the Interplay Administrator and log into the system running the Archive Engine.
2. In the Site Settings section of the Interplay Administrator window, click the Asset Tracking/Archive Settings icon.

The Asset Tracking/Archive Settings view opens.

3. Select the Archive database AvidAM from the database list.

The system displays the Asset Tracking/Archive Settings window for the Interplay Archive Engine.



4. Select one of the following settings for “Allow duplicated media files” option:
  - No — When you archive an Avid asset the first time, the Archive Provider archives all associated media. If you archive other assets that reference the same media, the Archive Provider archives the metadata but does not archive duplicate versions of the associated media (default setting).

## 5 Site Settings

- Yes — The Archive Provider archives the associated media each time you archive an asset. If you delete an asset that references the duplicated media, the system asks if you want to delete the associated media files. If you choose the delete the media, the system deletes all copies of the media.
5. Click Apply Changes.

### Adding AAF Metadata to an Archive

The Asset Tracking/Archive Settings view on the Interplay Archive Engine includes an option labeled “Allow Metadata Archive.” If you select Yes, AAF metadata for Avid assets is sent to the tape archive along with the media. This option requires special implementation by the tape archive vendor. If you select No, only media is sent to tape (the default). For the SGL FlashNet™ solution, keep the default selection No.

This setting appears only when you log in to an Archive Engine database.

### Specifying the Archive Server, Segment Size, and Restore Process

These settings appear when you log in to an Interplay Engine online database (AvidWG). You must set the name of the Archive Engine server. You might need to set the other options, depending on your workflow.

#### To specify Archive settings for an online database:

1. Open the Avid Interplay Administrator and log into the system running the Interplay Engine.
2. In the Site Settings section of the Interplay Administrator window, click the Asset Tracking/Archive Settings icon.

The Asset Tracking/Archive Settings view opens.

3. Select the AvidWG database from the database list.

The Archive Settings area displays these options.



The screenshot shows a dialog box titled "Archive and Restore Settings" with a light gray background. It contains three settings:

- Archive server name:** A text input field containing the value "wgb-flkarchm1".
- Archive Segment size (frames):** A numeric spinner control set to "1,800".
- Use best effort restore:** An unchecked checkbox.

4. In the Archive Settings area, do the following:

- ▶ In the Archive server name text box, type the name of the computer running the Avid Interplay Archive Engine.
- ▶ In the Archive Segment size (frames) text box, type the segment size used for partial restore operations, in frames. The default and minimum value is 1800 frames.



*If you later change the Archive Segment size, the new size applies only to new archives. Partial restores of media that is already archived use the original segment size.*

- ▶ Use best effort restore - if you select this option, a restore process restores as many files as it can without returning errors. This option requires special implementation by supported third-party vendors to ignore any missing files that are no longer in the archive storage. If you do not select this option, then the restore process fails when there are any missing files (the default).



**The “Use best effort restore” option is not supported by all third-party archive vendors. If you select this option and your archive vendor supports it, then a restore process restores as many files as it can without returning errors.**

5. Click Apply Changes at the bottom of the window.

## Setting the Ownership for New Database Folders

The Ownership Behavior view lets you determine how the owner is assigned when a user creates a new Interplay folder in the following applications:

- Interplay Access
- Interplay Assist
- Avid Instinct
- Interplay Window
- Interplay checkin from Avid editing system

By default, the user who creates a folder is set as the owner. As the owner, the user by default has read/write/delete permission on the folder. In Interplay Access, a problem could develop in the following situation:

1. Editor 1 owns a folder named Final that contains a sequence named Final\_Sequence and has read/write/delete permission on the folder.
2. Editor 2 has read/write permission on the folder, but not delete rights.
3. Editor 2 creates a folder named Final\_2 within folder Final, and thus has read/write/delete permission on the new folder.

## 5 Site Settings

4. Editor 2 duplicates Final\_Sequence, moves it into folder Final\_2 and renames it Final\_Sequence\_2. Referenced assets are selected to be displayed in folder Final\_2 (Tools > Options > Filter Settings), so the master clips that make up the sequence are displayed in the folder.
5. Editor 2 deletes Final\_Sequence\_2, its master clips, and its associated media.

As a result, all media for the original Sequence\_Final is also deleted (unless there is a reservation active on the material).

To prevent this situation, you can set an option so that a new folder is owned by the same owner as the parent folder. If this option is set, in the previous example, Editor 2 inherits read/write permissions on the new folder but does not have delete permission and thus cannot delete the sequence or master clips.




*An administrator can change the owner and permissions for a folder after it is created. For more information, see the Avid Interplay Access User's Guide or Help.*

### To specify how ownership is set for new folders:

1. In the Site Settings section of the Interplay Administrator window, click the Ownership Behavior icon.

The Ownership Behavior view opens.



2. Select the database for which you want to set the behavior.
3. Select the option you want.



- “Set creator as owner” is the default.
  - “Set same owner as parent folder” sets the owner of a new folder to be the owner of the folder in which the new folder was created.
4. Click Apply.  
The change takes effect immediately.
  5. To undo your change, click Revert, then click Apply.

## Setting Options for Deletion

The Delete Behavior view let you set options for the Delete dialog box, as described in the following topics:


- [“Understanding the Deletion Process” on page 161](#)
- [“Scheduling the Deletion of Database Assets” on page 166](#)
- [“Setting Options for Deleting Only OMF Media, Only MXF Media, or Both” on page 169](#)
- [“Setting Options for Deleting Locked Media” on page 169](#)

## Understanding the Deletion Process

When you check in a master clip or other Avid asset to Interplay, Interplay stores the original asset in the database and creates named, visible assets in one or more Interplay folders. These visible assets are links to the same original database asset (sometimes called the “real” asset).


If you select to delete assets and media in the Interplay Access Delete dialog box, the deletion process consists of three major parts:

1. Media files for assets that are not reserved are deleted from shared storage.




2. Links for assets that are not reserved or referenced by other assets are deleted from the database.

## 5 Site Settings



3. Database assets (and associated files such as AAF files and QuickTime reference files) are deleted unless they reference online media.


The following illustration shows the completed deletion.



The last part of the process is the part that takes the longest time and places the heaviest load on the Interplay Engine. In addition, this part of the process does not provide immediate feedback, as opposed to media deletion (you can see the files deleted from shared storage) and link deletion (you can see links are deleted from the Access folder structure). Database assets are not displayed in Interplay Access.

### Changes in Interplay v2.4

In Interplay v2.4 and later, the last part of the deletion process (database asset deletion) is disassociated from the first two parts of the deletion process. When the last link to a database asset is deleted, the Interplay Engine moves the last link for the database object to the Orphan Clips folder. This link points to the database asset.



Deletion of the link in the Orphan Clips folder and the database asset takes place during a time span that is set in the Interplay Administrator client application. By default, the time span in the Interplay Administrator is set as 24 hours (00:00 to 00:00). In this case, the database asset deletion takes place at approximately the same time that you run the deletion operation, and links to the database assets might not appear in the Orphan Clips folder because they are deleted almost immediately. The default time span results in the least disruption for established workflows, but it does not lessen the load the deletion operation places on the Interplay Engine.

To take advantage of the improved process and lessen the load on the Interplay Engine, you need to set a custom schedule with one or more time spans (see [“Scheduling the Deletion of Database Assets” on page 166](#)). Scheduling a deletion time span results in a faster initial deletion operation and less impact on other Interplay Engine operations.

Scheduled deletion works similarly on the Interplay Archive Engine. On the Interplay Archive Engine, media is flagged for deletion, but the deletion itself takes place through the third-party archive system.

### Changes to the Orphan Clips Folder



#### **The function of the Orphan Clips folder and the status of its contents changed in Interplay v2.4.**

Previously the Orphan Clips folder contained links for assets deleted or removed from Interplay folders that still referenced media files on shared storage (including unused rendered effects). Now, in addition to these links, the Orphan Clips folder also contains links for assets deleted from Interplay folders whose media files were also deleted.

## 5 Site Settings



*If your deletion time span is set for the default 24-hour period, you might not see links for assets without media in the Orphan Clips folder, because the database assets are deleted at approximately the same time as the asset deletion.*

You can distinguish links that have online media from links that do not have online media by displaying the Media Status column. A red icon indicates media offline. Double-click the column head to sort by the values of the column. Links with offline media are automatically scheduled for deletion.

Media Status	Name
Offline (Red icon)	720p23.9_AVC100_127hours-tlr1_720p...
Offline (Red icon)	720p23.9_AVC100_127hours-tlr1_720p...
Offline (Red icon)	1080p24_1to1_10b_duedate-tlr1_h1080...
Online (Green icon)	WG5-AMS-1.CapMgr04.30
Online (Green icon)	WG5-AMS-1.CapMgr04.29
Online (Green icon)	Short_Leagacy_CC_6_Antq_Road_GBH...

**Kept Media folder:** You can select an option to include deletion of links with online media in the scheduled deletion. If you do not select this option, the scheduled deletion moves any links with online media to a subfolder in the Orphan Clips folder named “Kept Media.” This option is not selected by default, so even if you do not enable custom deletion, the Interplay Engine creates a Kept Media folder when needed. You can manually delete clips and media from this folder at a time that is appropriate for your workflow.

**Failed to Delete folder:** If the deletion process is not able to delete a clip or its media (for example, if a clip is corrupted), the Interplay Engine creates a subfolder in the Orphan Clips folder named “Failed to Delete” and moves assets it could not delete to this folder. You can try to manually delete clips and media from this folder as well, but you might need to determine a different method of deleting these clips and media. For example, check the shared-storage system workspace to make sure the Server Execution User has delete rights.

These folders are useful in two ways:

- It is easier to browse and search a large Orphan Clips folder for assets with online media and assets that cannot be deleted.
- The scheduled deletion process ignores both of these folders, resulting in improved performance.

You can manually delete assets from the Orphan Clips folder at any time.

## Logs for Deleted Media and Metadata

Deletions are logged in two files:

- AvDeletes.log. This log lists information about media deleted from shared storage.
- AvMetaDataDelete.log This log lists information about assets (metadata) deleted from Orphan Clips or any other folder. Scheduled deletions are noted.

The following are examples of AvMetaDataDelete logs:

- When a user deletes metadata that is moved to the Orphan Clips folder:
 

```
[Thu Mar 10 12:12:17 2011] User 'Administrator' on host
'MUC-TReichgr' deleting metadata:
[Thu Mar 10 12:12:17 2011] From '/Projects/Test3/'
[Thu Mar 10 12:12:17 2011] 'LHJU MOUNTIES -Vakantiekamp' handle
1921 moved to Orphan Clips
[Thu Mar 10 12:12:17 2011] 'MOUNTIES - vakantiekamp' handle 1924
moved to Orphan Clips
```
- When a scheduled deletion permanently deletes metadata from the Orphan Clips folder:
 

```
[Tue Mar 08 13:45:00 2011] Scheduled deletion: deleting metadata from
Orphan Clips:
[Tue Mar 08 13:45:00 2011] 'Film BKG.mov' handle 1368 user
'Administrator'
[Tue Mar 08 13:45:00 2011] 'computer BLUE internet NN BG.mov'
handle 1361 user 'Administrator'
```
- When an administrator user permanently deletes metadata from the Orphan Clips folder:
 

```
[Thu Mar 17 20:16:10 2011] User 'Administrator' on host
'MUC-TReichgr' deleting metadata instantly:
[Thu Mar 17 20:16:10 2011] From '/Orphan Clips/'
[Thu Mar 17 20:16:10 2011] 'Aftiteling' handle 2100
```

The AvMove.log file includes entries for links moved to the Kept Media folder.

## New Properties for Deletion

The Interplay v2.4 database includes three new properties that are displayed only for assets in the Orphan Clips folder:

- Date Deleted: Displays the date and time the last link was deleted.
- Deleted By: Displays the user name of the person who deleted the last link.
- Original Path: Displays the folder path for an asset whose last link was deleted.

## 5 Site Settings

To display these properties, an Interplay administrator has to make them available in the Property Layout view. An Interplay Access user has to select the properties for display as entries in the Object Inspector or as columns in the Assets pane. For more information, see the Interplay Access and Interplay Administrator documentation.

### Scheduling the Deletion of Database Assets

You can schedule time spans and other options for deletion of database assets whose links are contained in the Orphan Clips folder in the Interplay Administrator.

The Orphan Clips folder contains two types of links:

- Links for assets deleted or removed from Interplay folders that still reference media files on shared storage (including unused rendered effects). You can delete these links manually (such as in an established delete workflow) or include them in a scheduled deletion.
- Links for assets deleted from Interplay folders whose media files were also deleted. Deletion of these links is automatic but takes place during a scheduled deletion. You can also delete these links manually.

During the scheduled time spans, the Interplay Engine reviews the objects in the Orphan Clips folder and deletes the links, the database assets, and the media (if media deletion is included in the scheduled deletion). At the end of a time span the Interplay Engine keeps a record of where it stopped and if not all eligible assets were deleted, continues from this position at the start of the next time span. This process also takes place if the scheduled deletion is interrupted, such as for system maintenance.

For more information, see [“Understanding the Deletion Process” on page 161](#).

#### **To schedule the deletion of database assets:**

1. In the Site Settings section of the Interplay Administrator window, click the Delete Behavior icon.

The Scheduled Deletion Options section is at the bottom of the view.

Scheduled Deletion Options

Enable custom schedule

Allow scheduled deletions during database backups

Permanently delete assets and associated online media from the Orphan Clips folder

Delay scheduled deletion by at least  days from the asset deletion date

Deletion Time Spans

From  :  to  :

2. In the Scheduled Deletion Options section, select “Enable custom schedule.”

If you do not enable a custom schedule, database asset deletion takes place at approximately the same time that you perform a deletion operation.

If you select “Enable custom schedule,” select options, and later deselect “Enable custom schedule,” the options you selected are disabled, but remain set in case you want to enable them again.

3. Select the options that you want:
  - Allow scheduled deletions during database backups  
By default, a scheduled deletion stops when an Interplay backup begins, and resumes when the backup ends or at the next scheduled deletion. Select this option to allow both processes to operate at the same time.
  - Permanently delete assets and associated online media from the Orphan Clips folder  
If all links for an asset are deleted or removed from Interplay folders, but media for the asset is still online, the last link is moved to the Orphan Clips folder. Select this option if you want to include these links and the media in the scheduled deletion. Otherwise the links and media are moved to the Kept Media folder.


## 5 Site Settings

- Delay scheduled deletion by at least  $x$  days from the asset deletion date

Select this option if you want to delay the scheduled deletion by a specified number of days. You can specify 1 to 30 days. This option gives you the opportunity to review the contents of the Orphan Clips folder before the scheduled deletion. To help determine which links will be deleted, you can check the asset deletion date in the Date Deleted column (see [“New Properties for Deletion”](#) on page 165).

For example, imagine that you selected this option with a time period of 1 day (24 hours), and a deletion is scheduled for 2 a.m. to 4 a.m. It's 6 p.m. Friday, March 25, and you delete a group of assets and media. The assets are moved to the Orphan Clips folder and scheduled for deletion at 2 a.m. Sunday morning, March 27 (32 hours later). This scheduled deletion will include any assets deleted at or before 2 a.m. on Saturday, March 26 (24 hours before the start of the scheduled deletion).

The following diagram illustrates this example.



4. Specify a time span for the deletion.

By default, a 24-hour time span is specified (00:00 to 00:00). This setting means deletion of database assets take place at approximately the same time that the links and media are deleted. You can set a more limited time span, for example, between 2:00 am and 4:00 am, when the Interplay Engine is not being used very much.

One time span must always be present. Each time span is limited to one day (24 hours). If you want to schedule a deletion period that extends from one day to another, such as 11:00 pm to 1:00 am, you need to create two time spans:

- One time span from 23:00 to 23:59
- One time span from 00:00 to 01:00

Click Add Time Span to create more than one time span. Click Remove Time Span to remove the associated time span. Overlapping time spans are not allowed.

5. When you are satisfied with your settings, click Apply.



## Setting Options for Deleting Only OMF Media, Only MXF Media, or Both

If a clip is associated with both OMF and MXF media, you might want to delete only the OMF media or only the MXF media. You can enable an option in the Interplay Administrator so that the Delete dialog box gives users the option of which media format to delete.

### To set an option that allows deleting only OMF media or only MXF media:

1. In the Site Settings section of the Interplay Administrator window, click the Delete Behavior icon.
2. In the OMF media handling section, select “Allow user choice for deleting OMF/MXF media.”
3. Click Apply.

The next time a user logs into Interplay Access and opens the Delete dialog box, the following options are displayed:

- MXF and OMF media (default)
- Only OMF media
- Only MXF media

## Setting Options for Deleting Locked Media

Editors working in an Avid editing application can use the Lock feature to lock a clip. This can cause a problem if the lock is no longer needed and the administrator wants to delete the asset. The administrator can set an option to control how Interplay Access handles locked clips during a Delete operation. The default setting is for Interplay Access to skip any locked files.

### To set an option for deleting locked media:

1. In the Site Settings section of the Interplay Administrator window, click the Delete Behavior icon.
2. In the Locked media handling section, select one of the following options:
  - Allow user choice in Delete dialog: Two options are available in the Delete dialog box: “Skip” and “Force delete.”
  - Always skip (default): In the Delete dialog box, the “Skip” option is shown but cannot be changed.
  - Always force-delete: In the Delete dialog box, the “Force delete” option is shown but cannot be changed.

## 5 Site Settings

Both “Skip” and “Force Delete” options are always active for Interplay Access users with administrative privileges

3. Click Apply to save any changes.

The next time a user logs into Interplay Access and opens the Delete dialog box, the options are active or inactive, depending on the current settings in the Delete Behavior view of the Interplay Administrator.

## Viewing and Setting the Metadata Override Status

The Metadata Override Settings view lets you manage how the Archive Provider handles metadata when an asset is archived more than once. This view appears only when the Interplay Administrator is logged on to an Archive Engine.

By default, the Archive Provider overrides the archived metadata for an Avid asset if you archive the asset again. You can use the Metadata Override feature in Interplay Access to disable metadata override on archived folders, or re-enable it if it is disabled. There is currently no visual indication in Interplay Access whether metadata override is enabled or disabled on a folder.

You can view the metadata override status in the Metadata Override Settings view in the Interplay Administrator. You can also use this view to enable or disable metadata override for a folder.


### **To view whether metadata override is enabled:**

1. In the Site Settings section of the Interplay Administrator window, click the Metadata Override Settings icon.

A folder tree displays the archive database.

- Folders that have metadata override enabled are marked with a blue check mark icon.
- Folders with metadata override disabled are marked with a red x icon.
- Folders marked with a gray icon indicate the inherited setting.

Folders with metadata override disabled are listed in the Locations window.



- (Option) Select a folder in the folder tree to limit the folders displayed in the Locations window to subfolders.

**To enable metadata override:**

- ▶ Select a folder in the folder tree or one or more folders in the Locations window and click Enable Override.

**To disable metadata override:**

- ▶ Select a folder in the folder tree or one or more folders in the Locations window and click Disable Override.



## 6 Application Settings

In the Application settings, you can configure application-specific permissions and options, as described in the following topics:

- [Application Database Settings View](#)
- [Setting Instinct/Assist User Options](#)
- [Pro Tools Plug-Ins Settings](#)

### Application Database Settings View


The Application Database Settings view lets you specify on a database or folder level the settings that are relevant when using an Interplay application.

All files and subfolders of the folder inherit its settings, but you can override the inherited settings for specific files and subfolders. Inherited settings are grayed out. These settings are used as the default for all new folders in the database, and are valid for all users unless they are changed explicitly for a user or user group in the Instinct/Assist User Settings view (see [“Setting Instinct/Assist User Options” on page 188](#)).

The Application Database Settings view has two tabs.

- Editor Settings tab. For a description of options in this tab, see the following topics:
  - [“Setting Options in the Editing Settings Tab” on page 174](#)
  - [“Application Database Settings: Editing Settings Tab” on page 176](#)
- Application Defaults. For a description of options in this tab, see the following topics:
  - [“Setting Audio Mixing Defaults for Access and Assist” on page 182](#)
  - [“Setting the Shotlist Start Timecode for Interplay Access and Interplay Assist” on page 185](#)
  - [“Setting an Automatic Timeout for Interplay Assist and Avid Instinct” on page 186](#)
  - [“Configuring the Frame Locators Display” on page 187](#)

## 6 Application Settings



### Setting Options in the Editing Settings Tab

The Editing Settings tab in the Application Database Settings view includes settings that apply to several different applications. Some settings apply to Interplay Instinct and Interplay Assist, some apply to Interplay Instinct only, and one setting (“Check in bins when closing”) applies only to Avid editing systems such as Media Composer®.

For information about these settings, see [“Application Database Settings: Editing Settings Tab”](#) on page 176.

#### To change the editor database settings in the Editing Settings tab:

1. In the Editing Settings section of the Interplay Administrator window, click the Application Database Settings icon.
2. Click the Editing Settings tab.
3. Select a folder in the database.

If the database icon has a red X, you are not connected. Click the database icon to connect. The database icon shows a green check mark when you are connected. For more information, see [“Viewing General Role Assignments” on page 118](#).

4. Do one of the following:
  - ▶ Select an option from a drop-down list or by clicking an option button.
  - ▶ Type a setting in the text box.

If a setting is grayed out, click the Edit button to enable editing.



5. Click Apply.
 

A notification box tells you whether or not the changes have been successfully applied. Users who are currently logged in need to log out and log in again to see the changes.
6. Click Dismiss to close the notification box.
 

If you do not click Dismiss or the close box, after a few seconds the notification box minimizes to a green bar at the bottom of the dialog box. To view the notification again, click the green bar. The green bar is available for approximately 45 seconds.

#### To undo a setting:

1. Click the red X button.
 

This button appears only if you have explicitly set the value of the setting. Clicking the red X button clears the setting, but does not revert the setting to the previous value.
2. Click Apply.

### Audio Settings for Two NAT or SOT Tracks in Avid Instinct

Avid Instinct version 2.5 and later supports two channels of input for both NAT (natural sound) and SOT (sound-on-tape). The following settings in the Editing Settings tab in the Application Database Settings view apply to this support:

- Audio Patching
- Audio - Source audio patching
- Audio - Storyline audio patching
- Send to Playback - Audio Mixdown Mode
- Audio Effects - Center-Panned Sound on Tape and Voice Over

## 6 Application Settings


These settings are described in “[Application Database Settings: Editing Settings Tab](#)” on [page 176](#). For more information about using these settings, see the *Avid Instinct User’s Guide*.

### Application Database Settings: Editing Settings Tab

You can set options for the Editing Settings tab in the Application Database Settings view as described in the following table. Options apply to Avid Instinct or Avid Interplay Assist unless specified otherwise.

---

#### Application Database Settings: Editing Settings Tab

Option	Setting	Description
Format	Video Format	(Avid Instinct only) Sets the default video format for your sequences. Select a format or select Any. If you select Any, Avid Instinct allows you to select a video format for your sequence when you create a new story.  <i>For HDV projects, select the HD1080i_60 video format.</i>
	Audio Patching	Natural Sound
Audio – Track labels	Sound on Tape	(Avid Instinct only) Lets you specify whether SOT clips should be patched to a single channel or to a two channels when added to the storyline.
	Natural Sound label	(Avid Instinct only) Allows you to specify a name for the NAT track in source clips. The default is NAT.
	Sound on Tape label	(Avid Instinct only) Allows you to specify a name for the SOT track in source clips. The default is SOT.
Audio – Source audio patching	Voice Over label	(Avid Instinct only) Allows you to specify a name for the voice-over track in source clips. The default is VOICE.
	Natural Sound track 1	(Avid Instinct only) Specifies which track of the source clip is mapped to NAT track 1. The default is A1.



---

**Application Database Settings: Editing Settings Tab (Continued)**

<b>Option</b>	<b>Setting</b>	<b>Description</b>
	Natural Sound track 2	(Avid Instinct only) If two channels are selected for NAT, specifies which track of the source clip is mapped to NAT track 2. The default is A4.
	Sound on Tape track 1	(Avid Instinct only) Specifies which track of the source clip is mapped to SOT track 1. The default is A2.
	Sound on Tape track 2	(Avid Instinct only) If two channels are selected for SOT, specifies which track of the source clip is mapped to SOT track 2. The default is A5.
	Voice Over track	(Avid Instinct only) Specifies which track of the source clip is mapped to voice-over sound. The default is A3.
Audio – Storyline audio patching	Natural Sound track 1	(Avid Instinct only) Specifies which track of the output sequence is mapped to NAT track 1. The default is A1.
	Natural Sound track 2	(Avid Instinct only) If two channels are selected for NAT, specifies which track of the output sequence is mapped to NAT track 2. The default is A4.
	Sound on Tape track 1	(Avid Instinct only) Specifies which track of the output sequence is mapped to SOT track 1. The default is A2.
	Sound on Tape track 2	(Avid Instinct only) If two channels are selected for SOT, specifies which track of the output sequence is mapped to SOT track 2. The default is A5.
	Voice Over track	(Avid Instinct only) Specifies which track of the output sequence is mapped to voice-over sound. The default is A3.

---

### Application Database Settings: Editing Settings Tab (Continued)

---

Option	Setting	Description
Audio – general settings	Media Creation workspace	<p>Sets the workspace location used for media clips created by Instinct and Assist users, such as voice-over recordings and clips created during send-to-playback operations.</p> <p>To view a list of available workspaces, the user logged into the Interplay Administrator must have a matching username and password on the Avid shared-storage system. The list shows all workspaces to which the logged-in user has write access.</p>
	Audio sample rate	<p>Sets the audio sample rate for audio clips created in Avid Instinct and Interplay Assist. The sample rate is used in send-to-playback operations, and it must match the setting on your playback device (for example, an Avid AirSpeed®). The default sample rate for DV resolutions is 48 kHz. This setting is not changeable.</p>
	Sample bit depth	<p>Sets the sample bit depth for audio clips created in Avid Instinct and Interplay Assist, such as voice-over recordings and audio mixdowns. The more bits used to sample the audio, the more accurately the amplitude is represented by the clip. The sample rate is used in send-to-playback operations, and it must match the setting on your playback device (for example, an Avid AirSpeed). The default is 16 bits.</p>
	Ducking [-dB]	<p>(Avid Instinct only) Allows you to specify the amount of audio ducking (automatic lowering of audio gain in background audio). The default is 12 dB.</p>
	Audio file format	<p>Sets the audio file format to PCM. Not changeable.</p>




---

### Application Database Settings: Editing Settings Tab (Continued)

Option	Setting	Description
	Audio Mixdown Mode	<p>Sets the mixdown mode used for send-to-playback operations:</p> <ul style="list-style-type: none"><li>• Mono — Maps to a center pan, which creates a mono mixdown of all audio tracks and outputs the resulting track to two channels when sent to playback. This results in two identical channels of audio, each containing the original audio tracks.</li><li>• Stereo — Maps to a left/right alternating pan (odd tracks on one channel, even tracks on the other channel), creates a stereo mixdown of all audio tracks, and outputs the resulting two tracks to two channels when sent to playback. This results in two channels of audio. For Avid Instinct, the default mapping is NAT/VOICE tracks (A1/A3) on one channel and the SOT track (A2) on the other channel. You specify how tracks are mapped in the Audio - Storyline Audio Patching settings.</li><li>• Direct Out — Does not combine audio in any way; all audio tracks remain as they are in the source media, which creates separate output channels for each audio track in the source media when it is sent to playback. Select this option to retain the greatest flexibility to do further audio manipulation after the source media is sent to the playback device.</li></ul> <p>The default mixdown mode is Mono.</p>


---

**Application Database Settings: Editing Settings Tab (Continued)**

Option	Setting	Description
	Audio Target Resolution	<p>Sets an audio resolution for output to a playback device. Currently, the only option is PCM.</p> <p>Sample Rate and Bit Depth: sets the resolution of the source audio for audio mixdowns.</p> <p> <i>If dynamic relink is enabled, you must set the audio target resolution to PCM and select a Sample Rate and Bit Depth.</i></p> <p>If the working resolution differs from the target resolution, audio clips relink to the target resolution when they are sent to playback. However, if the settings on the playback device differ from the target resolution, the clips convert to the playback resolution after relinking.</p>
	Prepare Editor Sequences for Review	For future use.
Audio Effects	Dissolve Duration (frames)	(Avid Instinct only) Sets the length of an audio dissolve in frames. For example, to create a default dissolve of 2 frames (the default), type 2.
	Center-Panned Sound on Tape and Voice Over	(Avid Instinct only) If enabled, maps SOT and VOICE sounds as center-panned (played on both channels). This effect applies to both Mono and Stereo Mixdown modes.
Auto Reservation	Duration [h]	<p>Allows you to set a default duration (in hours) for auto reservations. If you do not want auto reservation on a folder, set the duration to zero. The default duration is 24 hours.</p> <p>There are two situations that trigger an automatic reservation:</p> <ul style="list-style-type: none"> <li>• Capturing a master clip to the Interplay Window</li> <li>• Checking in a new or modified asset from a bin</li> </ul>

---

### Application Database Settings: Editing Settings Tab (Continued)

Option	Setting	Description
Bins	Check in bins when closing	(Avid editing systems only) Allows you to set the default behavior for checking in media objects from open bins to the Interplay database when closing your Avid editing application. The default is “Ask user.”  <i>This setting does not apply to Avid Instinct or Avid Assist.</i>

---


### Setting Audio Mixing Defaults for Access and Assist

The Audio Mixing Defaults in the Application Defaults tab apply to Interplay Access and Interplay Assist.

- For Interplay Access, the settings apply to the Audio Mixer controls, which let you enable and mute tracks and adjust volume. Adjustments that you make with these controls apply only when you play Avid assets and file assets in Interplay Access. For more information, see the *Avid Interplay Access User’s Guide*.
- For Interplay Assist, the settings apply to the Local Audio Mixing controls, which let you edit audio settings for clips or subclips that you load in the Monitor. Adjustments that you make with these controls apply only when you play clips, subclips, or shotlists in Interplay Assist. For more information, see the *Avid Interplay Assist User’s Guide*.

These settings apply to the entire database only. You cannot set them for individual folders.

The following illustration shows audio tracks 1 through 16 enabled, with left/right alternating pan (the initial default setting). Buttons for enabled tracks display a green icon.



**To set audio mixing defaults for Interplay Access and Interplay Assist:**

1. In the Application Settings section of the Interplay Administrator window, click the Application Database Settings icon.
2. Click the Application Defaults tab.
3. Select the Enable Audio Mixing Defaults option so that a green check mark is displayed.
4. For each track that you want to enable, click the corresponding button, so that the button has a green icon.

## 6 Application Settings

5. For each track, select Left, Mono, or Right to assign the track to an output channel (pan setting).
6. Click Apply.


## Sending a Source to Playback in Interplay Assist

The target settings for Send to Playback depend on the folder in which a loaded shotlist exists. The following sections describe how Interplay Assist uses target settings when sending a source to playback.

### Settings in the Interplay Administrator

You set the target audio and video resolution for a folder in the Interplay Administrator. If you have Dynamic Relink enabled in a workgroup, settings for audio and video target resolutions are enabled and required in the Interplay Administrator. You should set target resolutions for the root folder. Subfolders inherit this setting. You can set different target resolutions for subfolders that override the settings inherited from the root folder.

The following illustration shows DNxHD 1080 115-120-145 and PCM set as target resolutions on the database root folder.





## Sending a Source to Playback

If you send a source to playback (a clip, subclip, or sequence) and a shotlist is open, the send to playback operation uses the target resolution of the folder that holds the shotlist.

If a shotlist is not open, the send to playback operation uses the target resolution that is set at the database root. If this resolution is not what you want to use for the source, you need to create or open a shotlist in a folder that has the desired settings.

To make it easier to select target resolution settings to use when sending a Source to playback, you can create a set of template shotlists and folders, each in a folder that has been set with the target resolutions. You can then do one or both of the following:

- Create shortcuts to the folders
- Create the template shotlists with names that are easily searched, for example, TRES\_DNxHD1080, TRES\_MPEG50, and so on.

Then, before you send a source to playback, use a shortcut or search to load the appropriate shotlist.

## Setting the Shotlist Start Timecode for Interplay Access and Interplay Assist

An administrator can set the default starting timecode for shotlists that are created in Interplay Access or Interplay Assist. The default starting timecode for shotlists is 01;00;00;00 (drop frame) or 01:00:00:00 (non-drop frame). For example, you can use this setting to change the starting timecode hour from 01 to 00.

This setting applies to the entire database only. You cannot set it for individual folders.

Interplay Access and Interplay Assist determine the format of the timecode differently:

- For Interplay Access, the timecode format is determined by the first clip in the shotlist. You cannot mix drop-frame and non-drop-frame clips in the same shotlist.
- For Interplay Assist, you set the default starting timecode as Drop Frame or Non-Drop Frame in the Interplay Administrator. If you select Drop Frame, and if the frame rate of the first clip in the shotlist supports drop-frame timecode (for example, 29.97 fps), the timecode will be drop-frame. If you select Non-Drop Frame, or the first clip in the shotlist does not support drop-frame timecode, the default timecode will be non-drop-frame. You can mix drop-frame and non-drop-frame clips in the same shotlist.



*Interplay Assist users can change the starting timecode for an individual shotlist by using the command `Edit > Edit Shotlist Start Timecode`.*

## 6 Application Settings

### To set the shotlist start timecode:

1. Start Interplay Administrator and log on to the database for which you want to set the shotlist start timecode.
2. In the Application Settings section of the Interplay Administrator window, click the Application Database Settings icon.
3. Click the Application Defaults tab.
4. Select the database (AvidWG).
5. For the Shotlist Start Timecode option, enter the timecode in the format HH:MM:SS.  
You cannot enter a default starting frame.
6. For Interplay Assist, specify the Default NTSC Shotlist Format as Drop Frame or Non-Drop Frame.
7. Click Apply.

## Setting an Automatic Timeout for Interplay Assist and Avid Instinct

An Interplay administrator has the option of letting Interplay Assist and Avid Instinct automatically time out after a specified period of inactivity. This feature helps in license management, because it enables an unused license to be freed up without the administrator manually finding and closing inactive applications on user desktops.

If a timeout period is set, and the application does not detect any activity during that period, the application displays a message that asks if you want to quit. Click Yes to quit, or click No to keep the application open. If you do not click Yes or No, the application quits in twenty seconds.

The default setting is one hour. This setting applies to the entire database.

### To set the timeout period:

1. Start Interplay Administrator and log on to the database for which you want to set the automatic timeout.
2. In the Application Settings section of the Interplay Administrator, click the Application Database Settings icon.
3. Click the Application Defaults tab.
4. Select the database (AvidWG).

- In the Assist/Instinct - Defaults section, enter a value in hours for the Automatic Timeout option. Decimal values are allowed. For example, for a timeout period of one and a half hours, enter:

1.5

If you do not want a timeout period, enter 0 (zero).

- Click Apply.

The timeout period begins the next time you launch the application.

## Configuring the Frame Locators Display

The Frame Locators tab in the Object Inspector displays information about locators associated with an Avid asset. Administrators and users can configure which attributes (as columns) are displayed in the Frame Locators tab. Administrators can select a default set of columns in the Interplay Administrator, and users can change the default settings in Interplay Access.

You can display the following columns:

Frame Locators Column	Default Setting in Interplay Administrator
Timecode	Always selected
Comment	Always selected
Track	Selected by default
User	Selected by default
Color	Selected by default
UID (Unique Identifier)	Selected by default

The ability to configure which columns you display can be useful if you use locator information in another application. You can export locator information in various formats or you can copy rows of information and paste them into another application by using your desktop copy and paste commands.

### To configure the default display in the Interplay Administrator:

- Open the Interplay Administrator and log in to the database for which you want to set the default display.
- In the Application Settings section, click Application Database Settings.
- Click the Application Defaults tab.

## 6 Application Settings

4. In the Access Frame Locators View section, select the columns that you want to display in the Frame Locators tab.

The Timecode and Comment columns are always displayed.

5. Click Apply.

### **To override the default display in Interplay Access:**


1. Open Interplay Access and log in to a database.
2. Select Preferences > Options
3. Click the View Settings tab.
4. In the Frame Locators View section, select “Use local column configuration.”
5. Select the columns you want to display, or deselect the columns you do not want to display, then click OK.
6. Refresh Interplay Access (select View > Refresh or perform an action).

## Setting Instinct/Assist User Options

In the Instinct/Assist User Settings view, you can set permissions for various editing functions on the group or user level (working resolutions for video and audio are not available for groups). These settings apply to all folders in the database, so in some cases the settings apply to users on Avid editing systems (NewsCutter, Media Composer, and Symphony) who are checking Avid assets into the Interplay database.

For information about these settings, see [“Instinct/Assist User Settings” on page 190](#).

The settings in the following illustration are for an Instinct or Assist user who has permission to use only low-resolution MPEG2 media. In this example, most settings are grayed out, which indicate that they are inherited from the user group. For this user, the working video resolution is MPEG2-MPML NTSC and the “Can use higher resolutions” setting is No. The working audio resolution is MP2.




### To change the Instinct/Assist User settings:

1. In the Application Settings section of the Interplay Administrator window, click the Instinct/Assist User Settings icon.
2. In the Users tree on the left, select a group of users or an individual user.  
The settings for the selected user or user group area are displayed in the pane on the right.
3. Do one of the following:
  - ▶ Select an option from the drop-down list or by clicking an option button.
  - ▶ Type a setting in the text box.

## 6 Application Settings

If a setting is grayed out (inherited), click the Edit button to enable editing



4. Select among the following options for each setting:

Option	Description
Inherited	The user inherits this setting from the group it is a part of.
Yes	Grants the user this setting.
No	Denies the user this setting.

If you select Inherited, and then click Apply, the option changes to the inherited setting and the options are grayed out.

5. Click Apply.

A notification box tells you whether or not the changes have been successfully applied. Users who are currently logged on need to log out and log in again to see the changes.

6. Click Dismiss to close the notification box.

If you do not click Dismiss or the close box, after a few seconds the notification box minimizes to a green bar at the bottom of the dialog box. To view the notification again, click the green bar. The green bar is available for approximately 45 seconds.

### To undo a setting:

1. Click the red X button.

This button appears only if you have explicitly set the value of the setting. Clicking the red X button clears the setting, but does not revert the setting to the previous value.

2. Click Apply.

## Instinct/Assist User Settings

The following table describes options for the Instinct/Assist User Settings. The table includes columns that specify which applications the setting applies to.

<b>Setting</b>	<b>Instinct</b>	<b>Assist</b>	<b>Access</b>	<b>Avid editing applications</b>	<b>Description</b>
Can send to playback	x	x			If yes, allows the selected user or group to send material to a playback device.
Can modify column properties	x	x		x	If yes, allows the selected user or group to modify the properties of an asset (such as the name or a comment). If an editing application user regularly checks assets into Interplay, select “yes.”  Administrators and folder owners have this right set by default. Other users who have this right must also have a read/write or read/write/delete role for at least one folder that contains the asset.
Can create new column properties	x	x		x	If yes, allows the selected user or group to add new properties to an asset. If an editing application user regularly checks assets into Interplay, select “yes.”  Administrators and folder owners have this right set by default. Other users who have this right must also have a read/write or read/write/delete role for at least one folder that contains the asset.
Can see other users’ logs	x	x			If yes, allows the selected user or group to see locators and restrictions set by other users.

## 6 Application Settings

Setting	Instinct	Assist	Access	Avid editing applications	Description
Can use higher resolutions	x	x			<p>If yes, allows the selected user or group to work with a higher quality than the working resolution for video and audio clips if the working resolution is not available. If this option is set to No and the only available resolution is higher than the working resolution, the user sees Media Offline in the Video monitor.</p> <p>If you want a user to work with any available media, select “yes” for this option and “Can use lower resolutions.”</p>
Can use lower resolutions	x	x			<p>If yes, allows the selected user or group to work with a lower quality for video and audio clips than the working resolution if the working resolution is not available. If this option is set to No and the only available resolution is lower than the working resolution, the user sees Media Offline in the Video monitor.</p> <p>If you want a user to work with any available media, select “yes” for this option and “Can use higher resolutions.”</p>



Setting	Instinct	Assist	Access	Avid editing applications	Description
Can create locators		x	x	x	<p>If yes, allows the selected user or group to create locators. If no, a user of an Avid editing application can still create locators for an asset, but can check in only the asset, not the locator metadata (an error message is displayed).</p> <p>In most cases, if you want a user to create locators, select "yes" for both "Can create locators" and "Can modify locators." Both settings are needed because adding text is one aspect of modifying a locator.</p> <p>Administrators and owners have the ability to create locators by default. Other users must have "Can create locators" set to "yes" and must also have a read/write or read/write/delete role for at least one folder that contains the asset.</p>
Can modify locators		x	x	x	<p>If yes, allows the selected user or group to modify or delete locators. If no, a user of an Avid editing application can still modify locators on an asset, but can check in only the asset, not the locator metadata (an error message is displayed).</p> <p>Administrators and owners have the ability to modify locators by default. Other users must have "Can modify locators" set to "yes" and must also have a read/write or read/write/delete role for at least one folder that contains the asset.</p>

## 6 Application Settings

Setting	Instinct	Assist	Access	Avid editing applications	Description
Can create restrictions		x			<p>If yes, allows the selected user or group to mark a section of a clip with a restriction locator. In most cases, if you want a user to create restrictions, select “yes” for both “Can create restrictions” and “Can modify restrictions.” Adding text is considered modifying a restriction.</p> <p>Administrators and owners have this right set by default. Other users who have this right must also have a read/write or read/write/delete role for at least one folder that contains the asset.</p>
Can modify restrictions		x			<p>If yes, allows the selected user or group to modify a restriction.</p> <p>Administrators and owners have this right set by default. Other users who have this right must also have a read/write or read/write/delete role for at least one folder that contains the asset.</p>
Video Settings: Working Resolution	x	x			<p>If Dynamic Relink is enabled, specifies the default working video resolution for the selected user. You cannot apply this setting to a group.</p>
Audio Settings: Working Resolution	x	x			<p>If Dynamic Relink is enabled, specifies the default working audio resolution for the selected user. If the working resolution is set to PCM, you can select a sample rate and a bit depth for audio clips. You cannot apply this setting to a group.</p>

# Pro Tools Plug-Ins Settings

You can use Interplay Pro Tools Plug-ins to pass audio files back and forth between Avid video editing systems and Pro Tools audio editing and mixing systems.

The following topics include information for installing and configuring the plug-ins. For details on using these plug-ins, see the *Avid Interplay Best Practices* guide.

## Installing the Pro Tools Plug-Ins for Interplay

Before you use the Avid editing application to check files into Interplay for Pro Tools, you must install Interplay Access and the Pro Tools Interplay Option on the Pro Tools system. The installation software adds the following plug-ins to the Application Settings section in the Interplay Administrator on the Pro Tools system.

- Pro Tools Import Settings
- Editor Export Settings for Pro Tools
- Pro Tools User Settings

You can install Interplay Access and the Pro Tools Interplay Option on any Windows system that you want to use to configure the import and export settings. For example, you can install the Pro Tools option on the Interplay Engine server.

For information on installing the Pro Tools Interplay Option, see the *Avid Interplay Software Installation and Configuration Guide*.

## Configuring the Pro Tools Import Plug-In

The settings that you configure in the Pro Tools Import plug-in are used by a Pro Tools system when a Pro Tools editor performs an import. You can select import settings for the entire database or for particular folders. All files and subfolders in the parent folder inherit the settings of the parent folder.

If you do not configure Import Plug-in settings for a particular folder, the Pro Tools editor can modify those settings in the New Session dialog box and the Pro Tools AAF Import dialog box during the import into Pro Tools.

### **To configure the Pro Tools Import settings:**

1. In the Application Settings section of the Interplay Administrator window, click the Pro Tools Import Settings icon.


The Pro Tools Import Settings view opens.

2. Select the database or folder for which you want to configure import settings.

## 6 Application Settings

If the database icon has a red X, you are not connected. Click the database icon to connect. The database icon shows a green check mark when you are connected. For more information, see [“Viewing General Role Assignments” on page 118](#).

The following illustration shows the Pro Tools Import Settings view. In this example, the settings are configured for the entire database AvidWG. You can also select an individual folder and set specific values for that folder and its subfolders. Settings are inherited from the parent folder.



3. Select the values that Pro Tools should use to import the files and create a new session. For more information about these settings, see the Pro Tools documentation.
4. Click Apply.

## Configuring the Pro Tools Export Plug-In

The settings that you configure in the Pro Tools Export plug-in are used by an Avid editing application when an editor performs an audio export. You can select export settings for the entire database or for particular folders. All files and subfolders in the parent folder inherit the settings of the parent folder.

If you do not configure Export Plug-in settings for a particular folder, the Avid editing application displays the Pro Tools Export Settings dialog box when you perform the “Check In to Interplay for Pro Tools” operation to that folder. You can specify the settings for that particular export in the dialog box.

### To configure the Editor Export Settings for Pro Tools:


1. In the Application Settings section of the Interplay Administrator window, click the Editor Export Settings for Pro Tools icon.

The Editor Export Settings for Pro Tools view opens.

2. Select the database or folder for which you want to configure export settings.

If the database icon has a red X, you are not connected. Click the database icon to connect. The database icon shows a green check mark when you are connected. For more information, see [“Viewing General Role Assignments” on page 118](#).

The following illustration shows the settings for a project folder named “PR3 NTSC 30i.” You can modify the settings for any folder in the hierarchy. Subfolders inherit settings.



## 6 Application Settings

3. Select options as described in the following table.

Category	Option	Description
Video Details	Transcode Video Resolution	The Avid editing application uses this value to perform a video mixdown when you select the Video Mixdown option for a “Check In to Interplay for Pro Tools” operation.  The application might also use the value when you perform a “link to existing media” export. For more information, see the <i>Avid Interplay Best Practices</i> .
Audio Details	Audio Mixdown	Specifies whether to include an audio mixdown with each export. Available options are No Mixdown, Stereo, and Mono.
	Convert Audio Sample Rate	Specifies the audio sample rate for the export. The Project option refers to the current Avid editor project setting.
	Convert Audio Bit Depth	Specifies the audio bit depth for the export. The Project option refers to the current Avid editor project setting.

4. Click Apply.


Changes take effect for the Avid editing application the next time the Avid editor logs into the Interplay Window. The editor might have to log out of the Interplay Window and log back in.

## Configuring the Pro Tools User Settings Plug-In

This option is for future use.

## 7 Avid Interplay Services

The Avid Interplay Services settings include the Workgroup Properties and Service Configuration views, which are identical to parts of the Avid Service Framework. For example, the following illustration shows the Service Configuration view examining the Avid Interplay Media Indexer settings for a computer in the Interplay workgroup. You can use the Service Configuration view to configure services such as the Interplay Media Indexers for all the clients in your workgroup from one computer.



For more information about the Avid Interplay Services, see the *Avid Service Framework User's Guide* or *Avid Interplay Best Practices*.

## 7 Avid Interplay Services



*Avid Workgroup Properties and Avid Service Configuration are also available from the Interplay Access View menu.*



# 8 Troubleshooting

The following topics provide information for troubleshooting problems with the Avid Interplay Engine server:

- [Troubleshooting Login Problems](#)
- [Troubleshooting Client Connection Problems](#)
- [Optimizing Avid Interplay Performance](#)
- [Troubleshooting Firewalls and Avid Interplay](#)
- [Troubleshooting the Server Execution User Account](#)
- [Shutting Down or Locking the Server Process](#)

## Troubleshooting Login Problems

If you are not able to log in to the Interplay Administrator even when you are sure you provided a correct user name and password, verify if the Central Configuration Server for the server is set correctly. For information about the Central Configuration Server, see [“Understanding the Central Configuration Server” on page 93](#).

**To verify if the Central Configuration Server is set correctly:**

1. Click Start, then click Run.
2. Type `regedit` in the text box.

The Registry Editor opens.

3. Navigate to the following folder:

(32-bit OS) HKEY\_LOCAL\_MACHINE\Software\Avid Technology\  
Workgroup\Avid Workgroup\DatabaseServer

(64-bit OS) HKEY\_LOCAL\_MACHINE\Software\Wow6432Node\Avid Technology\  
Workgroup\Avid Workgroup\DatabaseServer

The string value CMS should specify the computer name of the Central Configuration Server.

4. If this value is not correct, shut down the Avid Interplay Engine by locking the server (see [“Locking and Unlocking the Server” on page 84](#)).

5. In the Registry Editor, double-click CMS, type a valid entry, and click OK.
6. Unlock the server.

# Troubleshooting Client Connection Problems

This topic provides suggestions for settings to check if a client system is not connecting properly.

## Network Configuration

- Check the TCP/IP connection by typing `ping <servername>` in the Command Prompt on the client.

## Server Settings

- Check if there is a user account for the user. See [“Managing Users, User Groups, and User Rights” on page 108](#).
- Check if the password is expired. See [“Viewing and Setting Attributes” on page 112](#).
- Check that the user has access to the database (a role other than No Access).
- Make sure the user authorization provider includes the user account. See [“Setting User Authentication Providers and Importing Users” on page 98](#).

## Client Settings

- Reinstall Interplay Access. This client application hosts Interplay Access, Interplay Administrator, and the connection package for any connection to Interplay.

# Optimizing Avid Interplay Performance

This topic provides some basic items to check if you are running into unexplained slowness (either server or client side) with Avid Interplay:

- Make sure that the server meets the current specifications. See the *Avid Interplay ReadMe*.
- Make sure that the client is running on a system that meets specifications.
- Run the client from the server machine.

If Interplay Access runs well on the server machine, it might indicate that the other clients are communicating slowly with the server because of a network problem. Start the client on the server machine and see if you have the same problems.

- Check for other processes running on the server machine.

Most installations should run the Avid Interplay Engine on a dedicated machine. If you are relying on the server machine to perform other duties as well, you might have performance issues. For example, some virus scanners can lock files on a server, and the Avid Interplay Engine waits until the file is unlocked before it can be moved, renamed, deleted, and so on.

- Check the speed of the LAN between the Avid Interplay Engine and the shared storage server.

Make sure that the Avid Interplay Engine and the Avid shared-storage server are connected appropriately; for example, the Avid Interplay Engine needs to read the files to create thumbnails. If the connection is slow, performance can drop.

- Check the speed of file operations of the Avid Interplay Engine on the shared storage server.

Make sure that the Avid Interplay Engine can move data quickly on the Avid shared-storage system. Log in to the Interplay Engine server and use Windows Explorer to transfer files from an Avid shared-storage workspace to the Interplay Engine server. The speed performance of these operations should be independent of file size and instantaneous. Make sure the connectivity and credentials are correct.

## Troubleshooting Firewalls and Avid Interplay

Firewalls on client machines interfere with Avid Interplay's TCP/IP communications.

### Symptoms

- The list of servers does not appear, for example, when you are connecting to a new database.
- Connection establishment to the server fails.

### Cause

These problems can be caused by personal firewalls installed on the client machine. A typical example for such a firewall is ZoneAlarm<sup>®</sup> from ZoneLabs<sup>™</sup> or the Windows XP firewall.

These applications intercept all outgoing and incoming network traffic and decide whether to let the traffic go through or block it. The effect is that applications like Avid Interplay fail to connect to their servers.

## 8 Troubleshooting

Typically when the client looks for available Avid Interplay Engines in the network, no servers can be retrieved. When the client is looking for servers, a UDP broadcast is sent out on port 8321.

### Solution

Usually these personal firewalls can be configured to allow all network traffic for specific applications. This should be done for Avid Interplay locally or for Internet access depending on which servers Avid Interplay should connect to.

For information about ports used by Avid Interplay, see [“Required TCP/IP Ports” on page 241](#) and [“Interplay Port Usage”](#) in the *Avid Interplay Software Installation and Configuration Guide*.

## Troubleshooting the Server Execution User Account

The Server Execution User is a Windows operating system user account that is used only to run the Interplay Engine processes. You specify the user name and password for the Server Execution User when you install the Interplay Engine on the server. The following topics provide more information about the Server Execution User account and information about how to recreate the account.



*The Server Execution User account is different from the Interplay Administrator account. The Server Execution User account is used to run the Interplay Engine processes. The Interplay Administrator account is used to manage users and the database.*

The following topics provide more information about the Server Execution User account:

- [Creating the Server Execution User Account](#)
- [Determining the Server Execution User Name](#)
- [Re-creating the Server Execution User](#)

## Creating the Server Execution User Account

When you install the Interplay Engine software you must specify the user name and password of the Server Execution User account. The Server Execution User is a Windows operating system user account that is used only to run the Interplay Engine processes.



*You should always use the Custom install option when installing the Interplay Engine software so that you can specify the Server Execution User.*

You have the following options for creating the Server Execution User:

- If your Interplay system is joined to a Windows domain, you can create a domain user (for example, “IPEngine”). The Interplay Engine installer will associate the appropriate permissions with the account. If you want to run the Avid Interplay Engine within your domain and also want to automatically make use of domain user management, such as Windows Domain or LDAP, you must specify a domain user as the Server Execution User.

For Interplay Engine failover cluster systems, you must specify a Windows domain user.

- You have the option of allowing the Interplay Engine installer to create the account. Select a name before the installation and specify the name and a password during the installation. The installer will create a local user in the Administrators group with the appropriate permissions.
- You can also create a local Administrator account manually and specify that account during the installation. The account must have local administration rights on the operating system for the Interplay Engine server (both nodes on a cluster system). The account must have the following local security policy settings set to enabled:
  - Act as part of the operating system
  - Back up files and directories
  - Restore files and directories
  - Adjust memory quotas for a process
  - Log on as a service
  - Increase scheduling priorities
  - Manage auditing and security log
  - Impersonate a client after authentication
  - Debug programs

An account with an identical user name and password must have read/write access to the Avid shared storage workspaces that contain media (including the workspace used for file asset sources in a split database). Use the Avid ISIS or Avid Unity MediaNetwork Administration tool to create this account.



**When you install the Interplay Engine or the Interplay Archive Engine, do not select the default Server Execution User. Create a custom user instead. The default user account is AVID\_WORKGROUP\_USER. Do not use this account.**

Ideally the Server Execution user should be an account that users do not use to log onto the system. This prevents accidental changes to the Server User Account during normal administration duties. For example, if someone changes the password by mistake, users might not be able to access the Interplay database.

## 8 Troubleshooting

For security reasons, do not use the Interplay Engine server operating system Administrator account. Create a unique account that you use only as the Server Execution User. For example, you can create an administrative account called “IPEngine.” Avoiding the word Administrator can help indicate that this account is not used for normal administrative tasks.



*The Server Execution User account is different from the Interplay Administrator account. The Server Execution User account is used to run the Interplay Engine processes. The Interplay Administrator account is used to manage users and the database.*

### Determining the Server Execution User Name

If necessary, you can check the user name of the Server Execution User account.

#### To determine the Server Execution User name:

1. Right-click My Computer and select Manage.
2. Expand the Services and Applications branch, then click Services.
3. Right-click Avid Workgroup TCP COM Bridge and select Properties.
4. Click the Log On tab.

The Log On tab contains the name of the Server Execution User.

On a cluster system, the Server Execution User name and password must match the Windows user account that is running the cluster service. On a cluster system, perform the next step.

5. (Cluster only) In the list of services, right-click Cluster Service, select Properties, and click the Log On tab. This is the Windows user account that is running the Cluster Service. If this account does not match the Avid Workgroup TCP COM Bridge account and the Avid Workgroup Engine Monitor account, do one of the following:
  - Run the cluster-aware version of the NXNServerUser tool (see [“Re-creating the Server Execution User” on page 207](#)).
  - Use the Custom install option when you upgrade the Interplay Engine software.
6. (Cluster only) In the list of services, right-click Avid Workgroup Engine Monitor, select Properties, and click the Log On tab. This is the Windows user account that is running the Avid Workgroup Engine Monitor service. If this account does not match the Avid Workgroup TCP COM Bridge account and the Cluster Service account, do one of the following:
  - Run the cluster-aware version of the NXNServerUser tool (see [“Re-creating the Server Execution User” on page 207](#)).
  - Use the Custom install option when you upgrade the Interplay Engine software.

See the *Avid Interplay ReadMe* for more information about upgrading and troubleshooting a cluster system.

## Re-creating the Server Execution User

If you need to re-create the Server Execution User, use the NxNServerUser.exe tool.

### To re-create the Server Execution User account:

1. Run the tool NxNServerUser.exe on the Avid Interplay Engine server.

The tool is located in the following directory on the Avid Interplay Installer DVD:

Installers\AssetMgr\Tools\NxNServerUser

2. Select Custom User.
3. Type the name, such as MYDOMAIN\IPEngine, and the password of the account.

Make sure that this name exactly matches the user name and password of an account in the Avid shared-storage Administration tool that has read/write access to the appropriate workspaces (see [“Creating the Server Execution User Account” on page 204](#)).



*Make sure that you use the correct password for the specified user because the tool cannot verify the password.*

The tool changes the execution user settings for the following servers and services:

- Avid Interplay Engine Server: The Avid Interplay Engine Server runs under the specified account. The NxNServerUser tool changes the corresponding DCOM settings. You can verify that the new user has been set using the dcomcnfg tool as described in [“Avid Interplay Engine Server” on page 242](#).
- Avid Interplay TCP/COM Bridge: The Avid Interplay TCP/COM Bridge Service runs under the specified account. You can verify that the new user has been set in the service control panel tool as described in [“Required TCP/IP Ports” on page 241](#).

## 8 Troubleshooting

- Impersonation of Apache® Modules: The Apache modules that need to access files on the file server are impersonated to the specified user account (see [“Avid Workgroup HTTP Server” on page 284](#) and [“Avid Workgroup Preview Server Service” on page 285](#)). You can verify that the new user and the encrypted password has been set in the following registry keys:
    - (32-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionUser
    - (32-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionSettings
    - (64-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Wow6432Node\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionUser
    - (64-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Wow6432Node\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionSettings
  - (Cluster Only) Avid Interplay Engine Monitor: The Avid Interplay Engine Monitor Service runs under the specified account. You can verify that the new user has been set in the service control panel.
  - (Cluster Only): Cluster Service: The Windows Cluster Service runs under the specified account. You can verify that the new user has been set in the service control panel.
4. Restart the server.

The Avid Interplay Engine processes have all necessary access rights.

## Shutting Down or Locking the Server Process

You might need to shut down or lock the Avid Interplay Engine Server process in certain circumstances, such as low disk space conditions (see [“Moving a Database Under Low Disk Space Conditions” on page 78](#)). For more information about the process, see [“Avid Interplay Engine Server” on page 242](#).

**To shut down or lock the Avid Interplay Engine Server process, do one of the following:**

- ▶ Lock the server using NxNServerLock.exe in the Avid Interplay Engine installation directory.
- ▶ Lock the server using the Lock Server view in the Interplay Administrator. See [“Locking and Unlocking the Server” on page 84](#).
- ▶ Shut down the server using NxNServerShutdown.exe in the Avid Interplay Engine installation directory.



# 9

## Configuring Interplay for a Split Database

An Interplay database includes a metadata database and a file repository (for file assets). If you do not have adequate local storage for your Interplay database, you can configure (or “split”) the Interplay database so that the metadata database remains on the Interplay Engine server and the file repository resides on an Avid shared storage workspace.

If your Interplay system uses a cluster configuration, it includes a large amount of local storage space, and a split database is probably not necessary.



*Storing the file repository of a large Interplay database on ISIS shared storage in a split-database configuration might reduce the maximum number of media files you can store on the ISIS system. If the number of assets in your Interplay database might exceed 50,000, contact your Avid representative for a recommendation.*

The following topics provide information about this configuration:

- [Understanding a Split Database](#)
- [Supported Configurations](#)
- [Preparing for a Split Database](#)
- [Splitting a Database for New Interplay Installations](#)
- [Splitting a Database for Existing Interplay Installations](#)
- [Reuniting a Split Database](#)

## Understanding a Split Database

When you first install Interplay Engine software, the installation program requires you to set one root folder for the database on a local drive. This folder functions as the root for two parts of the Interplay database:

- A metadata database, which the Interplay Engine uses to store metadata for all assets. These assets can include both Avid assets and file assets. (*File assets* include Photoshop files, Microsoft Office files, and other files that are not created through Avid systems.)
- A file repository, which holds the source files for file assets, streamed properties for Avid assets (such as head frames and AAF information), and other files.


If the Interplay Engine server does not have adequate local storage for your Interplay database, you can configure the Interplay Engine to store only the metadata database on the Interplay Engine. All other database files and folders can be stored on an Avid shared-storage workspace. This configuration is called a *split database*.



*Storing the file repository of a large Interplay database on ISIS shared storage in a split-database configuration may reduce the maximum number of media files you can store on the ISIS system. If the number of assets in your Interplay database might exceed 50,000, contact your Avid representative for a recommendation.*

If your Interplay system uses a cluster configuration, it includes a large amount of local storage space, and a split database is probably not necessary.

The following illustration shows the metadata database stored on the internal drive of the Interplay Engine server and the source files for the assets stored on Avid shared-storage workspaces.





*In a split database, source files for file assets and streamed properties for Avid assets are stored on a shared storage workspace. Media files for Avid assets, such as .mxf files, are always stored on a shared storage workspace.*

### **Relationship Between the File Repository and the Metadata Database**

The file repository contains folders that hold the file versions created through importing and checking in files, as well as other files such as preview images and head frames of clips. The metadata database contains the information needed by the Interplay Engine to access the files in the database, and stores metadata about the files.



*For a description of the files that make up the database, see “Avid Interplay Databases, Folders, and Files” on page 33.*

You can configure your system to store the file repository on shared storage. However, for performance and reliability reasons, Avid requires that the metadata database be stored on the server running the Interplay Engine. If the metadata database is stored on an external file server, network problems or unavailability of the shared storage server causes the Interplay Engine to lock the databases because it cannot write changes persistently.

### **Methods for Splitting a Database**

There are two methods for splitting the database:

- Specify how to split the database before you first create it.
- Split the database after you create it.

In either case, you need to prepare the shared storage workspace before you split the database. These procedures are described in the following topics:

- [“Preparing for a Split Database” on page 212](#)
- [“Splitting a Database for New Interplay Installations” on page 213](#)
- [“Splitting a Database for Existing Interplay Installations” on page 215](#)

## **Supported Configurations**

The following table summarizes the supported configurations for the Interplay Engine.

### Supported Configurations for the Interplay Engine

Metadata Location	File Repository Location	Supported	Comments
Interplay Engine server	Dedicated file server (Avid Unity MediaNetwork or Avid ISIS)	Yes	High reliability, high speed performance, large amount of storage space.
Interplay Engine server	Interplay Engine server	Yes	High reliability, high speed performance, limited storage space.
Dedicated file server A	Dedicated file server A	No	Not supported. Metadata database must be on Interplay Engine server.
Dedicated file server A	Dedicated file server B	No	Not supported. Metadata database must be on Interplay Engine server.
Dedicated file server	Interplay Engine server	No	Not supported. Metadata database must be on Interplay Engine server.

## Preparing for a Split Database

To split the database, you need to prepare the Avid ISIS or Avid Unity MediaNetwork workspace. A split database is supported on an Avid Unity MediaNetwork if the server can access the file system over a UNC path, such as `\\Unity_Server\WorkspaceName`.

### To prepare for a split database:

- Do one of the following:
  - Select an Avid shared-storage workspace to store the source files for file assets (file repository).
  - Create and name a new workspace.

For example, you can create a workspace named `\\SharedStorageServer\File_Assets`. For *SharedStorageServer*, substitute the network name of your Avid ISIS System Director or Avid Unity MediaNetwork File Manager.

Make sure there is adequate space to hold the files that will be created.

- Make sure that the Server Execution User has full access to the Avid shared-storage workspace.

The Server Execution User is usually a domain user, such as \\MYDOMAIN\IPEngine. In this case, create a user on the Avid shared-storage system that has the identical name and password as the domain user and the Server Execution User. For more information, see [“Creating the Server Execution User Account” on page 204](#).

3. Set read-only access on the workspace for all users that will connect to the Interplay Engine. Users will be able to edit local copies on their client systems.

## Splitting a Database for New Interplay Installations

### To split the database for new Interplay installations:

1. Prepare the shared storage workspace, as described in [“Preparing for a Split Database” on page 212](#).
2. Install the Interplay Engine. During the installation process, accept the default share on the Interplay Server as the database location.
3. Edit the workgroup.xml file to include the path for the shared storage workspace (see [“Configuring the workgroup.xml File” on page 219](#)).
4. Open the Interplay Administrator.
5. In the Server section of the Interplay Administrator window, click Server Settings.


The Server Settings view opens. This view shows the settings for two root folders: one for the metadata database and one for the data (file assets). Leave the root folder for the database unchanged.

6. In the text box labeled “Root folder for data (Assets),” type the UNC path or browse to the Avid shared-storage workspace you want to use as a file repository for the file assets.

The following screen capture shows an example.

- DOCWG is the Interplay Engine server, and WG\_Database\$ is the administrative share name for the folder that holds the metadata database. This location was set during the installation; by default the folder is named D:\Workgroup\_Databases. For more information, see [“Identifying the Root Folder of the Interplay Server Database” on page 220](#).
- AAC-ISIS is the Avid ISIS server and File\_Assets is the workspace.

## 9 Configuring Interplay for a Split Database




7. Click Apply Changes.

If an error message tells you that the server is not configured to accept the UNC path, make sure the `workgroup.xml` file is correctly edited to include the shared storage workspace (see [“Configuring the workgroup.xml File” on page 219](#)).

8. Click the Menu button.

9. In the Database section of the Interplay Administrator window, click the Create Database icon.

The Create Database view opens. The root folders displayed should match those in the Server Settings view.



10. Accept the Database Name, type a description, and click Create.

The new database is created.

- You should find the database folder on the Interplay Engine, for example `D:\Workgroup_Databases\AvidWG\_Database`.
- You should find the file repository on the Avid shared-storage workspace, for example `\\AAC-ISIS\File_Assets\AvidWG`. The AvidWG folder should contain `_Master` and other database folders and files.

11. In the Schedule Backups view of the Interplay Administrator, change the backup location to an external file server.

By default, the `_Backup` folder is now located on the shared storage workspace. To avoid filling up the workspace with backups, select Custom and specify the UNC path for a different external file server. Make sure the Server Execution User has read/write access to this external file server.

## Splitting a Database for Existing Interplay Installations

In some situations, you might need to split the database after you have created it. The following procedure assumes that you want to relocate the file repository of database AvidWG from the Interplay Engine server to an Avid ISIS or Avid Unity MediaNetwork workspace.



*During the installation of the Interplay Engine, a shared folder for the database is created on the Interplay Engine server. In the Interplay Administrator this folder is displayed as `WG_Database$`, which is a hidden share name and not an actual folder. By default the folder is named `D:\Workgroup_Databases` (non-cluster systems) or `S:\Workgroup_Databases` (cluster systems). For more information, see “[Identifying the Root Folder of the Interplay Server Database](#)” on page 220.*

The following procedure refers to two different types of backups:

- Interplay database backup: A backup copy of the Interplay database created by the automated backup system built into the Interplay Engine. For more information, see “[Creating and Restoring Database Backups](#)” on page 36.
- Archive database backup: A copy of the Interplay database manually created by using a third-party tool that can handle long path names (longer than 256 characters). Two examples are Robocopy (contained in `rktools.exe`, available on Microsoft.com) and 7-Zip. For more information, see “[Using an Archiving Tool for Backup](#)” on page 46 and documentation for the third-party tool.

## 9 Configuring Interplay for a Split Database

If you create an archive backup, keep in mind that creating a complete archive backup can take several hours. You must lock and deactivate the database before creating the archive. You can save time by removing old backups from the \_Backup folder, located by default in \\IEServer\WG\_Database\$\AvidWG\\_Backup.

### To split an existing database:

1. Create a full Interplay database backup by using the Interplay Administrator.  
Alternatively, manually create an archive database backup of all files and folders in \\IEServer\WG\_Database\$\AvidWG.
2. Prepare the shared storage workspace, as described in [“Preparing for a Split Database” on page 212](#).
3. On the Interplay Engine server, edit the workgroup.xml file to include the path for the new folder on the shared storage workspace (see [“Configuring the workgroup.xml File” on page 219](#)).
4. Lock the database to make sure that no user can access it:
  - a. In the Database section of the Interplay Administrator window, click Lock/Unlock Databases.
  - b. Select the database in the Unlocked Databases list.
  - c. Click Lock Database.The database name appears in the Locked Databases list.
5. Deactivate the database:
  - a. In the Database section of the Interplay Administrator window, click Manage Databases.
  - b. Select the database name in the Databases list.
  - c. Click Deactivate.The database name no longer appears in the Databases list.
6. Log out of the Interplay Administrator.
7. Mount the shared storage workspace you prepared, for example, \\AAC-ISIS\File\_Assets.
8. Use Windows Explorer to navigate to the shared storage workspace and create a folder named AvidWG.




**This folder name (AvidWG) must exactly match the name of the corresponding folder on the Interplay Engine server.**



9. Copy all files and folders except the `_Database` folder from  
`\\IEServer\WG_Database$\AvidWG` to the new location  
`\\SharedStorageServer\WorkspaceName\AvidWG`.

Windows Explorer cannot copy paths longer than 256 characters or Unicode names that are not in the default operating system language. If the database includes either or both of these items, use a tool such as Robocopy or 7-Zip.

After copying the files and folders, delete them from the original location (or rename them), so that this location contains only the `_Database` folder. The following illustration shows both locations: the metadata database on the Interplay Engine and the file repository on the shared storage workspace.



10. Navigate to the folder `\\SharedStorageServer\WorkspaceName\AvidWG` and open the `FolderLocations.xml` file.

## 9 Configuring Interplay for a Split Database

11. Make sure the file includes the correct path for the `_Database` directory. It should include the line

```
<Path>\\IEServer\WG_Database$\AvidWG\_Database</Path>
```

For *IEServer*, substitute the network name for the Interplay Engine server. This path points to the metadata database on the Avid Interplay Engine.

If the `FolderLocations.xml` file does not exist on the workspace, or it is empty, use a text editor or an XML editor to create the file in the folder `AvidWG`.

Add the file location information as follows:

```
<XML>
<Folder Name="_Database">
<Path>\\IEServer\WG_Database$\AvidWG\_Database</Path>
</Folder>
</XML>
```

For *IEServer*, substitute the network name for the Interplay Engine server. Be sure to use a UNC path. The Interplay Engine effectively maps it to a local path if possible.



**Make sure to type this information accurately. Errors in the file can prevent you from activating the database. XML files are case sensitive. Make sure that a text editor does not automatically change the XML tags to lower case.**

12. Activate the database:
  - a. In the Interplay Administrator, click `Manage Databases`.
  - b. In the “Database (.pro) file to activate” text box, type the full UNC path to the .pro file, which now resides on the shared storage workspace. For example:  
`\\SharedStorageServer\WorkspaceName\AvidWG\AvidWG.pro`  
You can also navigate through the network to select the file. For example, open `My Network Places > Entire Network > Avid ISIS Network`. Then navigate to `\\SharedStorageServer\WorkspaceName\AvidWG\AvidWG.pro`
  - c. Make sure “Load Database on Activation” is selected, and click `Activate`.  
When the database is activated, its name is displayed in the `Databases` list. The database is automatically unlocked.  
If the following error message is displayed, check the `FolderLocations.xml` file for accuracy: “Failed to open the database (the system cannot find the path specified).”
13. Test the setup by doing the following:
  - a. Open one Interplay Access client.
  - b. Connect to the database and import a new file asset.

- c. Lock and unlock the database.
  - d. After reconnecting to the database with Interplay Access, check if the file is still in the database.
14. In the Schedule Backups view of the Interplay Administrator, change the backup location to an external file server.
- By default, the \_Backup folder is now located on the shared storage workspace. To avoid filling up the workspace with backups, select Custom and specify the UNC path for a different external file server. Make sure the Server Execution User has read/write access to this external file server.
15. (Option) In the Server Settings view of the Interplay Administrator, specify the path for the shared storage workspace as the root folder for data, as described in step 6 in [“Splitting a Database for New Interplay Installations”](#) on page 213.

## Configuring the workgroup.xml File

When you move the file repository to a shared storage workspace, you must edit the workgroup.xml file to include a path for the file repository share.

This file is located in the Interplay Engine installation directory, for example,

- C:\Program Files\Avid\Avid Interplay Engine\Data\Apache\conf\workgroup.xml (non-cluster systems)
- S:\WorkgroupData\Apache\conf\workgroup.xml (cluster systems).



*On a cluster system, the following file might be installed on both nodes: C:\Program Files\Avid\Avid Interplay Engine\Data\Apache\conf\workgroup.xml. These files are not currently used and do not need to be edited.*

The default database location that you specified during the Interplay Engine installation is published through this file as a default. The following example shows the section of workgroup.xml that includes the database location:

```
<filetransfer>
<path read="true" write="true">
\\IEServer\WG_Database$
</path>
</filetransfer>
```

For *IEServer*, substitute the network name for the Interplay Engine server.

## 9 Configuring Interplay for a Split Database

If you move the file repository to a different location, this location must be published in this file as well. For example:

```
<filetransfer>

<path read="true" write="true">

\\IEServer\WG_Database$

</path>

<path read="true" write="true">

  \\SharedStorageServer\WorkspaceName

</path>

</filetransfer>
```

For *SharedStorageServer*, substitute the network name for the Avid ISIS System Director or the Avid Unity MediaNetwork File Manager. For *WorkspaceName*, substitute the workspace you designated for the file repository. For example, \\AAC-ISIS\File\_Assets.

### Identifying the Root Folder of the Interplay Server Database

WG\_Database\$ is a hidden administrative share name and not an actual folder. It represents the root folder of the database. For example, the default root folder (which is set during installation) is named D:\Workgroup\_Databases (S:\Workgroup\_Databases on a cluster system).


#### To identify the root folder of the database:

1. Log onto the Interplay server (local computer) with an administrative account.
2. Open a Command Prompt by clicking All Programs and selecting Accessories > Command Prompt.
3. Type the following command at the Windows Command line:

```
net share
```

All shares on the system are displayed, along with their paths, as shown in the following illustration:

Database root folder



```

Microsoft Windows [Version 5.2.3790]
(C) Copyright 1985-2003 Microsoft Corp.

C:\Documents and Settings\Administrator>net share

Share name      Resource
-----
C$              C:\
WG_Database$   D:\Workgroup_Databases
IPC$           C:\WINDOWS
ADMIN$         C:\WINDOWS
E$             E:\
J$            J:\
USER_WORKGROUP C:\Documents and Settings\USER_WORKGROUP

Remark
-----
Default share
Avid Interplay database directory
Remote IPC
Remote Admin
Default share
Default share

```


## Reuniting a Split Database

An Interplay configuration might include a split database (see [“Understanding a Split Database” on page 210](#)). This topic provides information about reuniting a split database.


The following illustrations show a correctly split database:

- The `_Database` folder is located in the `AvidWG` folder on the Interplay Engine server
- The remaining folders and files are located in the `AvidWG` folder on a shared storage workspace

## 9 Configuring Interplay for a Split Database




The following illustration shows all database files located in the same AvidWG folder on the Interplay Engine server.



**In a correctly split database, the AvidWG folder on the Interplay Engine should contain only the \_Database folder. If the AvidWG folder on shared storage includes a \_Database folder, do not copy this folder to the Interplay Engine. Rename this folder \_Database\_UNUSED or something similar before copying the other content to the Interplay Engine.**

In some configurations, the \_InternalData folder (which holds user metadata) might also be located on the shared storage workspace, or might be split between the Interplay Engine and the shared storage workspace. This folder should be located in \\IEServer\WG\_Database\$, for example, D:\Workgroup\_Databases, as shown in the following illustration.



## 9 Configuring Interplay for a Split Database

Follow one of these procedures to reunite a split database:

- If the `_InternalData` folder is already located on the Interplay Engine, see [“Reuniting a Split Database \(AvidWG Only\)” on page 224](#).
- If the `_InternalData` folder is located on a shared storage workspace, or split between the Interplay Engine and shared storage, see [“Reuniting a Split Database \(AvidWG and \\_InternalData\)” on page 227](#).

These procedures refer to two different types of backups:

- **Interplay database backup:** A backup copy of the Interplay database created by the automated backup system built into the Interplay Engine. For more information, see [“Creating and Restoring Database Backups” on page 36](#).
- **Archive database backup:** A copy of the Interplay database manually created by using a third-party tool that can handle long path names (longer than 256 characters). Two examples are Robocopy (contained in `rktools.exe`, available on Microsoft.com) and 7-Zip. For more information, see [“Using an Archiving Tool for Backup” on page 46](#) and documentation for the third-party tool.

If you create an archive backup, keep in mind that creating a complete archive backup can take several hours. You must lock and deactivate the database before creating the archive. You can save time by removing old backups from the `_Backup` folder, located by default in `\\IEServer\WG_Database$\AvidWG\_Backup`.

### Reuniting a Split Database (AvidWG Only)

**To reunite a split database (AvidWG only):**

1. If you are working on a cluster system, make sure that cluster services that provide the local S drive are running.
2. Lock the database to make sure that no user can access it:
  - a. In the Database section of the Interplay Administrator window, click Lock/Unlock Database.
  - b. Select the database in the Unlocked Databases list.
  - c. Click Lock Database.

The database name appears in the Locked Databases list.



3. Deactivate the database:
  - a. In the Database section of the Interplay Administrator window, click Manage Databases.
  - b. Select the database name in the Databases list.
  - c. Click Deactivate.

The database name no longer appears in the Databases list.

4. If you do not have a complete Interplay database backup available, manually create an archive backup of the database from both database locations:

- `\\SharedStorageServer\WorkspaceName\AvidWG`
- `\\IEServer\WG_Database$\AvidWG`

By default, this folder is

D:\Workgroup\_Databases\AvidWG (non-cluster system)

S:\Workgroup\_Databases\AvidWG (cluster system)

5. Copy the necessary files and folders from

`\\SharedStorageServer\WorkspaceName\AvidWG`

to

`\\IEServer\WG_Database$\AvidWG`

Windows Explorer cannot copy paths longer than 256 characters or Unicode names that are not in the default operating system language. If the database includes either or both of these items, use a tool such as Robocopy or 7-Zip.

## 9 Configuring Interplay for a Split Database

The following table lists the files and folders that you need to copy. These files and folders are illustrated in “Reuniting a Split Database” on page 221.

---

**Copy from**  
**\\SharedStorageServer\WorkspaceName\AvidWG**  
**to**  
**\\IEServer\WG\_Database\$\AvidWG**

---

\_Backup folder  
\_Buckets folder  
\_CheckIn folder  
\_Handover folder  
\_Import folder  
\_Master folder  
\_PropertyHandover folder  
\_PropertyStore folder  
\_AvidWG.nif  
Aliasconfig.xml  
AvidWG.pro  
FolderLocations.xml

---



**In a correctly split database, the AvidWG folder on the Interplay Engine should contain only the \_Database folder. If the AvidWG folder on shared storage includes a \_Database folder, do not copy this folder to the Interplay Engine. Rename this folder \_Database\_UNUSED or something similar before copying the other content to the Interplay Engine.**

6. Delete or rename \\IEServer\WG\_Database\$\AvidWG\FolderLocations.xml.
7. Edit the workgroup.xml file to include only the following path:

\\IEServer\WG\_Database\$

See “Configuring the workgroup.xml File” on page 219.

8. Activate the database:
  - a. In the Interplay Administrator, click Manage Databases.
  - b. In the “Database (.pro) file to activate” text box, type the full UNC path to the .pro file, which now resides on the Interplay Engine server. For example:  
`\\IEServer\WG_Database$\AvidWG\AvidWG.pro`
  - c. Make sure “Load Database on Activation” is selected, and click Activate.

If the database is activated, its name is displayed in the Databases list. The database is automatically unlocked.
9. Check the backup location in the Schedule Backups view of the Interplay Administrator.  
 If the `_Backup` folder was located on shared storage, it is now located on the Interplay Engine. If necessary, change the location to the Interplay Engine or to another external file server.
10. In the Server Settings view of the Interplay Administrator, make sure the path for the “Root folder for data” matches the path for the “Root folder for database.”  
 This location is used if you create a new database.
11. Test the setup by doing the following:
  - a. Open one Interplay Access client.
  - b. Connect to the database and import a new file asset.
  - c. Lock and unlock the database.
  - d. After reconnecting to the database with Interplay Access, check if the file is still in the database.
12. If the test is successful, delete or rename the folder  
`\\SharedStorageServer\WorkspaceName\AvidWG`.

## Reuniting a Split Database (AvidWG and `_InternalData`)

### To reunite a split database (AvidWG and `_InternalData`):

1. If you are working on a cluster system, make sure that cluster services that provide the local S drive are running.
2. Lock the database to make sure that no user can access it:
  - a. In the Database section of the Interplay Administrator window, click Lock/Unlock Database.
  - b. Select the database in the Unlocked Databases list.
  - c. Click Lock Database.

The database name appears in the Locked Databases list.

## 9 Configuring Interplay for a Split Database

3. Deactivate the database:
  - a. In the Database section of the Interplay Administrator window, click Manage Databases.
  - b. Select the database name in the Databases list.
  - c. Click Deactivate.

The database name no longer appears in the Databases list.

4. In the Server Settings view of the Interplay Administrator, edit the path for the “Root folder for data” to match the path for the “Root folder for database.”

This location is used if you create a new database.

5. Shut down the Interplay Engine services:
  - On a cluster system, bring the Avid Workgroup Engine Monitor resource (not the resource group) offline.
  - On a non-cluster system, stop the services Avid Workgroup TCP COM Bridge and the service Avid Workgroup Server Browser and run C:\Program Files\Avid\Avid Interplay Engine\Server\NxNServerShutdown.exe.

For more information on Interplay Engine services, see [“Avid Interplay Engine Servers and Services” on page 241](#).

6. If you do not have a complete Interplay database backup available, manually create an archive backup from both database locations:

- `\\SharedStorageServer\WorkspaceName\AvidWG`
- `\\EServer\WG_Database$\AvidWG`

By default, this folder is

D:\Workgroup\_Databases\AvidWG (non-cluster system)

S:\Workgroup\_Databases\AvidWG (cluster system)

7. Copy the necessary files and folders from

`\\SharedStorageServer\WorkspaceName\AvidWG`

to

`\\EServer\WG_Database$\AvidWG`

Windows Explorer cannot copy paths longer than 256 characters or Unicode names that are not in the default operating system language. If the database includes either or both of these items, use a tool such as Robocopy or 7-Zip.

The following table lists the files and folders that you need to copy. These files and folders are illustrated in “[Reuniting a Split Database](#)” on page 221.

---

**Copy from**  
 \\SharedStorageServer\WorkspaceName\AvidWG  
**to**  
 \\IEServer\WG\_Database\$\AvidWG

---

\_Backup folder  
 \_Buckets folder  
 \_CheckIn folder  
 \_Handover folder  
 \_Import folder  
 \_Master folder  
 \_PropertyHandover folder  
 \_PropertyStore folder  
 \_AvidWG.nif  
 Aliasconfig.xml  
 AvidWG.pro  
 FolderLocations.xml

---



**In a correctly split database, the AvidWG folder on the Interplay Engine should contain only the \_Database folder. If the AvidWG folder on shared storage includes a \_Database folder, do not copy this folder to the Interplay Engine. Rename this folder \_Database\_UNUSED or something similar before copying the other content to the Interplay Engine.**

- Use Windows or a tool that can copy long path names to copy the \_InternalData folder from

\\SharedStorageServer\WorkspaceName

to

\\IEServer\WG\_Database\$

If the contents of the folder are split between the Interplay Engine and the shared storage workspace, copy the files and folders listed in the following table.

## 9 Configuring Interplay for a Split Database

---

**Copy from**  
**\\SharedStorageServer\WorkspaceName\\_InternalData**  
**to**  
**\\IEServer\WG\_Database\$\\_InternalData**

---

\_Backup folder  
\_Buckets folder  
\_CheckIn folder  
\_Handover folder  
\_Import folder  
\_Master folder  
\_PropertyHandover folder  
\_PropertyStore folder  
\_AvidWG.nif  
Aliasconfig.xml  
AvidWG.pro  
FolderLocations.xml


---



**If the `_InternalData` folder on shared storage includes a `_Database` folder, do not copy this folder to the Interplay Engine. Rename this folder `_Database_UNUSED` or something similar before copying the other content to the Interplay Engine.**

9. Delete or rename `\\IEServer\WG_Database$\AvidWG\FolderLocations.xml`.
10. Delete or rename `\\IEServer\WG_Database$\_InternalData\FolderLocations.xml`.
11. Edit the `workgroup.xml` file to include only the following path:  
`\\IEServer\WG_Database$`  
See “[Configuring the workgroup.xml File](#)” on page 219.
12. Open a Command Prompt window, type `regedit`, and navigate to one of the following:
  - (32-bit OS) `HKEY_LOCAL_MACHINE\SOFTWARE\Avid Technology\Workgroup\Avid Workgroup\DatabaseServer`
  - (64-bit OS) `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Avid Technology\Workgroup\Avid Workgroup\DatabaseServer`

Check the UNC paths for RecentProject1 and RecentProject2. Both paths should show the Interplay Engine server, as shown in the following illustration.



13. Start the Interplay Engine services:

- On a cluster system, bring the Avid Workgroup Engine Monitor resource (not the resource group) online.
- On a non-cluster system, start the services Avid Workgroup TCP COM Bridge and the service Avid Workgroup Server Browser.

14. Activate the database:

- a. In the Interplay Administrator, click Manage Databases.
- b. In the “Database (.pro) file to activate” text box, type the full UNC path to the .pro file, which now resides on the Interplay Engine server. For example:  
`\\IEServer\WG_Database$\AvidWG\AvidWG.pro`
- c. Make sure “Load Database on Activation” is selected, and click Activate.

If the database is activated, its name is displayed in the Databases list. The database is automatically unlocked.

15. Check the backup location in the Schedule Backups view of the Interplay Administrator.

If the \_Backup folder was located on shared storage, it is now located on the Interplay Engine. If necessary, change the location to the Interplay Engine or to another external file server.

16. Test the setup by doing the following:

- a. Open one Interplay Access client.
- b. Connect to the database and import a new file asset.

## 9 Configuring Interplay for a Split Database

- c. Lock and unlock the database.
  - d. After reconnecting to the database with Interplay Access, check if the file is still in the database.
17. If the test is successful, delete or rename the folder  
*\\SharedStorageServer\WorkspaceName\AvidWG*.



# A Installed Components and Services

The following topics provide information about components and services that are installed as part of the Interplay Administrator:

- [Avid Interplay Engine Directory: Folders and Files](#)
- [Required TCP/IP Ports](#)
- [Avid Interplay Engine Servers and Services](#)

## Avid Interplay Engine Directory: Folders and Files

The following components are installed in the Avid Interplay Engine directory. By default, this directory is created during installation as C:\Program Files\Avid\Avid Interplay Engine.

- **Apache:** This folder includes an Apache server to provide access to Preview images and to provide client access. See [“Apache Folder” on page 234](#).
- **Data:** This folder contains all server-relevant configuration and data files. See [“Data Folder” on page 236](#).
- **Logs:** This folder contains the log files written by the Avid Interplay Engine. See [“Logs” on page 237](#).
- **NxN:** This directory contains services and modules for the Apache server.
- **PreviewServer:** This directory contains a tool for cleaning the Preview Server cache. See [“Preview Server Folder” on page 240](#).
- **Server:** This directory contains all data to execute an Avid Interplay Engine on this machine. See [“Server Folder” on page 241](#).

### Apache Folder

The Apache web server handles every incoming request and forwards them to the database server. The Apache folder includes important logs from the Apache process.

File Path (C:\Program Files\Avid\Avid Interplay Engine)	Description
Apache\logs\error.log	The central Apache web server log file that contains important messages from the Apache process, especially warnings and errors.
Apache\logs\access.log	The central Apache web server access log file. Only created if you enable this in Apache's configuration (httpd.conf).
Apache\bin\Machines\[MACHINENAME]\Apache.log	Contains preview server and generator errors.



*New log entries are appended to the log files, which makes them grow over time. The log files are not deleted automatically. This must be done manually, if required.*

#### error.log

This log file contains error messages and notices. An entry is received, for example, if a connection to the TCP/COM bridge failed. An entry is also created when a client logged in or logged off. The entries in this case look similar to the following:

```
[Thu Mar 14 18:24:07 2002] [notice] logon request received, session 'bad5781de4bd712b8bf49c7376de3cd4:1016126647' created
```

```
[Thu Mar 14 18:43:45 2002] [notice] logoff request for session 'bad5781de4bd712b8bf49c7376de3cd4:1016126647' received
```

A logon entry is always created when a client logs on, while a logoff entry is only created if the client performs a clean logout. No logoff entry is created if, for example, the network connection is interrupted.

#### access.log

The access.log file contains a log of every incoming request similar to the following:

```
192.168.1.199 - - [22/Jan/2002:21:11:49 +0100] "POST /nxn/workgroup/http HTTP/1.1" 200 172
```

The items in such a log entry are:

- The IP address of the machine where the request was coming from;
- The date and time when the request was received;
- The request method (GET or POST), the request URI and any request parameters;
- The HTTP status codes returned to the client.

The returned status codes are the standard HTTP codes as described in RFC 2616 available under <http://www.ietf.org/rfc/rfc2616.txt>. Some of the important values are:

- 200 OK: The request has succeeded.
- 403 Forbidden: The server refuses to perform the request.
- 404 Not found: The server has not found anything matching the requested URI.
- 500 Internal server error.



*The creation of the access.log file is by default deactivated for performance and space reasons.*

## Activating Creation of the access.log File

**To activate creation of the access.log file:**

1. Open the httpd.conf file.

This is the Apache server configuration file located in the Avid Interplay Engine installation directory, for example, C:\Program Files\Avid\Avid Interplay Engine\Data\Apache\conf

2. Remove the # from one of the two lines in the file that appear as follows:

```
#CustomLog logs/access.log common
```

or

```
#CustomLog logs/access.log combined
```

See the file itself for further information.

## Data Folder

The Data folder contains server-relevant configuration and data files, including the following Apache modules and configuration files used by the Avid Interplay Preview Server and Avid Interplay HTTP Server.

---

<b>File Path (C:\Program Files\Avid\Avid Interplay Engine)</b>	<b>Description</b>
Data\Apache\conf\httpd.conf	The configuration file for the Apache web server.
Data\Apache\conf\workgroup.xml	This file contains settings for the Avid Interplay Apache modules.  The settings in this file are used, for example, by the filetransfer and the preview server modules. The file transfer section contains items such as a list of UNC paths to which the Avid Interplay HTTP server can browse. The preview section defines variables such as when the preview cache expires.
Data\TCPComBridge\ServerXML.xml	Contains settings for client access.

---

## Logs

The Logs folder contains the following logs:

<b>File Path (C:\Program Files\Avid\Avid Interplay Engine)</b>	<b>Description</b>
Logs\Machines\[COMPUTER NAME]\AvDeletes.log	Records information about media delete operations. See <a href="#">“AvDeletes.log” on page 238</a> .
Logs\Machines\[COMPUTER NAME]\AvMetaDataDelete.log	Records information about metadata delete operations. See <a href="#">“AvMetaDataDelete.log” on page 239</a>
Logs\Machines\[COMPUTER NAME]\AvMoveEx.log	Records information about move operations. See <a href="#">“AvMoveEx.log” on page 240</a> .
Logs\Machines\[COMPUTER NAME]\NxNServer.log	The central Avid Interplay Engine Server log file containing information messages, warning and error messages generated by the Avid Interplay Engine Server.
Logs\Machines\[COMPUTERNAME]\NxNTCPComBridge.log	The log file for the Avid Interplay TCP/COM Bridge. Is not created until the first message occurs.
Logs\Machines\[COMPUTERNAME]\NxNBackup.log	Contains the backup log.

In Interplay version 1.6 and later, the Interplay Engine compresses and archives log files older than 7 days. The log compression process runs during project backup. For more information see [“Restoring Archived Log Files” on page 60](#).

### AvDeletes.log

The AvDeletes.log file includes the following information about media delete operations:

- Date and time of the delete operation
- Login of the user who performed the delete operation
- Computer name of the machine on which the delete operation was performed
- Name and path of the master clip deleted
- Name and path of the media files deleted, with deletion time in milliseconds (ms)

The following example shows these items.

#### AvDeletes.log

```
❶ [Mon May 25 14:02:29 2009] User 'airspeed' on host 'muc-ifspu  
t  
nik' deleting media  
for:  
❷ [Mon May 25 14:02:29 2009] /Projects/ETPB-  
1/INCOMING1/VIEWCUT_7151_MEDEA_020809_JT  
[Mon May 25 14:02:29 2009] Media locations:  
[Mon May 25 14:02:29 2009] Successfully deleted file //caetavdisis/feeds_a/avid  
mediafiles/mxf/tm_caetavdetpb-1/etpb_1v01d015d6.mxf 57 ms  
[Mon May 25 14:02:29 2009] Successfully deleted file //caetavdisis/feeds_a/avid  
mediafiles/mxf/tm_caetavdetpb-1/etpb_1a01d015d6.mxf 25 ms  
❸ [Mon May 25 14:02:29 2009] Successfully deleted file //caetavdisis/feeds_a/avid  
mediafiles/mxf/tm_caetavdetpb-1/etpb_1a02d015d6.mxf 25 ms  
[Mon May 25 14:02:29 2009] Successfully deleted file //caetavdisis/lowres/Avid  
MediaFiles/MXF/CAETAVDTC02.1/VIEWCUT_7151_MEDEA_498FCF9C.mxf 25 ms  
  
[Mon May 25 14:02:29 2009] User 'airspeed' on host 'muc-ifspu  
t  
nik' deleting media  
for:  
[Mon May 25 14:02:29 2009] /Projects/ETPB-1/INCOMING1/ccut street song recut  
012809  
[Mon May 25 14:02:29 2009] Media locations:  
[Mon May 25 14:02:29 2009] Successfully deleted file //caetavdisis/Feeds_A/Avid  
MediaFiles/MXF/TM_caetavdetpb-1/ETPB_1V01249C352.mxf 25 ms  
❹ [Mon May 25 14:02:29 2009] Unable to delete file //caetavdisis/Feeds_A/Avid  
MediaFiles/MXF/TM_caetavdetpb-1/ETPB_1A01249C352.mxf (net path not found 0x35) 0  
ms  
[Mon May 25 14:02:29 2009] Successfully deleted file //caetavdisis/Feeds_A/Avid  
MediaFiles/MXF/TM_caetavdetpb-1/ETPB_1A02249C352.mxf 25 ms
```

- ❶ Date, time, user login, and host system for the delete operation
- ❷ Name and path of master clip deleted
- ❸ Names and paths of four media files successfully deleted, with deletion time in milliseconds (ms)
- ❹ Failure to delete one object with Windows error “net path not found 0x35”

## AvMetaDataDelete.log

The AvMetaDataDelete.log includes the following information about metadata delete operations:

- Date and time of the delete operation
- Login of the user who performed the delete operation
- Computer name of the machine from on the delete operation was performed
- Display name, object handle, and path for every deleted object, grouped by path
- If an object could not be deleted, the error code (for example, a reservation)

The following example shows these items.

```

❶ [Mon May 25 14:02:30 2009] User 'airspeed' on host 'muc-ifspu
  data:
❷ [Mon May 25 14:02:39 2009]   From '/Projects/ETPB-1/INCOMING1/'
❸ [Mon May 25 14:02:39 2009]     'ET_VCT_7143_US_MICHELLE_5A_CY' handle 163841
  [Mon May 25 14:02:39 2009]     'VIEWCUT_7151_MEDEA_020809_JT.tr' handle 758621
  [Mon May 25 14:02:39 2009]     'IN_VIEWCUT_STREETSONG_FINAL 012' handle 1260969

  [Mon May 25 14:19:18 2009] User 'Administrator' on host 'muc-ifspu
  metadata:
  [Mon May 25 14:21:22 2009]   From '/Orphan Clips/'
❹ [Mon May 25 14:21:22 2009]     'Channel 4 News @ 5' handle 1231 failed to delete,
  error 0x899901a6

❺ [Mon May 25 14:21:39 2009] User 'Administrator' on host 'muc-ifspu
  metadata:
  [Mon May 25 14:21:40 2009]   From '/Orphan Clips/'
  [Mon May 25 14:21:40 2009]     'Channel 4 News @ 5' handle 1231

```

- ❶ Date, time, user login, and host system for the delete operation
- ❷ Name of the folder that holds the deleted objects
- ❸ Names and object handles of three objects successfully deleted
- ❹ Name and object handle of an object that could not be deleted with error 0x899901a6 (Object is still referencing media and cannot be deleted).
- ❺ Same object successfully deleted

## A Installed Components and Services

### AvMoveEx.log

The AvMoveEx.log includes the following information:

- Date and time of the move operation
- Login of the user who performed the move operation
- Computer name of the machine on which the move operation was performed
- Mime type (master clip, sequence, and so on), display name, object handle, and source and target path of the moved objects
- If the objects are sequences or subclips, the deleted and created proxies and references

The following example shows these items.

#### AvMoveEx.log

```
❶ Fri May 29 11:02:45 2009] User 'airspeed' on host 'muc-ifspudnik' moving master-clip 'Flash 1.mov' handle 1962859:
❷ [Fri May 29 11:02:45 2009] From '/Projects/DAILY PROJECTS/ETS PROJECTS/ETS DAILY PROJECTS/DONT_DELETE/LIGHT LEAKS ETC/'
❸ [Fri May 29 11:02:45 2009] To '/Projects/AOT/Test/'

❹ [Fri May 29 11:03:08 2009] User 'airspeed' on host 'muc-ifspudnik' moving sequence 'President' handle 538510:
[Fri May 29 11:03:08 2009] From '/Projects/AOT/Test/'
[Fri May 29 11:03:08 2009] To '/Projects/DAILY PROJECTS/ETS PROJECTS/ETS DAILY PROJECTS/DONT_DELETE/LIGHT LEAKS ETC/'
[Fri May 29 11:03:09 2009] Proxies & References deleted at '/Projects/AOT/Test/' during move:
[Fri May 29 11:03:09 2009] 'President' handle 538510
[Fri May 29 11:03:09 2009] 'President.Voice Over.1' handle 1108345
❺ [Fri May 29 11:03:09 2009] Proxies & References created at '/Projects/DAILY PROJECTS/ETS PROJECTS/ETS DAILY PROJECTS/DONT_DELETE/LIGHT LEAKS ETC/' during move:
[Fri May 29 11:03:09 2009] 'President' handle 2799799
[Fri May 29 11:03:09 2009] 'Channel 4 News @ 5' handle 69537
[Fri May 29 11:03:09 2009] 'President.Voice Over.1' handle 376256
```

- ❶ Date, time, user login, host system, and name and object handle of the master clip being moved
- ❷ Path the clip is being moved from
- ❸ Path the clip is being moved to
- ❹ Date, time, user login, and name of sequence being moved
- ❺ Proxy files and reference clips deleted and recreated for the sequence

### Preview Server Folder

The Preview Server folder contains a script to clear the Preview Cache.



## Server Folder

The Server folder contains the Avid Interplay Engine Server installation.

File Path (C:\Program Files\Avid\Avid Interplay Engine)	Description
Server\Machines\[COMPUTER NAME]\MachineConfig.ini	This file is generated by the Avid Interplay Engine Server. It contains information about the versions of the dll's loaded by the server.
Server\Config\Config.xml	This file contains the current configuration settings for the Avid Interplay Engine events, such as whenever the server runs out of disk space, emails can be sent to the administrator.

## Required TCP/IP Ports

When a client connects to the server through a local area network, the client uses HTTP.

On the server, port 8321 is used by the Avid Workgroup Server Browser service. The Avid Workgroup Server Browser service listens and broadcasts on this port.

Port 80 on the server is used for client communication.

## Avid Interplay Engine Servers and Services

This topic describes the different servers and services that Avid Interplay needs to run properly. It also provides information about the necessary access rights of these components to the file server.

Avid Interplay has a typical client/server structure. The Interplay Engine (the server) is configured to run on a central machine that is accessible to all users through a local area network (LAN) or the Internet (WAN). The Avid Interplay client applications are used to access and browse the central database. An Avid Interplay database consists of assets (files and folders) and metadata. See [“Avid Interplay Databases, Folders, and Files” on page 33](#).

## A Installed Components and Services

Two servers are installed on the Interplay Engine:

- The Avid Interplay Engine Server is the central process where all assets and asset meta-information are managed. See [“Avid Interplay Engine Server” on page 242](#).
- The Avid Workgroup HTTP Server is a module for the Apache server that allows clients to connect to the Avid Interplay Engine Server using a HTTP protocol. See [“Avid Workgroup HTTP Server” on page 243](#)

Four services are installed on the Interplay Engine. You can view these services through the Control Panel (Click Start and select Control Panel > Administrative Tools > Services):

- Avid Workgroup Server Browser service: This service makes the Avid Interplay Engine visible to the network. It answers requests on the 8313 port, which are called from the clients. See [“Avid Workgroup Server Browser Service” on page 244](#).
- Avid Workgroup Preview Server service: This service is an Apache web server. It provides the thumbnail images for the Preview facility and the client connection interface. See [“Avid Workgroup Preview Server Service” on page 244](#).
- Avid Workgroup TCP COM Bridge service: This service provides a bridge from TCP calls to the Avid Workgroup COM interface. See [“Avid Workgroup TCP/COM Bridge Service” on page 248](#).
- Avid Workgroup VSS service: This service provides backup functionality to the Avid Interplay Engine (Interplay version 2.1 and later only). See [“Avid Workgroup VSS Service” on page 249](#).

One service is installed only on the Interplay Failover Cluster:

- Avid Workgroup Engine Monitor: This service starts the Engine Server process and monitors the health of the Engine Server, Apache HTTP Server, and TCP/COM Bridge components (Interplay version 2.3 and later only) See [“Avid Workgroup Engine Monitor Service” on page 250](#).

## Avid Interplay Engine Server

The Avid Interplay Engine Server is the central process where all assets and asset metadata are managed. The main task of the server is to manage all the information that is in the database and implement the server-side logic of database operations. The database itself is changed whenever content in the database has been changed; therefore the Interplay Engine process needs fast access to the location where the database is installed.

### Backups

The database files, as well as the assets, can be backed up while the Interplay Engine is running. For details, see [“Creating and Restoring Database Backups” on page 36](#).

## Processes

The process running is usually listed as NxNServer.exe or NXNSer~3.exe.

This process is automatically launched at startup (machine boot) from the Avid Workgroup Server Browser Service. If, however, it is not running at any time and clients try to access it, it is automatically launched.

The Interplay Engine always runs under the user specified in the DCOMConfig Settings. DCOMCNFG is a Windows utility that allows you to configure various DCOM-specific settings in the registry. To access it, type dcomcnfg at the Command Prompt.



**Do not change the settings using the DCOM configuration tool. Instead, use NxNServerUser.exe to change the user under which the Avid Interplay Engine Server and other servers and services run. See “Troubleshooting the Server Execution User Account” on page 204.**

## Windows Services

There is no Windows service associated with this server process.

## Requirements

- The Avid Interplay Engine Server must run on a Windows Server 2003 or Windows Server 2008. For additional hardware requirements, see the *Avid Interplay Software Installation and Configuration Guide*.
- The user under which the Avid Interplay Engine Server runs (the Server Execution User) needs to have full read/write access to the database directory and to the Avid shared-storage workspaces.

## Avid Workgroup HTTP Server

The Avid Workgroup HTTP Server is a module for the Apache server which allows clients to connect to the Avid Interplay Engine Server using a HTTP protocol.

These modules are run by the same instance of Apache as the Avid Workgroup Preview Server modules.

## Connectivity

See “Avid Workgroup Preview Server Service” on page 244.

## Processes

See “Avid Workgroup Preview Server Service” on page 244.

## A Installed Components and Services



*The Avid Interplay HTTP Server uses the Apache modules `NxNworkgroupFileTransferService.nsm` and `NxNworkgroupInternetBridge.nsm`.*

### Windows Services

See “Avid Workgroup Preview Server Service” on page 244.

### Requirements

See “Avid Workgroup Preview Server Service” on page 244.

## Avid Workgroup Server Browser Service

The Avid Workgroup Server Browser service is responsible for providing information about the Interplay Engine server to Avid Interplay clients and searching for the available servers and databases. The Avid Workgroup Server Browser listens to port 8313.

### Processes

The process running is usually listed as `NxNworkgroupServerBrowser.exe` or `NxNworkgroupSe`. This process launches the Avid Interplay Engine Server during startup.

### Windows Services

The Avid Workgroup Server Browser is started automatically at system startup. This service always runs under the local system account. The main task of this service is to start the main Avid Interplay Engine process (`NXNServer.exe`). In order to access files on the file server, the main Interplay Engine process needs to run under a user account that has access to the file server.

### Requirements

- The Avid Workgroup Server Browser must run on the same machine as the Avid Interplay Engine Server.
- Port 8313 needs to be open.

## Avid Workgroup Preview Server Service

The Avid Workgroup Preview Server service generates upon demand thumbnails and preview images of items already in the database.

For items only on the local machine (not imported yet), the previews are generated directly on the client machine.

On both the Preview Server and on the local machine, cache directories keep the generated previews.

- On the Preview Server: in the directory you specified during installation, by default `\\IEServer\WG_Database$PreviewServer\Cache`.
- On the local machine: `C:\Documents and Settings\User\Local Settings\Application Data\Avid\Workgroup\Cache\Preview`.

The server is implemented as a module for Apache.

### Connectivity

The Preview Server is accessed only from clients via HTTP. It uses the default port 80.



*Make sure that no other application allocates port 80. For example, IIS might be installed as the default HTTP server. In this case, deactivate the corresponding application.*

### Processes

There are two processes of Apache.exe running. One of them is a watchdog whose only task is to make sure that the main Apache process is running. The main Apache process serves the preview requests of port 80.



*The Avid Interplay Preview Server uses the Apache module `NxNworkgroupPreviewService.nsm`.*

### Windows Services

The `Avid_Workgroup_Preview_Server` is started automatically at system startup. This service always runs under the local system account.

### Requirements

- The Avid Workgroup Preview Server must run on the same machine as the Avid Interplay Engine Server.
- Since the Avid Workgroup Preview Server needs to access the files on the file server during thumbnail rendering, a user with appropriate access rights must be impersonated for each preview action. To ensure that the impersonated user can access the files, we strongly advise setting it to the same user under which the Avid Interplay Engine Server runs.

## A Installed Components and Services

The user name and encrypted password for the impersonation is stored in the following registry keys:

- (32-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionUser
- (32-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionSettings
- (64-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Wow6432Node\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionUser
- (64-bit OS) HKEY\_LOCAL\_MACHINE\SOFTWARE\Wow6432Node\Avid Technology\Workgroup\Avid Workgroup Server\ExecutionSettings



**Change the impersonation settings for the Avid Interplay Preview Server with the NXNServerUser.exe tool only. See “Troubleshooting the Server Execution User Account” on page 204.**

### Configuring the Preview Service

The Preview Service is responsible for the generation of thumbnails and preview images on the server, as well as delivering them to the Interplay application.

All settings can be edited in the workgroup.xml file in the <preview><settings ... /> section. This file is located in the Interplay Engine installation directory, for example,

- C:\Program Files\Avid\Avid Interplay Engine\Data\Apache\conf\workgroup.xml (non-cluster systems)
- S:\WorkgroupData\Apache\conf\workgroup.xml (cluster systems).

The settings should look similar to the following. Default settings are shown; the actual file references the locations you specified during installation:

```
<settings

CacheRoot="C:\WG_Database$\PreviewServer\Cache"

IconRoot="C:\Program Files\Avid\Avid Interplay
Engine\Data\Apache/icons"

ServerEnableDiskGuard="yes"

ServerCacheMinFreeDiskSpace="250mb"

ThumbnailImageFormat="png"

ThumbnailsUseAlpha="yes"

PreviewsUseAlpha="yes"

/>
```

The Preview Server reads the settings from this file when the service is started. This means settings become active only after you restart the Preview Server. You can do this without restarting the whole machine by restarting the service `Avid_Workgroup_Preview_Server`. Select Control Panel > Administrative Tools > Services, double-click the service, and click Start.

### Description of Preview Generation Settings in `workgroup.xml`

- **CacheRoot:** Path where previews and thumbnails generated by the preview server are stored. This location is used by the preview server to create a cache of converted images. The preview server can reuse those images for subsequent requests from any client. To ensure best performance, this path should reside on a disk that has enough free space available to hold a reasonable working set of cached images. While the default is inside of the database directory of the Avid Interplay Engine, it is a good idea to place it on a different disk.
- **IconRoot:** Path to a directory where a set of icons is stored, usually pointing into the Avid Interplay Engine installation directory. The icons stored here are used by the Preview Server if, for example, a thumbnail generation failed or if an asset has an unknown format or is not an image/video file.
- **ServerEnableDiskGuard:** If “yes”, the free space on disk is constantly checked and cache files are purged if necessary. If “no”, cache files are never deleted. “1” and “0” are other possible notations.

## A Installed Components and Services

- **ServerCacheMinFreeDiskSpace:** If the disk guard is enabled it tries to ensure that the disk cache leaves at least this amount of space free on the disk. The disk guard cannot always ensure this limit because it works in parallel to the normal preview server operation and other applications might store data on the same disk. Use a value that is high enough to overcome spike usage on your disk. The disk guard removes the oldest cached files first.

Values are by default (no suffix) in megabytes, but can be specified in gigabytes ('gb'), or terabytes ('tb'), respectively ('1gb' == '1024').

- **ThumbnailImageFormat:** This is the format used by client application to request thumbnails. This should always match the requests made by the client application. It is advisable to set this to “png.” Note: The client does not change the request format if this setting is changed.
- **ThumbnailsUseAlpha:** If “yes,” generated thumbnails use the alpha channel to let a white background shine through the normal image. Use “no” to ignore alpha channel information.



*Generated thumbnails never contain any alpha information. This setting only renders the alpha channel into the normal image data.*

- **PreviewsUseAlpha:** If “yes,” generated preview images are delivered to the client with the alpha channel included (if it is actually displayed is a client option). Use “no” to generate previews without any alpha channel information.

## Avid Workgroup TCP/COM Bridge Service

The Avid Workgroup TCP/COM Bridge service acts as bridge to the Avid Interplay Engine Server.

The Avid Workgroup HTTP Server needs the Avid Interplay TCP/COM Bridge to connect to the Avid Interplay Engine Server.

### Connectivity

The Avid Workgroup TCP/COM Bridge listens to port 8318.

### Processes

The process running is usually NXNTCP~1.exe from NXNTCPCOMBridge.exe.

### Windows Services

The service “Avid Workgroup TCP COM Bridge” is automatically started at system startup and should be running all the time.



## Requirements

- The Avid Workgroup Server Browser must run on the same machine as the Avid Interplay Engine Server.
- The Avid Workgroup TCP/COM bridge needs to run under the same user account as the Avid Interplay Engine Server. To check under which user the bridge runs, use the Windows Services Control Panel.

To check the user account, click Start, click Run, and type services.msc. Right-click Avid Workgroup TCP COM Bridge and select Properties. In the Log On tab, the This Account option should display the Server Execution User.



**Use the tool NXNServerUser.exe to change the Server Execution User. Do not change the settings in the Control Panel. See “Troubleshooting the Server Execution User Account” on page 204.**

## Avid Workgroup VSS Service

The Avid Workgroup VSS service provides backup functionality to the Avid Interplay Engine (Interplay version 2.1 and later only). By working with the Windows Volume Shadow Copy service, it significantly reduces the impact of the backup process on other engine operations.

The Avid Interplay Engine needs the Avid Workgroup VSS Service to create scheduled backups of its databases.

### Connectivity

The VSS Service communicates with the Avid Interplay Engine using standard Operating System pipes.

### Processes

The process running is usually IEVSS~1.EXE or IEVSSService.exe.

### Windows Services

The Avid Workgroup VSS service is automatically started at system startup and should be running all the time. This service always runs under the local system account. The Avid Workgroup VSS service requires that the Windows Volume Shadow Copy service is also running. The Windows Volume Shadow Copy service is installed by default and started automatically.

## A Installed Components and Services

### Requirements

- The Avid Workgroup VSS service must run on the same machine as the Avid Interplay Engine Server.
- The Avid Workgroup VSS service requires that the Windows Volume Shadow Copy service is also running.

## Avid Workgroup Engine Monitor Service

The Avid Workgroup Engine Monitor is responsible for creating the Engine Server process and for monitoring the health of the Engine Server process, the Apache HTTP server, and the TCP/COM Bridge. On Failover Cluster installations this service is controlled by a cluster resource of the same name.

The Avid Workgroup Engine Monitor regularly tries to connect to the Engine Server process, the Apache HTTP server, and the TCP/COM Bridge. If those components are too slow to respond or do not respond at all, the Engine Monitor will trigger restarts of those components through the corresponding cluster resources.

The Avid Workgroup Engine Monitor logs actions and health issues to the Application Event log.

### Example 1: Startup:

```
Avid Workgroup Engine Monitor Event ID 22: Service has been started successfully
```

```
Avid Workgroup Engine Monitor Event ID 28: Workgroup Engine process started
```

```
Avid Workgroup Engine Monitor Event ID 30: Monitoring thread started: thorough ping 90 sec, heart beat max idle 90 sec, monitoring interval 15 sec
```

### Example 2: COM Failure

```
Avid Workgroup Engine Monitor Event ID 42: Failed to connect Workgroup Engine with DCOM 'Error 800706bb happened 8 times within the last 14981 msec'
```

```
Avid Workgroup Engine Monitor Event ID 31: Thorough check failed: Result code: 0x800706be
```

```
Avid Workgroup Engine Monitor Event ID 33: Monitoring thread terminated
```

## Processes

The process running is usually listed as IEMonitorService.exe or IEMONI~1.EXE.

## Windows Services

The service Avid Workgroup Engine Monitor is started by the cluster resource “Avid Workgroup Engine Monitor.”

## Requirements

- The Avid Workgroup Engine Monitor must run on the same machine as the Avid Interplay Engine Server. (This is ensured by the “Avid Workgroup Server” cluster resource group.)
- The Avid Workgroup Engine Monitor needs to run under the same user account as the Avid Interplay Engine Server. To check under which user the Engine Monitor runs, use the Windows Services Control Panel.

To check the user account, click Start, click Run, and type services.msc. Right-click Avid Workgroup Engine Monitor and select Properties. In the Log On tab, the This Account option should display the Server Execution User.

## A Installed Components and Services

## **B** Interplay Engine Configuration Files

The following topics provide information for configuration that you might need to do only under certain circumstances, such as troubleshooting:

- [Configuring the Server Event Manager](#)
- [Configuring Client Access](#)
- [Setting the Filetransfer Server](#)

If you are moving the file repository to a shared-storage workspace, you need to edit the workgroup.xml file. See “[Configuring the workgroup.xml File](#)” on page 219.

### **Configuring the Server Event Manager**

The Server Event Manager is a service that automatically informs administrators whenever an important event occurs on the server, for example, when the hard drive is almost full. Basic settings are configured in the Config.xml and LogWatch.xml files.

Consider the following:

- When the Interplay Engine server sends e-mails, it uses the login of the Server Execution User. Make sure the mail server is aware of the username and password of this account (usually a domain account). If the mail server is not aware of this account, it might reject the e-mail request.
- E-mail service might be unreliable if there are too many event notices in a short time frame. Some events might be dropped. Because a large number of event notices indicates a problem, the administrator needs to investigate and correct the problem.

#### **Config.xml File**

The Avid Interplay Engine reads its event manager settings from a file called Config.xml. By default, e-mail notification is disabled in the installation program. If you select e-mail notification during installation, basic settings are created in this file. If you want to add e-mail notification after installation, you can edit the Config.xml file.

The Config.xml file is located in the Avid Interplay Engine installation directory, for example, C:\Program Files\Avid\Avid Interplay Engine\Data\Server\Config.

## B Interplay Engine Configuration Files

The configuration file is an XML file that has the following format:

```
<XML>

<Events>

<Event Name="Name of Event">

<Action Name="Name of Action">

<Parameter Name="Name of Parameter">

Value of Parameter

</Parameter>

...

</Action>

<Parameter Name="Name of Parameter">

Value of Parameter

</Parameter>

...

</Event>

<Parameter Name="Name of Parameter">

Value of Parameter

</Parameter>

...

</Events>

</XML>
```

The `<Events>` block specifies to which events the Avid Interplay Engine should react. The `<Events>` block contains `<Event>` blocks that specify the names of the events that you want configured here.

Inside each `<Event>` block is the `<Action>` block that specifies the actions to be performed whenever an event occurs. The attribute “Name” describes which action is to be performed.

The <Parameter> blocks are used to specify the behavior of an action. It is also possible to identify a parameter by its “Name” attribute. Parameters are identified by their “Name” attributes.

Whenever the server performs an action, it searches the parameters from the inside out, which means it searches the parameter block inside the <Action> block first and then inside the <Events> block. This allows you to specify a parameter for all events. Alternatively, you can specify a parameter for all actions of an event.

Note the following:

- When the Interplay Engine server sends e-mails, it uses the login of the Server Execution User. Make sure the mail server is aware of the username and password of this account (usually a domain account). If the mail server is not aware of this account, it might reject the e-mail request.
- E-mail service might be unreliable if there are too many event notices in a short time frame. Some events might be dropped. Because a large number of event notices indicates a problem, the administrator needs to investigate and correct the problem.

## Supported Actions in Config.xml

The following section describes the action that is currently supported in Avid Interplay and that is configured in Config.xml to be performed when an event occurs.

## B Interplay Engine Configuration Files

### SendMail

The SendMail action is configured with the following XML block:

```
<Action Name="SendMail" >
<Parameter Name="SenderMachine" >
SERVERMACHINE
</Parameter>
<Parameter Name="RCPTList" >
administrator@mydomain.com, info@mydomain.com
</Parameter>
<Parameter Name ="SenderAddress" >
ServerExecutionUser@mydomain.com
</Parameter>
<Parameter Name="SMTPServer" >
123.123.123.123
</Parameter>
</Action>
```

The “SenderMachine” parameter specifies the name of the machine on which the server resides.

The “RCPTList” parameter contains a comma separated list of valid e-mail addresses. These addresses should receive an e-mail whenever the server performs an action.

The “SenderAddress” parameter contains the e-mail address of the sender (the Server Execution User). The sender should act as the originator of the sent e-mail.

Make sure the mail server is aware of the username and password of this account (usually a domain account). If the mail server is not aware of this account, it might reject the e-mail request.

The “SMTPServer” parameter contains a valid IP address of the mail server to which the mail is to be sent.



## Supported Events in Config.xml

The following sections describe the events that are currently supported in Avid Interplay and that can be configured in Config.xml as events to which the Avid Interplay Engine should react.

### DiskLimit Event

The “DiskLimit” event is configured with the following XML block:

```
<Event Name="DiskLimit">
<Parameter Name="FreeSpace">
30 100 500
</Parameter>
</Event>
```

The “FreeSpace” parameter contains a list of numbers that specify the free space on the disk in megabytes. Whenever the free space falls below one of the specified numbers, it triggers the server to perform one of the configured actions.

### BackupFailed Event

The “BackupFailed” event is triggered whenever the automatic backup of a database fails, that is, when the \_Database folder cannot be copied to the backup location.

The “BackupFailed” event is configured with the following XML block:

```
<Event Name="BackupFailed">
</Event>
```

To send an e-mail when a “BackupFailed” event is triggered, use the “SendMail” action described in [“Supported Actions in Config.xml” on page 255](#).

### LogEvent Event

The “LogEvent” event is triggered according to the settings in the LogWatch.xml, in which an administrator can specify what actions should happen if a severe problem inside of the Interplay Engine occurs (for example, send an e-mail or shut down the server). The file allows a rough definition by severity of the problem or a very detailed configuration via the message ID of the problem.

## B Interplay Engine Configuration Files

The LogEvent is configured in the Config.xml with the following XML block:

```
<Event Name="LogEvent" >  
  
</Event>
```

To send an e-mail when a “LogEvent” event is triggered, use the “SendMail” action.

See also “[LogWatch.xml](#)” on page 260.

### **ClusterResourceFailure Event**

The “ClusterResourceFailure” event is triggered only in a failover cluster setup. It is sent whenever a problem inside the cluster is detected.

The “ClusterResourceFailure” event is configured with the following XML block:

```
<Event Name="ClusterResourceFailure" >  
  
</Event>
```

To send an e-mail when a “ClusterResourceFailure” event is triggered, use the “SendMail” action.

## Server Event Configuration Example

The following is an example of the configuration of a server to send e-mails whenever the backup fails, or the free space on a server disk reaches one of the limits set, in this case 30, 100, or 500 MB:

```
<XML>

<Events>

<Event Name="DiskLimit">

<Action Name="SendMail">

</Action>

<Parameter Name="FreeSpace">

30 100 500

</Parameter>

</Event>

<Event Name="BackupFailure">

<Action Name="SendMail">

</Action>

</Event>

<Parameter Name="SenderMachine">

SERVERMACHINE

</Parameter>

<Parameter Name="RCPTList">

administrator@mydomain.com, info@mydomain.com

</Parameter>

<Parameter Name="SenderAddress">

ServerExecutionUser@mydomain.com

</Parameter>

<Parameter Name="SMTPServer">
```

## B Interplay Engine Configuration Files

```
123.123.123.123
```

```
</Parameter>
```

```
</Events>
```

```
</XML>
```

Here is an example of an e-mail sent by the Event Manager:

```
11/23/1999 12:09:14 [WGServer]
```

```
INFO:
```

```
This is a message sent by the Event Manager.
```

## LogWatch.xml

Log event notifications are configured in LogWatch.xml, located in the Avid Interplay Engine installation directory:

C:\Program Files\Avid\Avid Interplay Engine\Data\Server\Config.

Edit this file to assign actions for different log events. Actions can be assigned to all message events of a given severity or to specific events by message IDs.

Action	Value
None	0
Send mail	1
Shutdown server	2
Shutdown and lock server	3

ID	Severity
-500	Dump (debug dumps)
-400	Info (internal info)
-300	Message (external info, for users)
-200	Notes (status messages like "database opened successfully")

ID	Severity
-100	[WARN] (warnings like “loading took more than 3 sec”)
0	[ERROR] (normal errors, like “file couldn't be imported because it exists already”)
100	[FATAL] (Recoverable critical Errors, like “couldn't save database - disk full”)
200	Critical (non-recoverable errors, such as crashes)

## Sending E-mail Notifications from LogWatch.xml

**To send e-mail notification on any error with a specific severity level:**

- ▶ Add a mapping entry to LogWatch.xml within the <SeverityMappings> scope.

For example:

```
<SeverityMappings>
<Mapping Severity = "<severity level>" Action = "<action id>"/>
</SeverityMappings>
```

For example, following entry sends an e-mail on every [FATAL]:

```
<SeverityMappings>
<Mapping Severity = "100" Action = "1"/>
</SeverityMappings>
```

To configure how and where the event notification should be sent, see [“Supported Actions in Config.xml” on page 255](#).

**To send e-mail notification on a specific message event:**

- ▶ Add a mapping entry within MessageMapping scope (the message ID is decimal number)

```
<MessageMappings>
<Mapping MessageID = "<msg id>" Action = "<action id>"/>
</MessageMappings>
```

## B Interplay Engine Configuration Files

The message ID is the last number in brackets before the actual message string in the log file. The message ID of the entry below is 0x00004678. Note that the log file displays hexadecimal ids. You need to convert the numbers to decimal format before adding to the message mapping.

```
[Thu Sep 16 17:27:43 2004] [FATAL] [.\NxNDbServer.cpp           ] [
4627]

[0000034c] [00004678] Could not connect to Central Configuration
Service 'XXX' for database 'YYY'
```

The message mapping for the error [4678] hex (which is 18040 in decimal) triggering “Send email” action looks like the following:

```
<MessageMappings>
<Mapping MessageID = "18040" Action = "1"/>
</MessageMappings>
```

## Configuring Client Access

The configuration file ServerXML.xml allows you to specify the client access when accessing the server using HTTP from the client. In this configuration file, you specify servers that should be visible to clients, which databases are available, and which users are allowed to access these databases.

The Configuration file is located in a folder in the Avid Interplay Engine installation directory, by default, C:\Program Files\Avid\Avid Interplay Engine\Data\TCPComBridge. You configure access for the client in this file. The ServerXML.dll resides at NxN/Workgroup.



*Settings you configure in the User Management view through the Avid Interplay Administrator also apply to the databases (see “Managing Database Roles” on page 118). These settings are an additional security layer on top of the Avid Interplay User Management.*

### Configuring Access

The <server> token specifies the name of the server on your network that should be visible to clients connecting to a single server machine. Make sure that all of the database directories to be accessed are shared and visible on the single server machine.

Through <project> tokens, you specify which databases should be visible to clients connecting to the single server. The token can have two attributes: “name” and “access.”

The “name” attribute specifies the name of the database. This name must be the same as the name of the database configured in the Active Database List through the Avid Interplay Administrator. If a database is not in the Active Database List, it cannot be made visible by specifying its name in <project> token either. You can also use the “\*” as a wildcard character representing all databases in the Active Database List.

The “access” attribute specifies the type of access for the database. If it is set to “allow,” clients can see the database in the database browser and are allowed to access it. If the attribute is set to “deny,” the database is not accessible and is not even visible to the clients. By default, everything is set to “deny.”

With the <user> token, you specify which users are allowed to connect to a database. As with the <project> token, the “name” and “access” attributes can also be used here. The name attribute is the name of a user in the database. The “name” attribute supports the “\*” (wildcard) value representing all users.

Database and user settings are inherited from the parent node in the token tree if the settings are not specified on the current level. This allows you to specify access permissions for all databases on a server, or even for all servers.

The additional attribute “emptypassword” is supported for the <project> and <server> tokens. This attribute can be set to the value “allow” or “deny.” If set to “deny,” then all connection attempts by a user with no password specified are refused by the server or the database, respectively. By default, whenever you create a user in an Avid Interplay database, the password is set to empty. Avid highly recommends setting this value to “deny” for security reasons.

Following are some examples illustrating the configuration of database and user access.

### Example 1:

```
<XML>
  <server name="WGSERVER">
  </server>
</XML>
```

The server WGSERVER is visible to the outside, although no databases are accessible.

## B Interplay Engine Configuration Files

### Example 2:

```
<XML>

  <server name="WGSERVER" >

    <project name="*" access="allow" emptypassword="deny" >

      <user name="*" access="allow" />

    </project>

  </server>

</XML>
```

All databases on server WGSERVER are visible and any user can connect to the database. For all databases, connection requests with empty passwords are refused.

### Example 3:

```
<XML>

  <server name="WGSERVER" emptypassword="deny" >

    <project name="*" access="allow" >

      <user name="*" access="allow" />

      <user name="Administrator" access="deny" />

      <user name="John" access="deny" />

    </project>

  </server>

</XML>
```

All users except Administrator and John are allowed to access the databases on server WGSERVER. For all databases on the server, connection requests with empty passwords are refused.



**Example 4:**

```

<XML>

  <server name="WGSERVER">

    <user name="*" access="allow" />

    <user name="Administrator" access="deny" />

    <user name="John" access="deny" />

    <project name="Project1" access="allow" />

    <project name="Project2" access="allow">

      <user name="Nina" access="deny" />

    </project>

  </server>

</XML>

```

All users except Administrator and John are allowed to access the databases “Project1” and “Project2.” Access to “Project2” for the user “Nina” is refused.

**Example 5:**

```

<XML>

  <project name="*" access="allow" />

  <user name="*" access="deny" />

  <user name="Administrator" access="allow" />

  <server name="WGSERVER" />

</XML>

```

All databases on the specified servers are accessible only to Administrators.

## Setting the Filetransfer Server

Additional configuration might be required when the Interplay Server is running inside of a network configured using NAT. In this case, the IP returned by the Avid Interplay Engine is the internal address and not the external address needed by the client. The following change

## B Interplay Engine Configuration Files

in the workgroup.xml configuration file tells the client to connect to the file transfer server via its name instead of address. This allows clients to connect to the file transfer server in most standard NAT configurations.

```
<XML>
...
<http>
<filetransferservername>
myserver.mydomain.com
</filetransferservername>
</http>
...
</XML>
```

This file is located in the Interplay Engine installation directory, for example,

- C:\Program Files\Avid\Avid Interplay Engine\Data\Apache\conf\workgroup.xml (non-cluster systems)
- S:\WorkgroupData\Apache\conf\workgroup.xml (cluster systems).

# C Valid and Invalid Characters in Avid Interplay

The following table lists the valid and invalid characters (also known as special characters) for Avid Interplay.

	<b>Allowed</b>	<b>Not Allowed</b>
Avid asset names		Characters: / \
File asset names	All characters allowed for files in Windows	Characters: * ? : / \ " < >   Names ending with a dot Names used as DOS devices (LPT1, com1, ..., .., for example)
Property names (metadata field names)		Characters: / \
Video ID metadata field		Spaces, or characters / \ : * ? " < >
Users and user groups		Characters: / \   " ' < >

Although the following characters are valid for users and user groups in Interplay, they are not supported when naming projects, bins, and users on Avid editing systems:

: \* ? < >

Do not use these characters in Interplay user names or group names.

For information on International Character Support (ICS), see the Avid Interplay Help.



*When you name a Mac OS X computer, use single-byte ASCII characters without spaces.*

## C Valid and Invalid Characters in Avid Interplay

# D System Metadata Properties

Metadata is textual data you can use to identify and describe the creation, contents, and disposition of the clip or shotlist you are logging. Avid Interplay comes with an extensive list of system metadata.

The administrator determines some of the metadata properties that can be viewed in Interplay Access as headings in the Content View and Object Inspector, and also used in Interplay searches. Some metadata properties are always available and cannot be disabled.

By default, the Interplay Engine includes default sets of properties for Broadcast, Post and Film layouts, as described in the following table.

<b>Broadcast</b>		<b>Post</b>		<b>Film</b>	
<b>Content Default</b>	<b>Inspector Default</b>	<b>Content Default</b>	<b>Inspector Default</b>	<b>Content Default</b>	<b>Inspector Default</b>
Comments	Comments	Comments	Comments	Camroll	Camroll
Created By	Duration	Created By	Created By	Comments	Comments
Creation Date	Media File Format	Creation Date	Creation Date	Duration	Duration
DRM	Name	DRM	Duration	End	End
Duration	Tape ID	Duration	Media File	KN Dur	KN Dur
Format	Tracks	Format	Format	KN End	KN End
Media Status		Media Status	Name	KN Start	KN Start
Modified Date		Modified Date	Tape	Name	Name
Name		Name	Tracks	Pullin	Pullin
Tape ID		Tape		Pullout	Pullout
Tracks		Tracks		Start	Start

The following table lists all system metadata properties.

## D System Metadata Properties

<b>Heading</b>	<b>Description</b>	<b>Search Values and Hints on Searching in Interplay</b>
All Custom	All custom properties defined in the Property Layout of the Interplay Administrator.	Searches for all the custom properties that are set.
Access Rights	The access level or user role assigned to a particular folder or asset. The column displays an icon that represents the type of access.	
AudioBitDepth	Audio bit depth used when you work with audio files: 16 bit or 24 bit.	Type a value or use the arrows to select a value.
AudioFormat	Audio format of master clips (AIFF-C, SDII, or WAVE).	
AudioSR	Audio resolution (sample rate).	
AuxTC24	Original HDTV sources (1080p/24) or audio DATs created for PAL feature film productions that use in-camera timecode.	Type numbers only in the four colon-separated entry fields displayed.
Auxiliary Ink	Auxiliary ink format settings allow you to display an additional type of ink number. This lets you track additional types of film information for different film gauges. Used for 24p projects, 25p projects, and matchback projects only. Auxiliary Ink is the starting frame for the clip.	
AuxiliaryTC1 through TC5	You can type an auxiliary timecode or another timecode for editing film or audio timecode for film.	Type numbers only in the four colon-separated entry fields displayed.
AuxInkDur	Length of the clip, expressed in the auxiliary ink number.	Type numbers only in the four colon-separated entry fields displayed.
AuxInkEdge	Type of edgecode used in the auxiliary ink number.	
AuxInkEnd	Ending auxiliary ink number for the clip.	Type numbers only in the four colon-separated entry fields displayed.
AuxInkFilm		

<b>Heading</b>	<b>Description</b>	<b>Search Values and Hints on Searching in Interplay</b>
Cadence	Type of pulldown present on the source NTSC tapes when in a 23.976 or 24p project.	
Camera	Camera used to film this clip. This feature is used in multicamera shoots.	
Camroll	Camera roll containing this clip. Used for 24p projects, 25p projects, and matchback projects only.	
Category	Assigned category. Categories are defined by the administrator in the Configure Categories view of the Interplay Administrator.	Set to Ignore by default, change to a category name to search only for items assigned to that category.
CFPS	Captured frames per second.	Type a value or use the arrows to select a value.
Color	The text display color for metadata of the selected item in all Interplay Access displays.	Returns items of selected color found. The search does not find items colored only by inheritance (only the parent is returned).
Comments	Displays any comments added as metadata to the media file when it was originally ingested or captured. You can edit this field in Interplay Access.	Type text.
Created by	Displays the name of the user who created the shotlist.	
Creation Date	When the asset was created.	Select a time range and a particular date (for example, 12/4/04 or 12/4/2004) or a time period from the pop-up menu. Click the calendar to get clickable calendar.
Current Video Resolution	Last resolution checked in with the asset.	
Current/Last User	Last user that checked the asset in or out.	
Data Format	Data format AAF or OMF.	Select Is and then either AAF or OMF.
Date Deleted	(Orphan Clips folder only) Displays the date and time the last links was deleted.	

## D System Metadata Properties

Heading	Description	Search Values and Hints on Searching in Interplay
Deleted By	(Orphan Clips folder only) displays the user name of the person who deleted the last link.	
Disk Label	Displays the XDCAM disk label created when you import XDCAM media. (This value is not currently displayed in Interplay Access.)	
DPX	Frame-counting field for Digital Picture Exchange, a SMPTE standard describing frames scanned from film. The format is the following: a descriptor of up to 32 alphanumeric characters, followed by a hyphen (-), followed by a six-digit frame count, for example, DPXChildDocu-023657.	
DRM	Digital Rights Management property. Has the special operators Has DRM and Does not have DRM.	Depending on the search flags, this search can retrieve links to the assets, assets or links and assets which have at least one DRM protected media somewhere in the structure. Searches for DRM should return all of the sequences, subclips, rendered effects, and so on that use a restricted master clip. DRM is referred to as “restrictions” in Interplay Assist, Avid Instinct, and Avid editing systems.
Duration	The length of the asset in hours, minutes, seconds, and frames.	Type numbers only in the four colon-separated entry fields displayed.
End	Timecode of the clip’s tail frame.	Type numbers only in the four colon-separated entry fields displayed.
FilmTC	Timecode used on film. Used for 24p and 25p projects only.	Type numbers only in the four colon-separated entry fields displayed.
Format	The format of a clip or sequence as determined by the project type, such as 30i NTSC or 1080i/59.94. This is especially useful if you have both SD and HD clips in the same bin.	



<b>Heading</b>	<b>Description</b>	<b>Search Values and Hints on Searching in Interplay</b>
FPS	Play rate: the number of frames to be displayed each second. The default is 29.97 for NTSC and 25 for PAL for video. The play rate can also be 24 or 23.98.	Type a value or use the arrows to select a value.
Frame Chase Expected Duration	Expected length of a clip captured by the Frame Chase Editing method.	Type numbers only in the four colon-separated entry fields displayed.
Frame Chase Known Duration	Current length of a clip being captured by the Frame Chase Editing method.	Type numbers only in the four colon-separated entry fields displayed.
In Use	If Is in use, asset is referenced by a sequence also in the database.	Select Is in use or Is not in use.
IN-OUT	The length of the marked segment of a clip, if any.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Initial Checkin Date	Date that the asset was first checked in.	Select a time range and a particular date (for example, 12/4/04 or 12/4/2004) or a time period from the pop-up menu. Click the calendar to get clickable calendar.
InkDur	Length of the clip, expressed in ink number. Used for 24p projects, 25p projects, and matchback projects only. You cannot modify this number.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
InkEdge	Type of edgecode used in the ink number.	
InkEnd	Ending ink number for the clip. You cannot modify this number.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
InkFilm	Film gauge for the ink number.	
InkNumber	Ink number for the clip. Used for 24p projects, 25p projects, and matchback projects only.	
KNDur	Length of the clip, expressed in feet and frames. Used for 24p projects, 25p projects, and matchback projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.

## D System Metadata Properties

<b>Heading</b>	<b>Description</b>	<b>Search Values and Hints on Searching in Interplay</b>
KNEnd	Ending key number for the clip. Used for 24p projects, 25p projects, and matchback projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
KNFilm	Key number film gauge.	
KNIN-OUT	Mark IN and Mark OUT key number for the clip. Used for 24p projects, 25p projects, and matchback projects only.	
KNMarkIN	Key number for the IN point, if you set one for the clip. Used for 24p projects, 25p projects, and matchback projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
KNMarkOUT	Key number for the OUT point, if you set one for the clip. Used for 24p projects, 25p projects, and matchback projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
KNStart	Starting key number for the clip. Used for 24p projects, 25p projects, and matchback projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Labroll	Labroll containing the clip.	
Last Checkin Date	Date when the asset was last checked in.	Select a time range and a particular date (for example, 12/4/04 or 12/4/2004) or a time period from the pop-up menu. Click the calendar to get clickable calendar.
LUT	File name of the color look-up table used for the series of clips or frames.	
Mark IN	Timecode for the IN point, if you set one for the clip.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Mark OUT	Timecode for the OUT point, if you set one for the clip.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Master Dur	Length of the final master sequence, expressed in feet and frames. You cannot modify this number.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.

<b>Heading</b>	<b>Description</b>	<b>Search Values and Hints on Searching in Interplay</b>
Master Edge	Type of edgecode used in the final master sequence.	
Master End	Ending key number for the final master sequence. You cannot modify this number.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Master Film	Gauge of the final master sequence.	
Master Start	Starting key number of the final master sequence. Used for 24p projects, 25p projects, and matchback projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Media File Format	Clip media format.	MXF or OMF.
Media Size	Media file size.	Specify KB, MB, GB and type a number. Note that this specification cannot be saved in a Saved Search.
Media Status	Online, offline, or partially offline status, or exists on another workgroup.	Select is/is not, and then online, offline, partial, or nearonline.
Modified Date	When the asset was last modified (from the bin).	Select a time range and a particular date (for example, 12/4/04 or 12/4/2004) or a time period from the pop-up menu. Click the calendar to get clickable calendar.
Name	The name of the asset.	Type text (not case sensitive; spaces permitted).
Original Bin	Name of the bin where the media for this asset was originally captured.	
Original Machine Name	Name of the computer where the media for this asset was originally captured.	
Original Path	(Orphan Clips folder only) Displays the folder path for an asset whose last link was deleted.	
Original Project	Name of the project under which the media for this asset was originally captured.	Project name (dropdown list).
Offline	Track names for any media files that are offline.	

## D System Metadata Properties

Heading	Description	Search Values and Hints on Searching in Interplay
Path	Path to assets in the Interplay database.	Meant to be used in conjunction with other search conditions to narrow the area where the results are coming from: for example, combine a search for all masterclips that have been updated in the last 10 minutes and that are in path "/Projects/MyName/MyBin2." Select is or is not, then click the Select button and choose a path from the tree. Alternately, select contains or does not contain and type text.
Perf	Film edge perforations format used for 3-perf projects. Used for projects brought forward from earlier releases only; now superseded by the film size and perf options available in Ink Film, AuxInk Film, KN Film, and Master Film.	
Playable in Access	A green triangle in this column indicates that a clip is can be played in the Interplay Access Monitor. Also applies to subclips or shotlists created from playable clips.	
Pullin	Telecine pulldown of the first frame of the clip (pulldown phase). Pullin can have the values A, B, X (matchback only), C, or D. Used for NTSC 24p projects and matchback projects only.	
Pullout	Telecine pulldown of the last frame of the clip. Pullout can have the values A, B, X (matchback only), C, or D. Used for 24p projects and matchback projects only. (NTSC only)	
Record Complete	Indicates whether the capture operation is finished for this asset.	
Reel #	Source reel number. Used for 24p and 25p projects only.	
Reservation	Indicates whether there is a reservation applied to this asset.	

<b>Heading</b>	<b>Description</b>	<b>Search Values and Hints on Searching in Interplay</b>
Reserved	Indicated item is reserved for specified timeframe by specifies user.	Select a user and then select a time frame.
Scene	Scene number of the clip.	Type text.
ShootDate	Date the footage was shot.	
Slip	Number and direction of perfs for subclips (audio clips only).	
SoundTC	Timecode for audio.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Soundroll	Sound roll this clip came from. Used for 24p projects, 25p projects, and matchback projects only.	
Start	Timecode of the clip's head frame.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Take	Take number of the scene.	Type a number.
Tape	Source tape name (from the bin).	Type text (not case sensitive; spaces permitted).
TC24	24-fps timecode.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
TC25	25-fps timecode, no pulldown. Used for 24p and 25p projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
TC25P	25-fps timecode with PAL pulldown. Used for 24p and 25p projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
TC30	30-fps timecode with 2:3 pulldown. Used for 24p and 25p projects only.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
TC30NP	30-fps timecode with no pulldown (frames 00 through 29).	Select an operator and then type numbers only in the four colon-separated entry fields displayed.

## D System Metadata Properties

Heading	Description	Search Values and Hints on Searching in Interplay
TC60	60-fps timecode. Used for HD projects.	Select an operator and then type numbers only in the four colon-separated entry fields displayed.
Text		Combination of Name, Tape, User Attributes, Comments, and Annotations attributes. Allows you to search for text in all attributes at once. Type text (not case sensitive; spaces permitted).
Tracking	Displays colored icons that indicate the status of shared assets across workgroups. For more information, see “Viewing the Status Assets Across Workgroups (Asset Tracking).”	
Tracks	All tracks used by the asset (from the bin)	Select Video, Audio, or Both.
Transfer	Frame-counting field for sources that have been prepped for transfer. The format is the following: a descriptor of up to 32 alphanumeric characters, followed by a hyphen (-), followed by a six-digit frame count, for example, TransferChildDocu-023657.	
Type	Type of asset.	Select an operator and then an asset type from the dropdown list.
UNC Path	Universal Naming Convention that specifies the location of resources on a server. The location you type becomes a hyperlink to that location. Ctrl+click the cell, and then type the location.	
Version Comment		
VFX	Frame-counting field for visual effects. The format is the following: a descriptor of up to 32 alphanumeric characters, followed by a hyphen (-), followed by a six-digit frame count, for example, FXChildDocu-023657.	
VFX Reel	Source reel identification for the FX shot.	

---

<b>Heading</b>	<b>Description</b>	<b>Search Values and Hints on Searching in Interplay</b>
Video ID	Lists the identification number created to track a clip in a broadcast environment. This ID is equivalent to the Tape ID in Avid editors. You can edit this field in Interplay Access.	
VITC	Vertical interval timecode.	
Workspace	Name of an Avid shared-storage workspace	Type the name of the workspace.

---

## D System Metadata Properties



# **E** Server Error Codes

The following table lists the error codes and the textual expressions that the Interplay Engine can return.

---

0x52e	Logon failure: unknown user name or bad password.
0x525	The specified user does not exist.
0x8000ffff	Failed to open the database (catastrophic failure). Contact your administrator. May require Avid support.
8007000e	out of memory
80070005	Failed to open project: Access denied. The project is deactivated.
80004001	not implemented
80004005	general failure
89990010	out of range
89990011	nesting too deep
89990012	the operation was only partially successful
89990013	operation was canceled
89990020	database not initialized
89990021	database already initialized
89990022	database not available
89990023	database not found
89990024	database not open
89990025	database already exists
89990026	cannot load database initialization file
89990027	unable to write to database. Please contact your system administrator.
89990028	the database is not active
89990030	invalid path

## E Server Error Codes

---

89990031	invalid name
89990032	invalid handle
89990033	invalid destination
89990034	invalid property
89990035	invalid parameter
89990036	invalid filename
89990037	invalid object
89990038	invalid hostname
89990039	invalid macro string or tool installation file
89990040	object not found
89990041	parent not found
89990042	the template for the object could not be found
89990043	titerator is invalid for this iteration-capable command
89990050	property not found
89990051	property not set
89990052	cannot set property
89990053	cannot modify the property
89990054	the property is read-only
89990055	the object's style sheet was not found
89990057	the streamed property name is too long
89990060	folder not empty
89990061	object is not a folder
89990062	an item with that name already exists
89990068	dependency usage too long
89990069	The operation failed because non-versionable objects cannot live in versionable folders
89990070	cannot delete the root object
89990071	tree is not mounted into file system

---

89990072	root object has no parent
89990073	invalid operation for root object
89990080	cannot open file
89990081	cannot write to file
89990082	cannot read from file
89990083	the file does not exist
89990084	file system operation failed
89990085	access to file denied
89990086	sharing violation
89990087	corrupt file
89990090	cannot set mount point
89990091	object not mounted into file system
89990092	cannot create directory
89990093	cannot move directory or file
89990094	cannot copy file
89990095	cannot delete directory or file
89990096	cannot create a link to a link
89990097	folder does not exist
8999009b	cannot move the item to another branch. Due to the branch settings, the source and destination locations are in different branches.
8999009c	cannot create a share to a file in another branch. Due to the branch settings, the share and share target locations are in different branches.
8999009d	The original parent is currently in the recycle bin
8999009e	The original parent does not exist anymore
89990100	database not found
89990101	database with that name already exists
89990102	default database location not set
89990110	workspace not initialized

## E Server Error Codes

---

89990111	workspace already initialized
89990120	already connected to a server
89990121	not connected to a server
89990122	cannot connect to server
89990123	cannot disconnect from server
89990124	The database share on the server is not accessible. Please contact your administrator.
89990130	client connection was refused
89990131	invalid user name or password
89990132	client is not logged on
89990140	cannot lock folders, only files
89990141	cannot lock system items
89990142	the object could not be checked out
89990143	not authorized for this operation
89990144	the item is already checked out
89990145	the item is not checked out
89990146	the item is checked out by someone else
89990147	the object could not be checked in
89990148	the working path for the item is not set
89990149	error during reversal of transaction, file still pending, you must recover manually
8999014a	the item is already checked out to you
8999014b	the item is checked out exclusively by someone else
8999014c	multiple check out is not possible for this item
8999014d	Another check-in operation was performed before yours. Try the merge again against the correct version.
8999014e	The item or one of its children is checked out
89990160	the server evaluation period expired
89990161	limited server license

---

89990162	the dongle is not available on the server
89990163	the registration key is invalid
89990164	the server and client versions are not compatible
89990165	the server could not be instantiated (is the server installed on this machine?)
89990166	the server is locked by the Administrator
89990167	the server is low on virtual memory
89990168	the server is low on disk space
89990169	the server is out of disk space
89990170	the specified search expression is invalid
89990171	the database is locked by the Administrator
89990172	a temporary key cannot be installed if a permanent key is already active
89990173	the server with the CCS is locked by the Administrator
89990174	The server is temporarily locked because of a shutdown
89990175	cannot init indexed search
89990177	The hardware id is invalid
89990178	The license key contained one or more expired licenses. These licenses are ignored.
89990192	The object or one of its sub-objects is locked. It is not possible to make changes to this object.
89990195	the database was created with a newer version and cannot be opened with this server
89990196	The transaction commit failed because a merge is needed
8999019c	a file or folder has a pending change
8999019f	setting a property failed because the condition for setting did not match
899901a4	An item in a folder was removed while the folder was being enumerated
89990200	object not initialized
89990201	object not found
89990202	object already exists

## E Server Error Codes

---

89990220	CopyFile command failed
89990221	file already exists
89990222	file does not exist
89990224	cookie file does not exist
89990225	can not create cookie file
89990226	can not read cookie file
89990227	cookie file is corrupt
89990228	found cookie does not match wanted cookie
89990230	object must support INxNPersistDatabase
89990231	object must support INxNPersistDatabaseObj
89990232	object must support INxNVersionControlProperty
89990233	object must support INxNHandleStore
89990234	object must support INxNHandleStoreObj
89990235	unknown command passed to RunCommand
89990236	requested version was not found
89990237	versions are identical
89990238	not enough free disk space for new version
89990239	can not rollback to latest version
89990240	user is not correctly logged on
89990244	The specified object was already touched in the current transaction
89990250	incorrect cookie
89990251	incorrect user name
89990252	incorrect password
89990253	version control database not found
89990260	lookup for vital creation properties failed
89990261	version control is disabled for this object
89990262	Connect to version control server failed

---

89990280	Copying file from server location to local destination failed
89990290	archive is corrupted
89990291	file is not of correct type
89990292	Disabling version creation for abstract assets is not supported
89990300	the user 'UserManagement' is not allowed
89990301	user rights do not allow this operation
89990302	user/user group exists already
89990303	command exists already
89990304	user does not exist
89990305	user is invalid
89990306	user rights do not allow this operation in system folder
89990307	user rights do not allow this operation in level
89990308	user rights do not allow this operation (no ownership)
89990309	the login was disabled for this database
89990310	database is not a CCS
89990311	The given object is not an action
89990312	The given object is not a role
89990313	The given object is not an action category
89990314	The given action category name already used by another action category
89990315	The given action name already used by another action
89990316	The given action id is already used by another action
89990317	Unable to complete the operation because the action exists with another type
89990318	The given role name already used by another role
89990319	The given role id is already used by another role
89990320	Unable to complete the operation because the role exists with another type
89990321	The operation cannot be performed on a system defined role
89990322	The operation cannot be performed on a system defined action

## E Server Error Codes

---

89990323	The action is not assigned to the role
89990324	The system id's for roles or actions are out - impossible to create new system actions or roles
89990326	The operation is not permitted on the user administrator
89990327	The initialization of the authorization subsystem failed - read message for more information
89990340	The initialization of the user management subsystem failed - read message for more information
89990341	A generic command was called which is not supported for user or group objects
89990342	Internal requirements for user or groups objects are not fulfilled (for example, link broken)
89990351	The given user name is already used
89990352	The given user could not be created
89990353	The user can neither be moved nor removed (that is, users cannot be moved from the Everyone group and the Administrator cannot be moved from the Administrators group)
89990354	The given user shall be destroyed but was not deleted before
89990355	Not a user
89990356	Your user account has been deleted
89990361	The given group name is already used
89990362	The given group could not be created
89990363	The given group can neither be removed nor moved
89990364	the member creation for the given group failed
89990365	the group cannot be destroyed because it contains children
89990366	not a serigraph
8999036	the group must not contain other groups
89990368	the database is from a different CCS and needs a migration
89990369	could not connect to the LDAP server
8999036a	The operation failed because the object is protected by a reservation



---

8999036b	CCS Connection failed
8999036c	CCS is corrupt (for example, GUID missing)
8999036d	The authorization config file is missing
8999036e	The CCS does not have the same version as the server of the database
89990370	An LDAP search enum failed
89990371	Structural changes are not allowed on that object
89990372	No Children can be added to this folder or moved out of this folder
89990401	no handler was found
89990450	There is no open session for this client. If you are using an older version of the client, JXDK or MDK please upgrade to a newer version
89990500	cannot convert variant to given type
89990600	HTTP request error
89990601	continue
89990602	switching protocols
89990603	OK
89990604	created
89990605	accepted
89990606	non-authoritative information
89990607	no content
89990608	reset content
89990609	partial content
89990610	multiple choices
89990611	permanently moved
89990612	moved temporarily
89990613	see other
89990614	not modified
89990615	use proxy
89990620	bad request

## E Server Error Codes

---

89990621	unauthorized
89990622	payment required
89990623	forbidden
89990624	not found
89990625	method not allowed
89990626	not acceptable
89990627	proxy authentication required
89990628	request timeout
89990629	conflict
8999062a	gone
8999062b	length required
8999062c	precondition failed
8999062d	request entity too large
8999062e	request URI too long
8999062f	unsupported media type
89990630	internal server error
89990631	not implemented
89990632	bad gateway
89990633	service unavailable
89990634	gateway timeout
89990635	HTTP version not supported
89990700	database journal error
89990701	database journal initialization failed
89990702	database journal recovery failed
89990703	invalid entry in database journal found
89990704	failed to apply database journal transaction
89990705	failed to apply database journal operation

---

89990706	error opening database journal
89990707	error reading from database journal
89990708	error writing to database journal
89990709	database journal file error
89990800	SQL error
89990801	SQL error, more info available
89990802	invalid SQL configuration
89990900	the sender of the message does not exist
89990901	the recipient of the message does not exist
89990902	The sender must be a user. It cannot be a user group
89990903	The attachment of the message is invalid
89990904	A block size was 0 or negative
89990905	A message handle was invalid
89990906	the viewing counter of a mailbox is inconsistent with the viewing status of the messages
89990907	the outbox of a user could not be created
89990908	the inbox of a user could not be created
89990a00	Could not open an image because the file could not be found or the caller is not allowed to open the file.
89990a01	Could not read an image. The file could be opened but not be read.
89990a02	Could not create an image file. Maybe the destination folder does not exist or the caller is not allowed to write to that location.
89990a03	Could not write an image file. The file was created but writing to the file failed. This could for example happen if disk has insufficient disk space.
89990a04	The image could not be read because it does not have a known format.
89990a05	The image could not be read because the bitmap in it is invalid.
89990a06	An unknown error occurred in the image lib.
89990a07	An image could not be loaded or saved because the license for the LZW algorithm is not available.

## E Server Error Codes

---

89990a08	The image could not be read or stored because the file or image has an invalid format.
89990b00	The LDAP server detected an internal error, LDAP error: LDAP_OPERATIONS_ERROR(0x1)
89990b01	The LDAP server received an invalid request from the server, LDAP error: LDAP_PROTOCOL_ERROR(0x2)
89990b02	A specified time limit was exceeded in a request to the LDAP server, LDAP error: LDAP_TIMELIMIT_EXCEEDED(0x3)
89990b03	A specified size limit was exceeded in a request to the LDAP server, LDAP error: LDAP_SIZELIMIT_EXCEEDED(0x4)
89990b04	The LDAP server does not support the authentication method specified by the server, LDAP error: LDAP_AUTH_METHOD_NOT_SUPPORTED(0x7)
89990b05	The request sent to the LDAP server required strong authentication and therefore failed, LDAP error: LDAP_STRONG_AUTH_REQUIRED(0x8)
89990b06	A limit set by the LDAP administrator was exceeded in a request to the LDAP server, LDAP error: LDAP_ADMINLIMIT_EXCEEDED(0xB)
89990b07	The LDAP server was unable to satisfy a request because one or more critical extensions were not available, LDAP error: LDAP_UNAVAILABLE_CRITICAL_EXTENSION(0xC)
89990b08	The request sent to the LDAP server required confidentiality by the transport protocol and therefore failed, LDAP error: LDAP_CONFIDENTIALITY_REQUIRED(0xD)
89990b09	A search request sent to the LDAP server is not compatible with the attribute syntax specified by the LDAP database, LDAP error: LDAP_INAPPROPRIATE_MATCHING(0x12)
89990b0a	An LDAP object specified in a request could not be found by the LDAP server, LDAP error: LDAP_NO_SUCH_OBJECT(0x20)
89990b0b	The LDAP server detected an error when trying to dereference an alias, LDAP error: LDAP_ALIAS_PROBLEM(0x21)
89990b0c	The syntax of a DN sent to the LDAP server is incorrect, LDAP v: LDAP_INVALID_DN_SYNTAX(0x22)
89990b0d	The LDAP server cannot perform the operation on a leaf entry, LDAP error: LDAP_IS_LEAF(0x23)

---

89990b0e	A search request sent to the LDAP server could not dereference an alias because of missing access rights, LDAP error: LDAP_ALIAS_DEREF_PROBLEM(0x24)
89990b0f	An incorrect authentication method was used when sending a request to the LDAP server, LDAP v: LDAP_INAPPROPRIATE_AUTH(0x30)
89990b10	The credentials sent to the LDAP server are invalid, LDAP error: LDAP_INVALID_CREDENTIALS(0x31)
89990b11	The request sent to the LDAP server was not completed because of missing access rights, LDAP error: LDAP_INSUFFICIENT_ACCESS(0x32)
89990b12	The LDAP server is too busy at the moment to fulfill the request, LDAP v: LDAP_BUSY(0x33)
89990b13	The LDAP server is currently unavailable, LDAP v: LDAP_UNAVAILABLE(0x34)
89990b14	The LDAP server cannot process the request due to server-defined restrictions, LDAP error: LDAP_UNWILLING_TO_PERFORM(0x35)
89990b15	A loop was detected in an LDAP alias or referral, LDAP error: LDAP_LOOP_DETECT(0x36)
89990b18	The LDAP server could not complete the request because it violates the naming convention, LDAP error: LDAP_NAMING_VIOLATION(0x40)
89990b19	The LDAP server could not complete the request because it violates the rules set for the object class, LDAP error: LDAP_OBJECT_CLASS_VIOLATION(0x41)
89990b1a	The LDAP server cannot perform the operation on a non-leaf entry, LDAP error: LDAP_NOT_ALLOWED_ON_NONLEAF(0x42)
89990b1b	The LDAP server cannot perform the operation because it attempts to change attributes that are necessary for the relative DN of the entry, LDAP error: LDAP_NOT_ALLOWED_ON_RDN(0x43)
89990b1c	The LDAP server cannot perform the operation because the entry already exists, LDAP error: LDAP_ALREADY_EXISTS(0x44)
89990b1d	The LDAP server cannot perform the operation because it would change the structure rules of the object class, LDAP error: LDAP_NO_OBJECT_CLASS_MODS(0x45)
89990b1e	The results of a request to the LDAP server are too large to return them, LDAP error: LDAP_RESULTS_TOO_LARGE(0x46)

## E Server Error Codes

---

89990b1f	The LDAP operation needs to be performed by multiple LDAP servers, where this operation is not permitted, LDAP error: LDAP_AFFECTS_MULTIPLE_DSAS(0x47)
89990b20	The LDAP server cannot perform the operation because of a virtual list view error, LDAP error: LDAP_VIRTUAL_LIST_VIEW_ERROR(0x4C)
89990b21	The LDAP server encountered an unknown error, LDAP error: LDAP_OTHER(0x50)
89990b22	The LDAP server could not be contacted, LDAP error: LDAP_SERVER_DOWN(0x51)
89990b23	The LDAP client detected an error, LDAP error: LDAP_LOCAL_ERROR(0x52)
89990b24	The LDAP protocol detected an encoding error, LDAP error: LDAP_ENCODING_ERROR(0x53)
89990b25	The LDAP protocol detected a decoding error, LDAP error: LDAP_DECODING_ERROR(0x54)
89990b26	An LDAP search was aborted because of a timeout, LDAP error: LDAP_TIMEOUT(0x55)
89990b27	The LDAP server encountered an unknown authentication error, LDAP error: LDAP_AUTH_UNKNOWN(0x56)
89990b28	An LDAP search filter has an invalid format, LDAP error: LDAP_FILTER_ERROR(0x57)
89990b29	An LDAP operation was cancelled by the user, LDAP error: LDAP_USER_CANCELLED(0x58)
89990b2a	An LDAP operation failed because an invalid parameter was specified, LDAP error: LDAP_PARAM_ERROR(0x59)
89990b2b	An LDAP operation failed because the system is out of memory, LDAP error: LDAP_NO_MEMORY(0x5a)
89990b2c	The LDAP connection could not be created, LDAP error: LDAP_CONNECT_ERROR(0x5b)
89990b2d	An LDAP operation failed because it is not supported by the LDAP server, LDAP error: LDAP_NOT_SUPPORTED(0x5c)
89990b2e	The LDAP server refused to return results, LDAP error: LDAP_NO_RESULTS_RETURNED(0x5e)
89990b2f	An LDAP operation failed because a required control was not found, LDAP error: LDAP_CONTROL_NOT_FOUND(0x5d)

---

89990b31	A loop was detected in an LDAP alias or referral, LDAP error: LDAP_CLIENT_LOOP(0x60)
89990b32	An LDAP operation failed because a referral required too many referral hops, LDAP error: LDAP_REFERRAL_LIMIT_EXCEEDED(0x61)
89990b50	The operation failed because the user authentication provider is not enabled
89990b51	The authentication failed because empty passwords are not allowed
89990b52	The CCS was unable to retrieve the users from a user authentication provider
89990b53	The specified user authentication provider was not found
89990b54	The required setting for the LDAP server is not set
89990b55	The required setting for the LDAP user object class is not set
89990b56	The required setting for the LDAP user name attribute is not set
89990b57	The specified search root DN was not found
89990b70	The Unity API could not be found

---





# F Consistency Check Codes

The following tables explain the codes reported when you run a Consistency Check:

- [Consistency Check Critical Errors](#)
- [Consistency Check Errors](#)
- [Consistency Check Warnings](#)



**The Consistency Check is for support purposes. You should perform this check only if requested by Avid Technical Support.**

## Consistency Check Critical Errors



**If any of the following critical errors are reported, do not use your database; contact Avid immediately using the protocol outlined in the “If You Need Help” topic in the front of this manual.**

Code	Meaning
7050	object refers to the wrong parent
7051	object is not exist in name directory
7052	object has an invalid BIH
7053	object has an invalid BDH
7088	pending change table inconsistency
7089	pending change table inconsistency
7099	object doesn't have a parent
7100	internal error in database structure
7101	internal error in database structure
7110	streamed properties structure invalid
7141	repository data corruption

## F Consistency Check Codes

Code	Meaning
7142	repository data corruption
7143	repository data corruption
7144	repository data corruption
11064	user management failed to initialize

## Consistency Check Errors



*If any of the following errors are reported, some problems were found related to the particular object. It is still possible to use your database, but you should contact Avid using the protocol outlined in the “If You Need Help” topic in the front of this manual to resolve the problem.*

Code	Meaning
7061	Not possible to determine the server master path for the file
7063	file doesn't exist
7064	internal object state is invalid
7065	internal object state is invalid
7066	internal object state is invalid
7067	internal object state is invalid
7068	internal object state is invalid
7069	internal object state is invalid
7070	object history is not accurate
7071	object history is not accurate
7077	internal object state is invalid
7078	internal object state is invalid
7081	internal object state is invalid
7082	internal object state is invalid
7083	internal object state is invalid

---

<b>Code</b>	<b>Meaning</b>
7085	internal object state is invalid
7111	unknown property handle
7112	streamed property flag is not set
7113	unknown streamed property name
7114	invalid streamed property
7153	internal object state is invalid
7171	link is invalid
7172	link is invalid
7173	link is invalid
7174	link is invalid
7175	link is invalid
7176	link is invalid
11058	master user is not valid
11059	master user is not valid
11060	master user does not exist
11061	master user is not valid
11062	master user is not valid
23020	authorization assignment is incorrect
23021	authorization assignment is incorrect
23023	authorization assignment is incorrect

---

## Consistency Check Warnings

If any of the following warnings are reported, some problems were found, but no action is urgently needed.

<b>Code</b>	<b>Meaning</b>
7062	file size mismatch
7072	invalid dependency source
7073	invalid dependency source
7074	invalid dependency target
7075	invalid dependency target
7076	incorrect dependency type
7091	pending change problem fixed
23022	invalid entry in the authorization role table. This can happen when there is an entry in the permission table that does not refer back to an object. For example, an object was deleted or the creation of a folder was cancelled.

# Index

## Symbols

- \_Backup directory
  - described [33](#)
- \_Buckets directory
  - described [33](#)
- \_Database directory
  - backing up and restoring [36, 37](#)
  - described [33](#)
- \_Master directory
  - described [33](#)
- \_PropertyStore directory
  - backing up and restoring [36, 37](#)
  - described [33](#)

## Numerics

- 7-Zip
  - for Interplay backups [46](#)

## A

- AAF metadata
  - adding to tape archive [158](#)
- Access control
  - for custom properties [138](#)
- Accumulated inherited role
  - described [113](#)
- Activating
  - database [64](#)
- Administrator role
  - described [113](#)
- Administrators group [110](#)
- Apache web server
  - activating creation of access.log [235](#)
  - folder and files [234](#)

- Application Database Settings view [173, 174](#)
  - options [176](#)
- Application key (dongle) [86](#)
- Archive
  - metadata override [170](#)
- Archive Engine
  - setting computer name [158](#)
- Archive settings
  - adding AAF metadata [158](#)
  - allow duplicate media files [156](#)
  - allow metadata archive [156](#)
  - archive segment [156](#)
  - archive server name [156](#)
  - best effort restore [158](#)
  - duplicate versions [156](#)
  - online database [158](#)
  - segment size [158](#)
  - server name [158](#)
  - use best effort [156](#)
- Archive Settings view [156](#)
- Archiving [156](#)
- Attributes
  - setting for users or groups [112](#)
- Authentication
  - described [98](#)
  - global [98](#)
  - setting for individual users [116](#)
- Authentication providers
  - for individual users [116](#)
  - global [98](#)
- Automatic backups
  - scheduling [41](#)
- Automatic reservations [181](#)
- Automatic timeout
  - setting [186](#)
- AvDeletes.log [238](#)

Avid  
  online support [15](#)  
  training services [17](#)

Avid assets  
  described [20](#)

Avid Instinct  
  Application Database options [176](#)  
  setting Application Database options [173](#), [174](#)  
  setting user options [188](#)  
  user options [190](#)

Avid Interplay  
  client-server application [23](#)  
  optimizing performance [202](#)

Avid Interplay Administrator  
  *See* Interplay Administrator

Avid Interplay Assist  
  Application Database options [176](#)  
  setting Application Database options [173](#), [174](#)  
  setting user options [188](#)  
  user options [190](#)

Avid Interplay Engine directory  
  Apache folder [234](#)  
  Data folder [236](#)  
  folders and files [233](#)  
  Logs folder [237](#)  
  Preview Server folder [240](#)  
  Server folder [241](#)

Avid Interplay Engine Server process [242](#)  
  locking or shutting down [208](#)

Avid Media Composer  
  setting Application Database option [173](#), [174](#)

Avid Service Framework  
  Services views [199](#)

Avid Unity  
  authentication [100](#)  
  file repository on workspace [210](#)

Avid Unity ISIS  
  workspace for file repository [212](#)

Avid Unity MediaManager  
  migrating users from [110](#)

Avid Unity MediaNetwork  
  workspace for file repository [212](#)

Avid Workgroup Engine Monitor service [250](#)

Avid Workgroup HTTP Server process [243](#)

Avid Workgroup Preview Server service [244](#)

Avid Workgroup Server Browser service [244](#)

Avid Workgroup TCP/COM Bridge service [248](#)

Avid Workgroup VSS service [249](#)

AvidAM.pro file  
  described [33](#)

AvidWG.pro file  
  described [33](#)

AvMetaDataDelete.log [239](#)

AvMoveEx.log [240](#)

## B

BackupArchive tool [57](#)

BackupFailed event [257](#)

Backups  
  described [36](#), [37](#)  
  manual, starting [45](#), [45](#)  
  number of backups to keep [38](#)  
  performing [41](#)  
  recommendations for configuring [38](#)  
  restoring [48](#)  
  scheduling [41](#)  
  scheduling automatic backups [41](#)  
  using archiving tool [46](#)

Best effort restore  
  setting [158](#)

## C

Categories  
  adding [146](#)  
  configuring [146](#)  
  removing [148](#)

Central Configuration Server (CCS)  
  adding users [98](#)  
  caution when moving [93](#)  
  described [23](#)  
  moving to another server [94](#)  
  overview [93](#)  
  selecting a different server [96](#)

Client access  
  configuration [262](#)

Client connections  
  troubleshooting [202](#)

Clients  
  disconnecting all [85](#)  
  list of connected [82](#)

ClusterResourceFailure event [257](#)

Complete backup  
 described [36, 37](#)  
 Config.xml [253](#)  
 supported actions [255](#)  
 supported events [257](#)  
 Configuration files  
 Interplay Engine [253](#)  
 Configuring  
 automatic backup [38](#)  
 categories [146](#)  
 client access [262](#)  
 Interplay Engine files [253](#)  
 Pro Tools Export plug-in [197](#)  
 Pro Tools Import plug-in [195](#)  
 project token attributes [262](#)  
 remote workgroups [144](#)  
 Consistency Check  
 critical errors [297](#)  
 error codes [297](#)  
 errors [298](#)  
 performing [60](#)  
 warnings [300](#)  
 Create Database view [31](#)  
 Custom Meta Data tab  
 using [135](#)  
 Custom properties  
 adding [135](#)  
 creating [134](#)  
 custom lists for [140](#)  
 extended search [143](#)  
 removing a list [142](#)  
 setting access control [138](#)  
 XML files for [140](#)

## D

Data folder [236](#)  
 Database  
 activating [64](#)  
 backing up [36](#)  
 blocking access to [124](#)  
 changing root folders [81](#)  
 creating [31](#)  
 deactivating [63](#)  
 described [19](#)  
 directories and files [33](#)  
 limits [36](#)

locking [62](#)  
 migrating [67](#)  
 moving (clustered) [73](#)  
 moving (non-clustered) [69](#)  
 moving database and users (clustered) [76](#)  
 moving database and users (non-clustered) [71](#)  
 moving when disk space low [78](#)  
 renaming [79](#)  
 restoring [36](#)  
 restoring example [56](#)  
 splitting [210](#)  
 supported storage configurations [211](#)  
 unlocking [62](#)  
 viewing information about [60](#)  
 Database asset  
 deletion [161](#)  
 Database Information View [60](#)  
 DCOMConfig Settings [242](#)  
 Deactivating  
 database [63](#)  
 Deleting  
 options for deleting locked media [169](#)  
 options for deleting OMF or MXF [169](#)  
 overview [161](#)  
 scheduling [166](#)  
 users and user groups [117](#)  
 Dictionaries  
 for custom properties [140](#)  
 Differential backup  
 described [37](#)  
 DiskLimit event [257](#)  
 Dongle [86](#)  
 DRM (restrictions) [272](#)  
 Duration attribute [272](#)  
 Dynamic relink  
 Editor Database option [176](#)

## E

E-mail notifications  
 errors and severity level [261](#)  
 Engine Monitor Service [250](#)  
 Error codes  
 Consistency Check [297](#)  
 server [281](#)  
 Event Manager settings [253](#)  
 Everyone group [110](#)

## Exiting

- Interplay Administrator 29

## Exporting

- license 90

## Extended search

- custom properties 143

**F**

Failed to Delete folder 161

## Fast backup

- described 37

## File assets

- described 20
- source files for 210

## File repository

- described 210

Filetransfer server 265

## Firewalls

- troubleshooting 203

## Folderlocations.xml

- described 33

## Folders

- assigning roles to 118
- blocking access to 124
- setting ownership 159

## Frame Locators tab

- configuring display 187

## Full backup

- described 36, 37

**G**

## General role assignments

- setting 121
- viewing 118

Global authentication 98

**H**

## Handover directories

- described 33

Hardware ID 86

## Help

- opening 28

**I**

Imported Users group 110

## Importing

- LDAP users 103
- license 88
- users 98
- Windows domain users 101

## Incremental backup

- described 37

Inherited rights 113

IN-OUT attribute 273

## Installing

- Pro Tools Import plug-in 195

Instinct/Assist User Settings view 188

- options 190

## Interplay Access

- default folders in 31
- defining property layouts for 129
- enabling login from Windows domain 101

## Interplay Administrator

- described 23
- exiting 29
- Help 28
- opening a view 28
- starting 24

## Interplay Administrator views

- opening 28

## Interplay Administrator window

- using 26

## Interplay Archive Engine

- described 22

## Interplay database

- described 19
- See also* Database

## Interplay Engine

- Avid Interplay Engine Server process 242
- Avid Workgroup Engine Monitor service 250
- Avid Workgroup HTTP Server process 243
- Avid Workgroup Preview Server service 244
- Avid Workgroup Server Browser service 244
- Avid Workgroup TCP/COM Bridge service 248
- Avid Workgroup VSS service 249
- configuration files 253
- described 19
- folders and files 233
- optimizing performance 202



- ports used [241](#)
- servers and services [241](#)
- Interplay Media Services Engine
  - registering [149](#)
- Interplay Media Services view [153](#)
- Interplay Portal
  - viewing [15](#)
- Interplay Transfer
  - configuring for remote workgroups [144](#)
- Interplay Transfer Settings view [154](#)
- Interplay Transfer Status view [154](#)
- Interplay Window
  - automatic reservation [181](#)
- Interplay workgroup
  - described [19](#)
  - multiple workgroups [21](#)
- InterplayRestore tool
  - described [48](#)
  - example [56](#)

## J

- Journal files
  - described [33](#)

## K

- Kept Media folder [161](#)

## L

- LDAP authentication [103](#)
- LDAP server settings [105](#)
- LicenseKeyInfo.exe [91](#)
- Licenses
  - displaying and printing [91](#)
  - exporting [90](#)
  - importing [88](#)
  - managing [86](#)
  - permanent [88](#)
  - troubleshooting [90](#)
  - types [89](#)
- Licenses view [86](#)
- Lock Server view [84](#)
- Lock/Unlock Database view [62](#)
- Locked clips
  - deleting [169](#)

- Locking
  - database [62](#)
  - server process [208](#)
- Log files
  - deletion [161](#)
- LogEvent event [257](#)
- Logging in
  - troubleshooting [201](#)
- Logging out
  - Interplay Administrator [29](#)
- Logs folder [237](#)
- Logwatch.xml [260](#)

## M

- Manage Database Roles view [118](#)
- Managing Databases view [63](#)
- Manual backup
  - starting [45, 45](#)
- Media Composer
  - setting Application Database option [173, 174](#)
- Media Indexer
  - registering in Interplay Administrator [149](#)
- MediaManager
  - migrating users from [110](#)
- Metadata
  - system, list [269](#)
- Metadata override
  - for archive [170](#)
- Migrated Users group [110](#)
- Migrating
  - database [67](#)
- Moving
  - database (clustered) [73](#)
  - database (non-clustered) [69](#)
  - database and users (clustered) [76](#)
  - database and users (non-clustered) [71](#)
  - database when disk space low [78](#)
- MXF files
  - option for deleting [169](#)

## N

- No Access role
  - described [113](#)
- NxNServerLock.exe
  - locking server process [208](#)

- moving database with [78](#)
- NxNServerShutdown.exe
  - moving database with [78](#)
  - shutting down server process [208](#)
- NxNServerUnlock.exe
  - moving database with [78](#)
- NXNServerUser.exe
  - recreating Server Execution User [207](#)

## O

- Object Inspector
  - configuring Frame Locators [187](#)
- OMF files
  - option for deleting [169](#)
- Online support [15](#)
- Orphan Clips folder
  - changes for v2.4 [161](#)
  - types of links [166](#)
- Ownership Behavior view [159](#)

## P

- Passwords
  - viewing and setting [112](#)
- Perform Consistency Check view [60](#)
- Performance
  - optimizing Interplay [202](#)
- Permanent license [88](#)
- Permissions
  - setting [113](#)
  - See also* Roles
- Presets
  - workgroup transfer [154](#)
- Preview Server folder [240](#)
- pro file
  - described [33](#)
- Pro Tools
  - configuring Export plug-in [197](#)
  - configuring Import plug-in [195](#)
  - installing plug-ins [195](#)
  - plug-ins for Interplay [195](#)
  - User Settings plug-in [198](#)
- Property Layout view [129](#)

## R

- Read role
  - described [113](#)
- Read/Write role
  - described [113](#)
- Read/Write/Delete role
  - described [113](#)
- Remote workgroups
  - configuring for search or transfer [144](#)
- Renaming
  - database [79](#)
- Reservations
  - automatic [181](#)
- Resolutions
  - setting available in clients [132](#)
- Restart Server view [85](#)
- Restarting
  - server [85](#)
- Restoring
  - backup version [48](#)
- Restrictions
  - DRM property [272](#)
- Reuniting
  - split database [221](#)
- Rights
  - setting [113](#)
  - See also* Roles
- Robocopy
  - for Interplay backups [46](#)
- Role assignments
  - general [118](#)
- Roles
  - assigning to folders [118](#)
  - described [113](#)
  - viewing and changing [114](#)
- Root folders
  - setting [81](#)

## S

- Schedule Backups view [41](#)
- Scheduled deletion [166](#)
- Searches
  - custom properties [143](#)
- Searching
  - remote workgroups [144](#)

Send mail action [255](#)  
 Server  
     error codes [281](#)  
     information about [82](#)  
     locking [84](#)  
     restarting [85](#)  
     shutting down [84](#)  
     unlocking [84](#)  
 Server Event configuration  
     example [259](#)  
 Server Event Manager  
     configuring [253](#)  
 Server Execution User  
     described [23](#)  
     recreating [207](#)  
     troubleshooting [204](#)  
 Server folder [241](#)  
 Server Hostname Settings view [149](#)  
 Server Information view [82](#)  
 Server Settings view [81](#)  
 ServerXML.xml [262](#)  
 Service Configuration view (Avid Service Framework) [199](#)  
 Shotlist  
     changing default start timecode [185](#)  
 Shutting down  
     server process [208](#)  
 Split database  
     configuring workgroup.xml file [219](#)  
     described [210](#)  
     existing Interplay installations [215](#)  
     new Interplay installations [213](#)  
     preparing for [212](#)  
     reuniting [221](#)  
     reuniting AvidWG and \_InternalData [227](#)  
     reuniting AvidWG only [224](#)  
 Start timecode  
     changing default for shotlist [185](#)  
 Streamed properties  
     described [33](#)  
 System metadata  
     list [269](#)

## T

Taxonomies  
     for custom properties [140](#)

TCP/COM Bridge service [248](#)  
 TCP/IP  
     ports required [241](#)  
 Timecode  
     changing default start for shotlist [185](#)  
 Timeout  
     setting automatic [186](#)  
 Tracks attribute [278](#)  
 Training services [17](#)  
 Transferring  
     to remote workgroup [144](#)  
 Transfers  
     configuring transfer engines [154](#)  
     monitoring status [154](#)  
     preset view [154](#)  
 Troubleshooting [15](#)  
     client connection problems [202](#)  
     firewalls [203](#)  
     licenses [90](#)  
     login-in problems [201](#)  
     optimizing Interplay performance [202](#)  
     server process [208](#)

## U

Unlocking  
     database [62](#)  
 User Authentication Providers view [98](#)  
 User groups  
     adding [111](#)  
     default [110](#)  
     deleting [117](#)  
     removing users from [117](#)  
     roles [113](#)  
     setting attributes for [112](#)  
     setting passwords for [112](#)  
 User management  
     guidelines [127](#)  
 User Management view [108](#)  
 Users  
     adding from Avid Unity [100](#)  
     adding manually [111](#)  
     adding to a CCS [98](#)  
     default [110](#)  
     deleting [117](#)  
     disconnecting all [85](#)  
     importing [98](#)

- importing from LDAP [103](#)
- importing from Windows domain [101](#)
- list of connected [82](#)
- management guidelines [127](#)
- managing [108](#)
- removing from group [117](#)
- roles [113](#)
- setting attributes for [112](#)
- setting passwords for [112](#)

## V

- VITC (Vertical Interval Timecode)
  - in a bin [279](#)
- VSS service [249](#)

## W

- WG\_Database\$
  - identifying root folder for [220](#)
- Windows Domain authentication [101](#)
- Workgroup name
  - setting [149](#)
- Workgroup Properties view (Avid Service Framework) [199](#)
- Workgroup Transfer Presets view [154](#)
- workgroup.xml file
  - configuring for file transfer server [265](#)
  - configuring for split database [219](#)
- Workgroups
  - described [19](#)
  - multiple workgroups [21](#)
  - remote [144](#)

## X

- XML files
  - for custom properties [140](#)



**Avid**  
75 Network Drive  
Burlington, MA 01803-2756 USA

**Technical Support (USA)**  
Visit the Online Support Center at  
[www.avid.com/support](http://www.avid.com/support)

**Product Information**  
For company and product information,  
visit us on the web at [www.avid.com](http://www.avid.com)