

One Identity Manager 8.1.2

Attestation Administration Guide

Copyright 2020 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC.

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC. Attn: LEGAL Dept 4 Polaris Way Aliso Viejo, CA 92656

Refer to our Web site (http://www.OneIdentity.com) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at http://www.OneIdentity.com/legal/patents.aspx.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

WARNING: A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.

CAUTION: A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

One Identity Manager Attestation Administration Guide Updated - January 2020 Version - 8.1.2

Contents

Attestation and recertification	8
One Identity Manager users for attestation	8
Attestation base data	
Attestation types	10
Default attestation types	11
Additional tasks for attestation types	11
Attestation procedure	12
General master data for an attestation procedure	
Defining reports for attestation	
Default attestation procedures	15
Additional tasks for attestation procedures	
Schedules	17
Default schedules	19
Additional tasks for schedules	20
Compliance frameworks	21
Additional tasks for compliance frameworks	22
Chief approval team	
Standard reasons for attestation	
Predefined standard reasons	24
Attestation policies	25
General master data for attestation policies	25
Risk assessment	27
Default attestation policies	
Additional tasks for attestation policies	29
The attestation policy overview	29
Assigning approvers	29
Assigning compliance frameworks	29
Mitigating controls	
Running attestation for single objects	
Showing or hiding conditions	
Creating a copy	



Showing selected objects	33
Deleting attestation policies	
Disabling attestation policies	
Custom mail templates for notifications	34
Creating and editing attestation mail templates	34
General properties of a mail template	
Creating and editing a mail definition	
Using base object properties	
Use of hyperlinks in the Web Portal	37
Customizing email signatures	
Copying mail templates for attestation	
Displaying attestation mail templates previews	40
Deleting mail templates for attestation	40
Custom notification processes	40
Approval processes for attestation cases	42
Approval policies for attestations	
General master data for approval policies	43
Default approval policies	
Additional tasks for approval policies	
Editing approval workflows	44
Validity checking	44
Approval workflow for attestations	45
Working with the workflow editor	45
Setting up approval workflows	48
Editing approval levels	
Editing approval steps	50
Properties of an approval step	50
Connecting approval levels	54
Additional tasks for approval workflows	55
The approval workflow overview	55
Copying approval workflows	55
Deleting approval workflows	
Default approval workflows	56
Selecting attestors	56
Default approval procedures	



Using attestation policies to find attestors	
Using roles of employees to be attested to find attestors	62
Using attestation objects to find attestors	62
Using attestation object managers to find attestors	64
Using persons responsible for attestation objects to find attestors	65
Using a specified role to find attestors	67
Using product owners to find attestors	67
Using owners of a privileged object to find attestors	68
Using additional Active Directory group owners to find attestors	
Using owners of the attestation objects to find attestors	68
Calculated approval	69
Approvals to be made externally	
Waiting for further approval	
Setting up approval procedures	72
General master data for an approval procedure	73
Queries for finding attestors	73
Additional tasks for approval procedures	76
Overview of the approval procedure	76
Specifying permitted approval procedures for tables	
Copying an approval procedure	77
Deleting approval procedures	77
Determining the responsible attestors	78
Setting up multi-factor authentication for attestation	80
Prevent attestation by employee awaiting attestation	81
Managing attestation cases	81
Getting more information	82
Appointing other attestors	82
Escalating an attestation case	83
Attestors cannot be established	85
Automatic approval on timeout	
Aborting an attestation case on timeout	
Attestation through chief approval team	
Attestation sequence	
Starting attestation	91
Additional tasks for attestation cases	92



Attestation case overview	93
Approval sequence	93
Attestation history	94
Modifying approval workflows for pending attestation cases	95
Closing attestation cases for deactivated employees	96
Deleting attestation cases	97
Notifications in the attestation process	98
Demanding attestation	
Reminding attestors	100
Scheduling attestation demands	101
Reminding attestors about attestation objects	101
Granting or denying attestation cases	
Notifying delegates	
Aborting attestation cases	104
Escalation of attestation cases	
Delegating attestations	105
Rejecting approvals	105
Notifications with questions	
Notifications from additional attestors	106
Link for verifying new external users	107
Default mail templates	107
Attestation by mail	
Processing attestation mails	110
Default attestation and withdrawal of entitlements	
System entitlements attestation	
System role attestation	
Application role attestation	
Business role attestation	
User attestation and recertification	
One Identity Manager users for attesting and recertifying users	
Configuring user attestation and recertification	
Attesting new users	
Self-registration of new users in the Web Portal	
Adding new employees using a manager or employee administrator	



Importing new employee master data	
Scheduled attestation	129
Limiting attestation objects for certification	
Recertifying existing users	131
Preparing for recertification	
The recertification sequence	133
Limiting attestation objects for recertification	
Mitigating controls	
General master data for mitigating controls	
Additional tasks for mitigating controls	137
Mitigating controls overview	137
Assigning attestation policies	137
Calculating mitigation	
Appendix: Configuration parameters for attestation	
About us	
Contacting us	
Technical support resources	149
Index	



Attestation and recertification

Managers or others responsible for compliance can use the One Identity Manager attestation functionality to certify correctness of access permissions, authorizations, requests, or exception approvals either scheduled or on demand. Recertification is the term generally used to describe regular certification of permissions. One Identity Manager uses the same workflows for recertification and attestation.

There are attestation policies defined in One Identity Manager for carrying out attestations. Attestation policies specify which objects are attested when, how often, and by whom. Once an attestation is performed, One Identity Manager creates attestation cases that contain all the necessary information about the attestation objects and the attestor responsible. The attestor checks the attestation objects. They verify the correctness of the data and initiate any changes that need to be made if the data conflicts with internal rules.

Attestation cases record the entire attestation sequence. Each attestation step in the attestation case can be audit-proof reconstructed. Attestations are run regularly using scheduled tasks. You can also trigger single attestations manually.

Attestation is complete when the attestation case has been granted or denied approval. You specify how to deal with granted or denied attestations on a company basis.

TIP: One Identity Manager provides various default attestation procedures for different data situations and default attestation procedures. If you use these default attestation procedures, you can configure how you deal with denied attestations.

For more information, see Default attestation and withdrawal of entitlements on page 112.

To use attestation functionality

• In the Designer, set the **QER | Attestation** configuration parameter.

One Identity Manager users for attestation

The following users are used for attestation.



Table 1: Users

User	Tasks	
Administrators for attestation	Administrators are assigned to the Identity & Access Governance Attestation Administrators application role.	
cases	Users with this application role:	
	 Define attestation procedures and attestation policies. 	
	 Create approval policies and approval workflows. 	
	 Specify which approval procedure to use to find attestors. 	
	 Set up attestation case notifications. 	
	Configure attestation schedules.	
	Enter mitigating controls.	
	Create and edit risk index functions.	
	Monitor attestation cases.	
One Identity Manager administrators	 Create customized permissions groups for application roles for role-based login to administration tools in the Designer as required. 	
	 Create system users and permissions groups for non role-based login to administration tools in the Designer as required. 	
	 Enable or disable additional configuration parameters in the Designer as required. 	
	 Create custom processes in the Designer as required. 	
	 Create and configure schedules as required. 	
	 Create and configure password policies as required. 	
Attestors	Check attestation objects in the Web Portal.	
	Confirm data correctness.	
	 Initiate changes if data conflicts with internal rules. 	
	Attestators in charge are determined through approval procedures.	
Compliance and security officer	Compliance and security officers must be assigned to the Identity & Access Governance Compliance & Security Officer application role.	
	Users with this application role:	
	 View all compliance relevant information and other analysis in the Web Portal. This includes attestation policies, company policies and policy violations, compliance rules, and rule violations and risk index functions. Edit attestation polices. 	



User	Tasks
Auditors	Auditors are assigned to the Identity & Access Governance Auditors application role.
	Users with this application role:
	 See the Web Portal all the relevant data for an audit.
Chief approval team	The chief approver must be assigned to the Identity & Access Governance Attestation Chief approval team application role.
	Users with this application role:
	Approve using attestation cases.
	 Assign attestation cases to other attestors.

Attestation base data

The attestation framework and the objects to be attested are specified in the attestation policy. You require certain base data to define attestation policies.

Attestation types:	Attestation types on page 10
Approval policies:	Approval policies for attestations on page 42
Approval workflows:	Approval workflow for attestations on page 45
Approval procedures:	Setting up approval procedures on page 72
Attestation procedures:	Attestation procedure on page 12
Schedules:	Schedules on page 17
Compliance frameworks:	Compliance frameworks on page 21
Mail templates:	Custom mail templates for notifications on page 34
Chief approval team:	Chief approval team on page 23
Standard reasons:	Standard reasons for attestation on page 23

Attestation types

Attestation types are used to group attestation procedures. These make it easier to assign a matching attestation procedure to the attestation policies.



To edit attestation types

- 1. Select Attestation | Basic configuration data | Attestation types.
- Select an attestation type in the result list and run Change master data.
 OR
 - Click 榋 in the result list.
- 3. Edit the attestation type master data.
- 4. Save the changes.

Default attestation types

You cannot edit default attestation types and their attestation procedure assignments.

One Identity Manager supplies attestation types by default. These attestation types are assigned to default attestation procedures. They are necessary for setting up attestation policies in the Web Portal.

To display default attestation types

• In the Manager, select the Attestation | Basic configuration data | Attestation types | Predefined category.

For detailed information about using default attestation types, see the *One Identity Manager Web Portal User Guide*.

Additional tasks for attestation types

After you have entered the master data, you can run the following tasks.

Overview of the attestation type

You can see the most important information about an attestation type on the overview form.

To obtain an overview of an attestation type

- 1. In the Manager, select the **Attestation | Basic configuration data | Attestation types** category.
- 2. Select the attestation type in the result list.
- 3. Select the **Attestation type overview** task.



Assigning attestation procedures

Use this task to assign the selected attestation type to all the attestation procedures that should be included in the group.

To assign attestation procedures to attestation types

- 1. In the Manager, select the **Attestation | Basic configuration data | Attestation types** category.
- 2. Select the attestation type in the result list.
- 3. Select the **Assign attestation procedure** task.

Assign the attestation procedures in **Add assignments**.

TIP: you can remove the assignment of attestation procedures in **Remove assignments**.

To remove an assignment

- Select the attestation procedure and double-click *S*.
- 4. Save the changes.

Attestation procedure

Attestation procedures specify the attestation base object. They define which attestation object properties are to be attested. Attestation object data can be provided in list or report form.

To edit an attestation procedure

- 1. In the Manager, select the **Attestation | Basic configuration data | Attestation procedures** category.
- 2. Select an attestation procedure in the result list and run **Change master data**.

- OR -

Click 🖥 in the result list.

- 3. Edit the attestation procedure master data.
- 4. Save the changes.

General master data for an attestation procedure

Enter the following properties for an attestation procedure.



Property	Description
Attestation procedure	Any name for the attestation procedure.
Attestation type	Criteria for grouping attestation procedures. Attestation types make it easier to assign a matching attestation procedure to the attestation policies.
Description	Spare field for additional explanation.
Report	Report for the attestor containing all the necessary information about the attestation objects.
	Predefined reports are supplied in a menu. If you do not want to assign a report, you can specify additional information about the attestation objects in the Property 1-4 (template) fields.
Table	Database table in which the attestation objects are to be found (= attest- ation base object). All tables, which fulfill the following conditions, are available:
	a. The table contains a X0bjectKey column.
	b. The table type is Table , View , ReadOnly , or Proxy .
	 c. The usage type is User data, Materialized data, or Read only data.
	 It is not the basetree table. It is not an assignment table referencing basetree.
	e. Table belongs to the application data model.
	f. Table is not disabled.
	For detailed information about table types and usage types, see the One Identity Manager Configuration Guide.
Preprocessor condition	Specifies the preprocessor configuration parameters on which the attest- ation procedure depends. Attestation procedures that are disabled through a preprocessor condition are not displayed in One Identity Manager.
Grouping column 1-3	A value template for formatting the value used to group and filter pending attestation cases in the Web Portal.
(template)	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Grouping column 1-3	Column headers for Grouping column 1-3 (template) . The columns are multi-language. To enter a translation, click ^C .
Property 1-4 (template)	Templates for formulating a value that supplies additional information about the attestation object. Use these fields to show additional inform-

Table 2: General master data for an attestation procedure



Property	Description
	ation about the attestation object in the Web Portal.
	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Property 1-4	Column headers for Property 1-4 (template) . The columns are multi- language. To enter a translation, click [©] .
Risk index template	Template for formulating the value for the attestation case's risk index.
	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
Related object 1-3 (template)	Template for formulating an object key for an object related to the attest- ation base object.
	Enter a value template in \$ notation. This template can access the base object properties and the properties of all objects connected through foreign keys.
	Define the display value for this object in Grouping column 1-3 (template).

Example

You want to attest Active Directory group memberships. Group the attestation cases by user account display value, Active Directory group display value, and the display value of associated employees. The Active Directory group's canonical name should be displayed with every group membership in the Web Portal. The attestation case's risk index can be determined from the group membership's risk index. The object key for the object relation can be found from the Active Directory user account. The information required about the attestation objects will be summarized in a report. To do this, enter the following data on the master data form.

Property	Value
Table	Database table ADSAccountInADSGroupTotal
Report	<report name=""></report>
Grouping column 1	\$UID_ADSAccount[d]\$
Grouping column 2	\$UID_ADSGroup[d]\$
Grouping column 3	\$FK(UID_ADSAccount).UID_Person[d]\$
Property 1 (template)	\$FK(UID_ADSGroup).CanonicalName\$
Risk index template	\$RiskIndexCalculated\$
Object relation 1	<pre>\$FK(UID_ADSAccount).XObjectKey\$</pre>

Table 3: Example of an attestation case definition



Detailed information about this topic

- Attestation types on page 10
- Defining reports for attestation on page 15

Defining reports for attestation

Define attestation reports with the Report Editor. Note the following when you define a report for attestation:

- The base table for the report must be identical to the one for the attestation procedure.
- Enter **Attestation** as the report category. This ensures that the report is displayed in the **Report** menu of the attestation procedure.
- In order to create a report for each attestation object with the information relating exactly to the attestation object, define a ObjectKeyBase parameter for the attestation object in the report. Use the parameters in the data source definition for the report in **Condition** text box.

Example: XObjectKey = @ObjectKeyBase

Default reports

One Identity Manager supplies some default reports for attestation. These are used in the default attestation procedures, amongst others. Default report are given the prefix **VI_**.

TIP: Default reports cannot be changed. If you want to customize a default report, create a copy and edit it according to your requirements. Then assign the copy to the attestation procedure.

Default attestation procedures

One Identity Manager provides a default approval procedure for default attestation of new users and recertification of all employees stored in the One Identity Manager database. Moreover, default approval procedures are supplied through which the different roles, user accounts, and system entitlements mapped in the Unified Namespace can be attested. Using these default approval policies you can create attestation procedures easily in the Web Portal.

To display default attestation procedures

• In the Manager, select the Attestation | Basic configuration data | Attestation procedures | Predefined category.

For detailed information about using default attestation procedures, see the One Identity Manager Web Portal User Guide.



15

Related topics

- User attestation and recertification on page 121
- Default attestation and withdrawal of entitlements on page 112

Additional tasks for attestation procedures

After you have entered the master data, you can run the following tasks.

Overview of the attestation procedure

You can see the most important information about an attestation procedure on the overview form.

To obtain an overview of an attestation procedure

- 1. In the Manager, select the **Attestation | Basic configuration data | Attestation procedures** category.
- 2. Select the attestation procedure in the result list.
- 3. Select the **Attestation procedure overview** task.

Assigning approval policies

Use this task to assign the selected attestation procedure to the approval policies that should be used in this attestation procedure. All approval policies permitted for the attestation base object are listed.

To assign approval policies to attestation procedures

- 1. In the Manager, select the **Attestation | Basic configuration data | Attestation procedures** category.
- 2. Select the attestation procedure in the result list.
- 3. Select Assign approval policies task.

Assign the approval policies in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of approval policies.

To remove an assignment

- Select the approval policy and double-click \oslash .
- 4. Save the changes.

Which approval policies are permitted depends on the approval procedures in use. Approval procedures dictate to which tables an approval procedure can be assigned.



Related topics

• Specifying permitted approval procedures for tables on page 76

Creating a copy

You can make copies of attestation procedures and those copies allow you to modify default attestation procedures.

To copy an attestation procedure

- 1. In the Manager, select the **Attestation | Basic configuration data | Attestation procedures** category.
- 2. Select the attestation procedure in the result list.
- 3. Select Create copy task.
- 4. Confirm the security prompt with **Yes**.
- 5. Decide whether the condition types should be copied for the attestation wizard in the Web Portal as well.

Condition types are required if attestation policies are created and edited with the attestation wizard in the Web Portal. For detailed information, see *One Identity Manager Web Portal User Guide*.

6. Edit the attestation procedure copy and save the changes.

The attestation procedure copy is displayed on the master data form with the name **<Name of original attestation procedure>(copy)**. You can rename and edit this attestation policy.

Schedules

Use schedules to automate attestation. These specify when and how often attestation cases are created. One Identity Manager supplies several default schedules for attestation.

To edit schedules

1. In the Manager, select the **Attestation | Basic configuration data |** Schedules category.

The result list shows all schedules configured for attestation policies (AttestationPolicy task).

2. Select a schedule in the result list and run the **Change master data** task.

- OR -

Click 🖬 in the result list.

- 3. Edit the schedule's master data.
- 4. Save the changes.



Enter the following properties for a schedule.

Table 4: Schedule properties

Property	Meaning
Name	Schedule ID. Translate the given text using the 🄄 button.
Description	Detailed description of the schedule. Translate the given text using the $$ button.
Table	Table whose data can be used by the schedule. Schedules for the attestation must refer to the AttestationPolicy table.
Enabled	Specifies whether the schedule is enabled or not.
	NOTE: Only active schedules are run.
Time zones	Choose between Universal Time Code or one of the time zones in the menu.
	NOTE:
	When you add a new schedule, the time zone is preset to that of the client from which you started the Manager.
Start (date)	The day on which the schedule should be run for the first time. If this day conflicts with the defined interval type, the first run is on the next available day based on the start date.
Validity	Period within which the schedule is run.
period	 If the schedule will be run for an unlimited period, select the Unlimited duration option.
	 To set a validity period, select the Limited duration option and enter the day the schedule will be run for the last time in End (date).
Occurs	Interval in which the task is run. Permitted interval types are Every minute, Hourly, Daily, Weekly, Monthly, and Yearly.
	For the Weekly interval type, specify the precise weekday. For the Monthly interval type, specify the day of the month (1st to 31st day of the month). For the Yearly interval type, specify the day of the year (1st to 366th day of the year).
	NOTE: If the schedule is not going to be run until next month because the interval type is Monthly with sub-interval 29 , 30 , or 31 , the last day of the current month is used.
	Example:
	A schedule that is run on the 31st day of each month is run on 30th April. In February, the schedule is run on the 28th (or 29th in leap year).
	Schedules with the interval type Yearly with sub interval 366 are only run in leap year.

Property	Meaning
Start time	Fixed start type for the Daily , Weekly , Monthly , and Yearly interval types. Enter the time in local format for the chosen time zone.
	For the interval types Every minute and Hourly , the start time is calcu- lated from the rate of occurrence and the interval type.
Repeat every	Rate of occurrence for running the schedule within the selected time interval. For the Weekly interval type, select at least one weekday.
Last planned run/Next planned run	Execution time calculated by the DBQueue Processor. Execution times are recalculated whilst the schedule is running. The time of the next run is calculated from the interval type, rate of occurrence, and the start time.
	NOTE: One Identity Manager provides the start information in the time zone of the client where the program was started. Changes due to daylight saving are taken into account.

Default schedules

One Identity Manager supplies the following attestation schedules by default:

Schedule	Description
Half-Yearly	
Monthly	
Quarterly	Default schedules for any attestation.
Weekly (Monday)	
Yearly	
Deactivated	Default schedule for default attestation policies.
	The schedule is disabled by default and should not be enabled. To run attestation, assign another schedule to the attestation policies and enable that one.
Daily	Default schedules for any attestation.
	This schedule is assigned to the New user certification attestation policy by default.

Table 5: Default attestation schedules

Related topics

- Preparing for recertification on page 132
- Scheduled attestation on page 129



Additional tasks for schedules

After you have entered the master data, you can run the following tasks.

Schedule overview

You can see the most important information about a schedule on the overview form.

To obtain an overview of a schedule

- 1. In the Manager, select the **Attestation | Basic configuration data |** Schedules category.
- 2. Select the schedule in the result list.
- 3. Select the **Schedule overview** task.

Assigning attestation policies

Use this task to assign attestation policies to the selected schedule, which will runs them. If you double-click on one of the attestation policies you assign it to the current schedule.

To assign attestation policies to a schedule

- 1. In the Manager, select the **Attestation | Basic configuration data |** Schedules category.
- 2. Select the schedule in the result list.
- 3. Select the Assign attestation polices task.
- 4. In **Add assignments**, double-click the attestation policies that are to be assigned.
- 5. Save the changes.

To change an assignment

- 1. In the Manager, select the **Attestation | Basic configuration data |** Schedules category.
- 2. Select the schedule in the result list.
- 3. Select the Assign attestation polices task.
- 4. Select **Show objects already assigned to other objects** in the assignment form context menu.

This shows attestation policies that are already assigned in other schedules.

- 5. Double-click on one of these attestation policies in **Add assignments**. The attestation policy is assigned to the currently selected schedule.
- 6. Save the changes.



NOTE: Assignments cannot be removed. Attestation policies must be assigned a schedule. It is compulsory.

Starting schedules immediately

NOTE: If a schedule is started, it starts attestation for all active attestation policies assigned with the schedule.

To start a schedule immediately

- 1. In the Manager, select the **Attestation | Basic configuration data |** Schedules category.
- 2. Select the schedule in the result list.
- 3. Select the **Start immediately** task.

A message appears confirming that the schedule was started.

Compliance frameworks

Compliance frameworks are used for classifying attestation policies, compliance rules, and company policies according to regulatory requirements.

Compliance frameworks can be organized hierarchically. To do this, assign a parent framework to the compliance frameworks.

To edit compliance frameworks

- 1. In the Manager, select the **Attestation | Basic configuration data | Compliance Frameworks** category.
- 2. Select a Compliance Framework in the result list and run the **Change master data** task.

- OR -

Click **New** in the result list toolbar.

- 3. Edit the compliance framework master data.
- 4. Save the changes.

Enter the following properties for compliance frameworks.

Table 6: Compliance framework properties

Property	Description
Compliance framework	Name of the compliance framework.
Parent framework	Parent compliance framework in the framework hierarchy. Select



Property	Description
	an existing compliance framework in the menu to organize compli- ance frameworks hierarchically.
Manager/supervisor	Application role whose members are allowed to edit all attestation policies assigned to this compliance framework
Description	Spare field for additional explanation.

Additional tasks for compliance frameworks

After you have entered the master data, you can run the following tasks.

Compliance framework overview

You can see the most important information about a compliance framework on the overview form.

To obtain an overview of a compliance framework

- 1. In the Manager, select the **Attestation | Basic configuration data | Compliance Frameworks** category.
- 2. Select the compliance framework from the result list.
- 3. Select the **Compliance framework overview** task.

Assigning attestation policies

Use this task to assign attestation policies to the selected compliance framework.

To assign attestation policies to a compliance framework

- 1. In the Manager, select the **Attestation | Basic configuration data | Compliance Frameworks** category.
- 2. Select the compliance framework from the result list.
- 3. Select the Assign attestation polices task.

Assign the attestation policies in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of attestation policies.

To remove an assignment

- Select the approval policy and double-click \bigcirc .
- 4. Save the changes.



Chief approval team

Sometimes, approval decisions cannot be made for attestation cases because an attestor is not available or does not have access to One Identity Manager tools. To complete these attestations, you can define a chief approval team whose members are authorized to intervene in the approval process at any time.

There is a default application role in One Identity Manager for the chief approval team. Assign this application role to all employees who are authorized to approve, deny, abort attestations in special cases, or to authorize other attestors. For detailed information about application roles, see the *One Identity Manager Authorization and Authentication Guide*.

Table 7: Default application role for chief approval team

User	Tasks
Chief approval team	The chief approver must be assigned to the Identity & Access Governance Attestation Chief approval team application role.
	Users with this application role:
	 Approve using attestation cases.

• Assign attestation cases to other attestors.

To add members to the chief approval team

- 1. In the Manager, select the **Attestation | Basic configuration data | Chief approval team** category.
- 2. Select the **Assign employees** task.

In **Add assignments**, assign the employees who are authorized to approve all attestations.

TIP: In **Remove assignments**, you can remove the assignment of employees.

To remove an assignment

- Select the employee and double-click 𝔄.
- 3. Save the changes.

Detailed information about this topic

• Attestation through chief approval team on page 89

Standard reasons for attestation

For attestations, you can specify reasons in the Web Portal that explain the individual approval decisions. You can freely formulate this text. You also have the option to

predefine reasons. The attestors can select a suitable text from these standard reasons in the Web Portal and store it with the attestation case.

Standard reasons are displayed in the attestation history.

To edit standard reasons

- 1. Select the **Attestation | Basic configuration data | Standard reasons** category.
- 2. Select a standard reason in the result list and run the Change master data task.

- OR -

Click 榋 in the result list.

- 3. Edit the master data for a standard reason.
- 4. Save the changes.

Enter the following properties for the standard reason.

Table 8: General master data for a standard reason

Property	Description
Standard reason	Reason text as displayed in the Web Portal and in the attestation history.
Description	Spare field for additional explanation.
Automatic Approval	Specifies whether the reason text is only used for automatic approvals by One Identity Manager. This standard reason cannot be selected by manual approvals in the Web Portal.
	Do not set the option if the you want to select the standard reason in the Web Portal.
Additional text required	Specifies whether an additional reason should be entered in free text for the attestation.
Usage type	Usage type of standard reason. Assign one or more usage types to allow filtering of the standard reasons in the Web Portal.

Predefined standard reasons

One Identity Manager provides predefined standard reasons. These standard reasons are entered into the attestation case in the case of automatic approval by One Identity Manager.

To display predefined standard reasons

• In the Manager, select the Attestation | Basic configuration data | Standard reasons | Predefined category.

Attestation policies

Attestation policies specify the concrete conditions for attestation. Use the master data form to enter the attestation procedure, approval policy and the schedule. You can use a WHERE clause to limit the attestation objects.

To edit attestation polices

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select an attestation policy in the result list and run Change master data.
 - OR -

Click 🛃 in the result list.

- 3. Edit the master data for the attestation policy.
- 4. Save the changes.

General master data for attestation policies

Enter the following data for attestation policies.

Property	Description
Attestation policy	Name of the attestation policy.
Attestation procedure	Attestation procedure used for attesting. Attestation procedures are displayed in a menu grouped by attestation type.
Approval policies	Approval policy for determining the attestor for the attestation objects.
Owner	Creator of the attestation policy. The name of the user logged in to One Identity Manager is entered here by default. This can be changed.
Time required (days)	Number of days within which a decision must be made over the attest- ation. Enter 0 if you do not want to specify a particular processing period. One Identity Manager does not stipulate which actions are carried out if
	processing times out. Define your own custom actions or evaluations to deal with this situation.
Description	Spare field for additional explanation.
Risk index	Specifies the risk for the company if attestation for this attestation policy is denied. Use the slider to enter a value between ${f 0}$ and ${f 1}$.

Table 9: General master data for attestation policies



Property	Description
	• 0 : No risk.
	• 1: The denied attestation is a problem.
	This input field is only visible if the QER CalculateRiskIndex config- uration parameter is activated.
Risk index (reduced)	Show the risk index taking mitigating controls into account. The risk index for an attestation policy is reduced by the Significance reduction value for all assigned mitigating controls.
	This input field is only visible if the QER CalculateRiskIndex config- uration parameter is activated. The value is calculated by One Identity Manager and cannot be edited.
Calculation schedule	Schedule for running attestation. Attestation cases are started automat- ically at the times specified by the schedule.
Deactivated	Specifies whether the attestation policy is disabled or not.
	Attestation cases cannot be added to disabled attestation policies and, therefore, no attestation is done. Disabled attestation policies can be deleted.
	Completed attestation cases can be deleted once the attestation policy is disabled.
Close obsolete	Specifies whether pending attestation cases are aborted if new ones are added.
tasks automat- ically	If attestation is started and this option is set, new attestation cases are created according to the condition. All pending, obsolete attestation cases for newly determined attestation objects of this attestation policy are aborted. Attestation cases for attestation objects that are not recal- culated, remain intact.
Obsolete tasks limit	Specifies the maximum number of closed attestation cases for each attestation object that should remain in the database when closed attestation cases are deleted.
	• 0 : No attestation cases are deleted.
	 > 0: The given number of closed attestation cases for each attestation object to remain in the database.
Reason for decision	Reason that is given if the Close obsolete tasks automatically option is set and pending attestation cases are automatically closed.
Output format	Format in which the report is generated.
	This menu is only visible if the QER Attestation AllowAllRe- portTypes configuration parameter is set. If the configuration parameter is not set, the default PDF format is used because it is the only format that is version compatible.



Property	Description
Edit connec- tion	Starts the WHERE clause wizard. Use this wizard to create a condition to determine the attestation objects from the database table specified in the attestation procedure.
Condition	Data query for finding attestation objects. This option is only available if the Show condition task has been run beforehand.
Attestation with multi- factor authen- tication	Attestation of this attestation policy requires multi-factor authentication.

NOTE: You can only edit attestation policies in the Web Portal that were created in the Web Portal. You will see a corresponding message on the master data form as to whether the attestation policy as created in the Web Portal.

If you want to edit attestation policies like this, create a copy in the Manager.

For detailed information about editing attestation policies in the Web Portal, see the *One Identity Manager Web Portal User Guide*.

Detailed information about this topic

- Showing or hiding conditions on page 32
- Schedules on page 17
- Disabling attestation policies on page 33
- Mitigating controls on page 136
- Setting up multi-factor authentication for attestation on page 80
- Creating a copy on page 32

Related topics

- Deleting attestation cases on page 97
- Deleting attestation policies on page 33

Risk assessment

You can use One Identity Manager to evaluate the risk of attestation cases. To do this, enter a risk index for the attestation policy. The risk index specifies the risk involved for the company in connection with the data to be attested. The risk index is given as a number in the range 0 ... 1. By doing this you specify whether data to be attested is considered not to be a risk (risk index = 0) or whether every denied attestation poses a problem (risk index = 1).

The risk that attestations will be denied approval can be reduced by using the appropriate mitigating controls. Enter these controls as mitigating controls in One Identity Manager. You reduce the risk by the value entered as the significance reduction on the mitigating control. This value is used to calculate the reduced risk index for the attestation policy.

You can create several reports with the Report Editor to evaluate attestation cases depending on the risk index. For more detailed information, see the *One Identity Manager Configuration Guide*.

Risk assessments can be carried out when the **QER | CalculateRiskIndex** configuration parameter is enabled. For more detailed information, see the *One Identity Manager Risk Assessment Administration Guide*.

Detailed information about this topic

• Mitigating controls on page 136

Default attestation policies

One Identity Manager provides default attestation policies for default attestation of new users and recertification of all employees stored in the One Identity Manager database. In addition to this, default attestation policies are provided through which various roles, memberships in roles, and system entitlements can be attested.

To display default attestation policies

• In the Manager, select the **Attestation | Attestation policies | Predefined** category.

You can customize the following properties for default attestation policies:

- Approval policies (if several approval policies can be assigned)
- Owner
- Processing time
- Risk index
- Calculation schedule
- Deactivated
- Close obsolete tasks automatically
- Obsolete tasks limit
- Reason for decision

TIP: If you want to limit the number of attestation objects for default attestation polices, create a copy of the default attestation policy. You can edit the condition in the copy.

NOTE: You can edit attestation policies, whose condition is stored as a definition (XML), in the Web Portal. The definition (XML) cannot be edited in the Manager. For detailed information, see *One Identity Manager Web Portal User Guide*.



Additional tasks for attestation policies

After you have entered the master data, you can run the following tasks.

The attestation policy overview

You can see the most important information about an attestation policy on the overview form.

To obtain an overview of an attestation policy

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list.
- 3. Select Attestation policy overview task.

Assigning approvers

Use this task to assign employees that can be determined as approvers in an attestation case to the selected attestation policy.

To assign approvers to an attestation policy

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list.
- 3. Select the **Assign approver** task.

Assign the approvers in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of approvers.

To remove an assignment

- Select the approver and double-click 𝔄.
- 4. Save the changes.

Detailed information about this topic

• Selecting attestors on page 56

Assigning compliance frameworks

Use this task to specify which compliance frameworks are relevant for the selected attestation policy. Compliance frameworks are used for classifying attestation policies,



compliance rules, and company policies according to regulatory requirements.

To assign compliance frameworks to an attestation policy

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list.
- 3. Select the **Assign compliance frameworks** task.

Assign the compliance frameworks in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of compliance frameworks.

To remove an assignment

- Select the compliance framework and double-click 𝔄.
- 4. Save the changes.

Mitigating controls

Mitigating controls describe controls that are implemented if an attestation rule was violated. The attestation can be approved after the next attestation run, once controls have been applied.

To edit mitigating controls

• In the Designer, enable the **QER | CalculateRiskIndex** configuration parameter.

Detailed information about this topic

- Mitigating controls on page 136
- Assigning mitigating controls on page 30
- Creating mitigating controls on page 31

Assigning mitigating controls

Specify which mitigating controls apply to the selected attestation policy.

To assign mitigating controls to an attestation policy

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list.
- 3. Select the **Assign mitigating controls** task.

In **Add assignments**, assign the mitigating controls.

TIP: In **Remove assignments**, you can remove the assignment of mitigating controls.



To remove an assignment

- Select the mitigating control and double-click *S*.
- 4. Save the changes.

Creating mitigating controls

To create a mitigating control for attestation policies

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select an attestation policy in the result list.
- 3. Select the Assign mitigating controls task.
- 4. Select Create mitigating controls task.
- 5. Enter the master data for the mitigating control.
- 6. Save the changes.
- 7. Select the Assign attestation polices task.
- 8. In **Add assignments**, double-click the attestation policies that are to be assigned.
- 9. Save the changes.

Detailed information about this topic

• Mitigating controls on page 136

Running attestation for single objects

Use this task to start attestations independently from a schedule. If you run the task, a separate window is opened. Select the objects to be attested now from a list of all attestation objects. The selection is one-off.

The **Close obsolete tasks automatically** option is not taken into account for the selected attestation objects.

To start attestation for the selected objects

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list. Select the Change master data task.
- 3. Select the **Run attestation cases for single objects...** task.

This opens a separate window.

- 4. In the Attestation column, select every object for which attestation is to be run.
- 5. Click Run.

Attestation cases are generated for the selected attestation objects. As soon as DBQueue Processor has processed the task, you will see the newly created



attestation cases in the navigation view under the **Attestation runs | <attestation policy> | Attestation runs | <year> | <month> | <day> | Pending attestations menu item.**

6. Click Close.

Showing or hiding conditions

The condition for finding attestation objects can be viewed and edited in the Where Clause Wizard. The SQL query for this condition can be displayed on the master data form.

To show the condition for finding attestation objects on the master data form

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Select the **Show condition** task.

This displays the **Condition** text box on the master data form. The condition is written like a database query WHERE clause. You can edit it directly.

To hide the condition for finding attestation objects

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Select the Hide condition task.

The input field **Condition** is no longer displayed on the master data form.

Creating a copy

You can make copies of attestation policies and use them to modify default attestation policies, for example.

To copy an attestation policy

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list.
- 3. Select the Create copy task.
- 4. Confirm the security prompt with **Yes**.

The attestation policy copy is displayed on the master data form with the name **Copy** of **<Name of original attestation policy>**. You can edit this attestation policy.



Showing selected objects

To show a list of attestations found

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list and run Change master data.
- 3. Select **Show selected objects** task.

An additional **Result** tab is shown on the master data form. This displays a list of attestation objects found through the condition.

Deleting attestation policies

IMPORTANT: Do not delete attestation policies, for audit reasons.

Attestation policies may still be removed from the One Identity Manager database under specific conditions. Ensure that the attestation policy is archived when deleted.

For detailed information about data archiving, see the *One Identity Manager Configuration Guide*.

Prerequisite

• The attestation policy is disabled.

To delete an attestation policy

- 1. In the Manager, select the **Attestation | Attestation policies | Disabled policies** category.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Select **Delete attestation policy** task.
- 4. Confirm the security prompt with **Yes**.

The attestation policy is deleted. All associated attestation cases, approval workflows and the attestation history are deleted.

Related topics

• Disabling attestation policies on page 33

Disabling attestation policies

Attestations are run when the schedule assigned to an attestation policy is enabled. You can disabled attestation policies to prevent attestation cases being created for individual attestation policies.



TIP: Numerous default attestation policies are supplied with One Identity Manager. Check which of the default attestation policies are relevant for your data situation when you set up your database. Disable all unnecessary attestation policies.

To disable an attestation policy

- 1. In the Manager, select Attestation | Attestation policies.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Set **Disabled**.
- 4. Save the changes.

Custom mail templates for notifications

A mail template consists of general master data such as target format, importance, or mail notification confidentiality, and one or more mail definitions. Mail text is defined in several languages in the mail template. This ensures that the language of the recipient is taken into account when the email is generated.

In One Identity Manager, there is a Mail Template Editor to simplify writing notifications. You can use the Mail Template Editor to create and edit mail texts in WYSIWYG mode.

Creating and editing attestation mail templates

To edit mail templates

1. In the Manager, select the **Attestation | Basic configuration data | Mail templates** category.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select a mail template in the result list and run the **Change master data** task.
 - OR -

Click 🖬 in the result list.

This opens the mail template editor.

- 3. Edit the mail template.
- 4. Save the changes.



Detailed information about this topic

- General properties of a mail template on page 35
- Creating and editing a mail definition on page 36

General properties of a mail template

The following general properties are displayed for a mail template:

Property	Meaning
Mail template	Name of the mail template. This name will be used to display the mail templates in the administration tools and in the Web Portal. Translate the given text using the [©] button.
Base object	Mail template base object. A base object only needs to be entered if the mail definition properties of the base object are referenced.
	Use the AttestationCase or AttestationHelper base object for notific- ations about attestation.
Report (parameter set)	Report, made available through the mail template.
Description	Mail template description. Translate the given text using the S button.
Target format	Format in which to generate email notification. Permitted values are:
	 HTML: The email notification is formatted in HTML. Text formats, for example, different fonts, colored fonts, or other text formatting, can be included in HTML format.
	 TXT: The email notification is formatted as text. Text format does not support bold, italics, or colored font, or other text formatting. Images displayed directly in the message are not supported.
Design type	Design in which to generate the email notification. Permitted values are:
	 Mail template: The generated email notification contains the mail body in accordance with the mail definition.
	 Report: The generated email notification contains the report specified under Report (parameter set) as its mail body.
	• Mail template, report in attachment: The generated email notific- ation contains the mail body in accordance with the mail definition. The report specified under Report (parameter set) is attached to the notification as a PDF file.

Table 10: Mail template properties



Property	Meaning
Importance	Importance for the email notification. Permitted values are Low , Normal , and High .
Confidentiality	Confidentiality for the email notification. Permitted values are Normal , Personal , Private , and Confidential .
Can unsubscribe	Specifies whether the recipient can unsubscribe email notification. If this option is set, the emails can be unsubscribed through the Web Portal.
Deactivated	Specifies whether this mail template is disabled.
Mail definition	Unique name for the mail definition.
Language	Language that applies to the mail template. The recipient's language preferences are taken into account when an email notification is generated.
Subject	Subject of the email message.
Mail body	Content of the email message.

Creating and editing a mail definition

Mail texts can be defined in these different languages in a mail template. This ensures that the language of the recipient is taken into account when the email is generated.

To create a new mail definition

- 1. Open the mail template in the Mail Template Editor.
- 2. Click the **button** next to the **Mail definition** list.
- 3. In the result list, select the language for the mail definition in the **Language** menu.

All active languages are shown. To use another language, in the Designer, enable the corresponding countries. For more detailed information, see the *One Identity Manager Configuration Guide*.

- 4. Enter the subject in **Subject**.
- 5. Edit the mail text in the Mail definition view with the help of the Mail Text Editor.
- 6. Save the changes.

To edit an existing mail definition

- 1. Open the mail template in the Mail Template Editor.
- 2. Select the language in Mail definition.
- 3. Edit the mail subject line and the body text.
- 4. Save the changes.



Using base object properties

In the subject line and body text of a mail definition, you can use all properties of the object entered under **Base object**. You can also use the object properties that are referenced by foreign key relation.

To access properties use dollar notation. For more detailed information, see the *One Identity Manager Configuration Guide*.

Example

Duran autor Malara

An attestor should receive email notification of new attestations.

Table 11: Email notification properties

Property	Value
Base object	AttestationHelper
Subject	New attestations
Mail body	Dear \$FK(UID_PersonHead).Salutation[D]\$ \$FK(UID_ PersonHead).LastName\$,
	There are new attestations pending for the attestation policy "\$FK(UID_ AttestationCase).UID_AttestationPolicy[D]\$".
	Created: \$FK(UID_AttestationCase).PolicyProcessed:Date\$
	You can see this request in the "One Identity Manager Self Service Portal".
	Best regards

Use of hyperlinks in the Web Portal

You can add hyperlinks to the Web Portal in the mail text of a mail definition. If the recipient clicks on the hyperlink in the email, the Web Portal opens on that web page and further actions can be carried out. In the default version, this method is implemented in attestations.

Prerequisites for using this method

• The **QER** | **WebPortal** | **BaseURL** configuration parameter is enabled and contains the URL path to the Web Portal. You edit the configuration parameter in the Designer.

```
http://<server name>/<application>
with:
<server name> = name of server
<application> = path to the Web Portal installation directory
```



To add a hyperlink to the Web Portal in the mail text

- 1. Click the position in the mail text of the mail definition where you want to insert a hyperlink.
- 2. Open the **Hyperlink** context menu and enter the following information.
 - **Display text**: Enter a caption for the hyperlink.
 - Link to: Select the File or website option.
 - Address: Enter the address of the page in the Web Portal that you want to open.

NOTE: One Identity Manager provides a number of default functions that you can use to create hyperlinks in the Web Portal.

3. To accept the input, click **OK**.

Default functions for creating hyperlinks

Several default functions are available to help you create hyperlinks. You can use the functions directly when you add a hyperlink in the mail body of a mail definition or in processes

Direct function input

You can reference a function when you add a hyperlink in the **Address** field of the **Hyperlink** context menu.

\$Script(<Function>)\$

Example:

\$Script(VI_BuildAttestationLink_Approve)\$

Default functions for requests

The VI_BuildAttestationLinks script contains a collection of default functions for composing hyperlinks to directly grant or deny approval of requests from email notifications.

Function	Usage
VI_BuildAttestationLink_Show	Opens the attestation page in the Web Portal.
VI_BuildAttestationLink_ Approve	Approves an attestation and opens the attestation page in the Web Portal.
VI_BuildAttestationLink_Deny	Denies an attestation and opens the attestation page in the Web Portal.
VI_BuildAttestationLink_ AnswerQuestion	Opens the page for answering a question in the Web Portal.

Table 12: Functions of the VI_BuildAttestationLinks script



Function	Usage
VI_BuildAttestationLink_ Pending	Opens the page with pending attestations in the Web Portal.

Customizing email signatures

Configure the email signature for mail templates using the following configuration parameter. Edit the configuration parameters in the Designer.

 Table 13: Configuration parameters for email signatures

Configuration parameter	Description
Common MailNotification Signature	Data for the signature in email automatically generated from mail templates.
Common MailNotification Signature Caption	Signature under the salutation.
Common MailNotification Signature Company	Company name.
Common MailNotification Signature Link	Link to the company's website.
Common MailNotification Signature LinkDisplay	Display text for the link to the company's website.

VI_GetRichMailSignature combines the components of an email signature according to the configuration parameters for use in mail templates.

Copying mail templates for attestation

To copy a mail template

1. In the Manager, select the **Attestation | Basic configuration data | Mail templates** category.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select the mail template that you want to copy in the result list and run the **Change master data** task.
- 3. Select the **Copy mail template** task.
- 4. Enter the name of the new mail template in the **Name of copy** field.
- 5. Click **OK**.



Displaying attestation mail templates previews

To display a mail template preview

1. In the Manager, select the **Attestation | Basic configuration data | Mail templates** category.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select a mail template in the result list and run the **Change master data** task.
- 3. Select the **Preview** task.
- 4. Select the base object.
- 5. Click **OK**.

Deleting mail templates for attestation

To delete a mail template

1. In the Manager, select the **Attestation | Basic configuration data | Mail templates** category.

This shows all the mail templates that can be used for attestation cases in the result list.

- 2. Select the template in the result list.
- 3. Click 🔽 in the result list.
- 4. Confirm the security prompt with **Yes**.

Custom notification processes

Set up customized processes to send more email notifications within an attestation case. You can use following events for generating processes.

Table 14: Events for the AttestationHelper object

Event	Triggered by
DecisionRequired	New attestation case created
	Move to the next approval level
Remind	Reminder interval expired



Event	Triggered by
Granted	Approval granted for an approval step.
Dismissed	Approval denied for an approval step.
OrderGranted	Approval granted for an entire approval procedure.
FinalDismissed	Approval denied for an entire approval procedure.
QueryToPerson	Making a query
AnswerFromPerson	Answering a query
RecallQuery	Recalling a query
Escalate	Attestation case escalated.
Aborted	Attestation case aborted.
Canceled	Obsolete attestation case aborted.

Table 15: Events for the AttestationCase object

For detailed information about creating processes, see the One Identity Manager Configuration Guide.



Approval processes for attestation cases

All attestation procedures are subject to a defined approval process. During this approval process, authorized employees grant or deny approval for attestation objects. You can configure this approval process in various ways, and therefore customize it to meet your company policies.

You define approval policies and approval workflows for approval processes. Specify the approval workflows to apply to the attestation cases in the approval policies. Use approval workflows to find out, which employees in which order, can grant or deny attestation. An approval workflow can contain several approval levels and several approval steps. A special approval procedure is used to determine the attestors in each approval step.

Detailed information about this topic

- Approval policies for attestations on page 42
- Approval workflow for attestations on page 45
- Editing approval levels on page 49
- Default approval procedures on page 57

Approval policies for attestations

One Identity Manager uses approval policies to determine the attestor for each attestation case.

To edit an approval policy

- 1. Select the Attestation | Basic configuration data | Approval policies category.
- 2. Select an approval policy in the result list and run the **Change master data** task.
 - OR -

Click 🖶 in the result list.



- 3. Edit the approval policy master data.
- 4. Save the changes.

General master data for approval policies

Enter the following master data for an approval policy. If you add a new approval step, you must fill out the compulsory fields.

Property	Description
Approval policies	Approval step name.
Approval	Workflow for finding attestors.
workflow	Select any approval workflow from the menu or click 뒾 to set up a new approval workflow.
Mail templates	Mail template used to create email notifications for granting, denying, extending, unsubscribing, or canceling an attestation or for giving notice of its expiry.
D	

Table 16: General master data for approval policies

Description Spare field for additional explanation.

Detailed information about this topic

- Setting up approval workflows on page 48
- Notifications in the attestation process on page 98

Default approval policies

One Identity Manager provides a default approval policy for default attestation of new users and recertification of all employees stored in the One Identity Manager database. Moreover, default approval policies are supplied through which different roles and system entitlements mapped in the Unified Namespace can be attested. You can use default approval policies for creating attestation policies in the Web Portal.

To edit default approval policies

• In the Manager, select the Attestation | Basic configuration data | Approval policies | Predefined category.

For detailed information about using default approval policies, see the *One Identity Manager Web Portal User Guide*.



Related topics

- User attestation and recertification on page 121
- Default attestation and withdrawal of entitlements on page 112

Additional tasks for approval policies

After you have entered the master data, you can run the following tasks.

Editing approval workflows

Here, you can edit the approval workflow assigned to the approval policy.

To edit the assigned approval workflow

- 1. Select Attestation | Basic configuration data | Approval policies.
- 2. Select the approval policy in the result list.
- 3. Select **1. Editing approval workflows**.

This opens the Workflow Editor.

Detailed information about this topic

• Working with the workflow editor on page 45

Validity checking

Once you have edited an approval policy, you need to test it. This checks whether the approval steps can be used in the approval workflows in this combination. Non-valid approval steps are displayed in the error window.

To test an approval policy

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval policies** category.
- 2. Select the approval policy in the result list.
- 3. Select the Validity check task.



Approval workflow for attestations

You need to allocate an approval workflow to the approval policies in order to find the attestors. In an approval workflow, you specify the approval procedures, the number of attestors and a condition for selecting the attestors.

Use the workflow editor to create and edit approval workflows.

To edit an approval workflow

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval** workflows category.
- 2. Select the approval workflow in the result list and run the **Change master data** task.

- OR -

Click 🛃 in the result list.

This opens the Workflow Editor.


- 3. Edit the approval workflow master data.
- 4. Save the changes.

Working with the workflow editor

Use the workflow editor to create and edit approval workflows. The workflow editor allows approval levels to be linked together. Multi-step approval processes are clearly displayed in a graphical form.



Figure 1: Workflow editor



Approval levels and approval steps belonging to the approval workflow are edited in the workflow editor using special control elements. The workflow editor contains a toolbox. The toolbox items are activated or deactivated depending on how they apply to the control. You can move the layout position of the control elements in the workflow editor with the mouse or these can be moved automatically.

Control	Item	Meaning
Workflow	Edit	Edit the properties of the approval workflow.
	Layout automatically	The workflow elements are aligned automatically. The workflow layout is recalculated.
Approval	Add	A new approval level is added to the workflow.
levels	Edit	Edit the properties of the approval workflow.
	Delete	Deletes the approval level.
Approval	Add	Add a new approval step to the approval level.
steps	Edit	Edit the properties of the approval step.
	Delete	Deletes the approval step.
Assignments	Remove positive	The Approved connector for the selected approval level is deleted.

Table 17: Entries in the toolbo



Control	Item	Meaning
	Remove negative	The Deny connector for the selected approval level is deleted.
	Remove reroute	The Reroute connector for the selected approval level is deleted.
	Remove escalation	The Escalate connector for the selected approval level is deleted.

Each of the controls has a properties window for editing the data of the approval workflow, level, or step. To open the properties window, select the **Toolbox | < Control> | Edit** item.

To delete a control, select the element and then the **Toolbox | <Control> | Delete** item.

Individual elements are linked to each other with a connector. Activate the connection points with the mouse. The cursor changes into an arrow icon for this. Hold down the left mouse button and pull a connector from one connection point to the next.

Figure 2: Approval workflow connectors






Table 18: Approval workflow connectors

Connector Mooning

Connector	meaning
Approve	Link to next approval level if the current approval level was granted approval.
Deny	Link to next approval level if the current approval level was not granted approval.
Reroute	Link to another approval level to bypass the current approval.
Escalation	Connection to another approval level when the current approval level is escalated after timing out.

By default, a connection between workflow elements and level elements is created immediately when a new element is added. If you want to change the level hierarchy, drag a new connector to another level element.

Alternatively, you can release connectors between level elements using the **Toolbox** | **Assignments** items. To do this, mark the level element where the connector starts. Then add a new connector.

Different icons are displayed on the level elements depending on the configuration of the approval steps.

Table 19: Icons on the level elements

Icon	Meaning
Ø*	The approval decision is made by the system.
a	The approval decision is made manually.
\sim	The approval step contains a reminder function.
Ø	The approval step contains a timeout.

Changes to individual elements in the workflow do not take place until the entire approval workflow is saved. The layout position in the workflow editor is saved in addition to the approval policies.

Setting up approval workflows

An approval workflow consists of one or more approval levels. An approval level can contain one approval step or several parallel approval steps. Within the attestation process, all of the approval steps for one approval level must be executed before the next approval level is called. Use connectors to set up the sequence of approval levels in the approval workflow.

When you add a new approval workflow, the first thing to be created is a new workflow element.



To edit approval level properties

- 1. Open the Workflow Editor.
- 2. Select the Toolbox | Workflow | Edit item.
- 3. Edit the workflow properties.
- 4. Click **OK**.

Table 20: Approval workflow properties

Property	Meaning
Name	Approval workflow name.
System abort (days)	Number of days to elapse after which the approval workflow, and therefore the system, automatically ends the entire attestation procedure.

Description Spare field for additional explanation.

Detailed information about this topic

• Aborting an attestation case on timeout on page 88

Editing approval levels

An approval level provides a method of grouping individual approval steps. All the approval steps in one approval level are executed in parallel. All the approval steps for different approval levels are executed one after the other. You use the connectors to specify the order of execution.

Specify the individual approval steps in the approval levels. At least one approval step is required per level. Enter the approval steps first before you add an approval level.

To add an approval level

1. Select the Toolbox | Approval levels | Add item.

This opens the properties dialog for the first approval step.

- 2. Enter the approval step properties.
- 3. Save the changes.

You can edit the properties of an approval level as soon as you have added an approval level with at least one approval step.

To edit approval level properties

- 1. Select the approval level.
- 2. Select the Toolbox | Approval levels | Edit item.



- 3. Enter a display name for the approval level.
- 4. Save the changes.

NOTE: You can define more than one approval step for each approval level. In this case, the attestors of an approval level can make a decision about an attestation case in parallel rather than sequentially. The attestation case cannot be presented to the attestors at the next approval level until all approval steps in one approval level have been completed in the attestation procedure.

To add more approval steps to an approval level

- 1. Select the approval level.
- 2. Select the **Toolbox | Approval levels | Add** item.
- 3. Enter the approval step properties.
- 4. Save the changes.

Related topics

- Properties of an approval step on page 50
- Editing approval steps

Editing approval steps

To edit approval level properties

- 1. Select the approval step.
- 2. Select the **Toolbox | Approval steps | Edit** item.
- 3. Edit the approval step properties.
- 4. Save the changes.

Detailed information about this topic

• Properties of an approval step on page 50

Properties of an approval step

On the **General** tab, enter the data described below. On the **Mail templates** tab, select the mail templates for generating mail notifications. If you add a new approval step, you must fill out the required fields.



Property	Meaning
Single step	Approval step name.
Approval Procedure to use for determining the attestors. procedure	
Role	Hierarchical role from which the attestors are to be determined using the default approval procedures OM and OR.
Fallback approver	Application role whose members are authorized to approve attestation cases if an attestor cannot be determined through the approval procedure. Assign an application from the menu.
	To create a new application role, click 🗐. Enter the application role name and assign a parent application role. For detailed information, see the One Identity Manager Authorization and Authentication Guide.
	NOTE: The number of approvers is not applied to the fallback approvers. The approval step is considered approved the moment as soon as one fallback approver has approved the request.
Condition	Condition for calculating approval with approval procedures CD, EX, or WC.
Number of approvers	Number of attestors required to approve an attestation case. Use this number to further restrict the maximum number of approvers of the implemented approval procedure.
	If there are several people allocated as approvers, then this number specifies how many people from this group have to approve an attestation case. A request can only be passed up to next level afterwards.
	If not enough attestors can be found, the approval step is presented to the fallback approvers. The approval step is considered approved as soon as one fallback approver has approved the attestation case.
	If you want approval decisions to be made by all the employees found using the applicable approval procedure, for example, all members of a role (default approval procedure OR), enter the value -1 . This overrides the maximum number of attestors defined in the approval procedure.
	The number of approvers defined in an approval step is not taken into account in the approval procedures CD, EX,or WC.
Description	Spare field for additional explanation.
Approval	Reason entered in the attestation case if approval is automatically granted.
reason	This field is only shown for the approval procedures CD, EX, and WC.
Reject reason	Reason entered in the attestation case and the attestation history, if approval is automatically denied.
	This field is only shown for the approval procedures CD, EX, and WC.

Table 21: General properties of an approval step



Property	y Meaning		
Reminder interval	Number of working hours to elapse after which the attestor is notified by mail that there are still pending attestation cases for attestation.		
(hours)	The reminder interval is set to 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.		
	NOTE: Ensure that a state, county, or both is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about calculating employees' working hours, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .		
	If more than one attestor was found, each attestor will be notified. The same applies if an additional attestor has been assigned.		
	If an attestor delegated the approval, the time point for reminding the delegation recipient is recalculated. The delegation recipient and all the other attestors are notified. The original attestor is not notified.		
	If an attestor has made an inquiry, the time point for reminding the queried employee is recalculated. As long as the inquiry has not been answered, only this employee is notified.		
TimeOut (working	Number of working hours to elapse after which the approval step is automatically granted or denied approval.		
hours)	The timeout is check every 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.		
	The working hours of the respective approver are taken into account when the time is calculated.		
	NOTE: Ensure that a state, county, or both is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about calculating employees' working hours, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .		
	If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.		
	If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.		
	If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not		



Property Meaning

	receleulated
	recalculated.
Timeout behavior	Action that is executed if the timeout expires.
	 Approved: The attestation case is approved in this approval step. The next approval level is called.
	 Deny: The attestation case is denied in this approval step. The approval level for denying is called.
	 Escalation: The attestation case is escalated. The escalation approval level is called.
	 Abort: The approval step and, therefore, the attestation case, are canceled.
Additional approver possible	Specifies whether a current attestor is allowed to instruct another employee as an attestor. This additional attestor has parallel authorization to make approvals for the current attestation case. The attestation case is not passed on to the next approval level until both attestors have made a decision.
	This option can only be set for approval levels with a single, manual approval step.
Approval can be delegated	Specifies whether a current attestor can delegate the attestation to another person. This employee is added to the current approval step as the attestor. This employee then makes the approval decision instead of the attestor who made the delegation.
	This option can only be set for approval levels with a single, manual approval step.
Approval by affected employee	Specifies whether the employee who is affected by the approval decision can also approve it. If this option is set, employees to be attested can attest themselves.
	If this option is not set, use the QER Attestation PersonToAt- testNoDecide configuration parameter to define whether the employees to be attested can attest themselves.
Do not show in approval history	Specifies whether or not the approval step should be displayed in the attest- ation history. For example, this behavior can be applied to approval steps with the CD - calculated approval procedure, which are used only for branching in the approval workflow. It It makes it easier to follow the attest- ation history.

Detailed information about this topic

- Notifications in the attestation process on page 98
- Reminding attestors on page 100
- Escalating an attestation case on page 83
- Automatic approval on timeout on page 86

- Aborting an attestation case on timeout on page 88
- Using a specified role to find attestors on page 67
- Calculated approval on page 69
- Approvals to be made externally on page 70
- Waiting for further approval on page 71
- Prevent attestation by employee awaiting attestation on page 81

Related topics

- Selecting attestors on page 56
- Attestors cannot be established on page 85
- Attestation through chief approval team on page 89

Connecting approval levels

When you set up an approval workflow with several approval levels, you have to connect each level with another. You may create the following links.

Table 22: Links to approval levels

Link	Description
Approve	Link to next approval level if the current approval level was granted approval.
Deny	Link to next approval level if the current approval level was not granted approval.
Reroute	Link to another approval level to bypass the current approval. Attestors can pass the approval decision through another approval level, for example, if approval is required by a manager in an individual case. To do this, create a connection to the approval level to which the approval can be rerouted. This way, approvals can also be rerouted to a previous approval level, for example, if an approval decision is considered not to be well- founded. It is not possible to reroute approval steps with the approval procedures EX, CD, SB, or WC.
Escalation	Link to another approval level when the current approval level is escalated

after timing out.

If there are no further approval levels after the current approval level, the attestation case is considered approved if the approval decision was to grant approval. If approval is not granted, the attestation case is considered to be finally denied. The attestation procedure is closed in both cases.



Additional tasks for approval workflows

After you have entered the master data, you can run the following tasks.

The approval workflow overview

To obtain an overview of an approval workflow

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval** workflows category.
- 2. Select the approval workflow in the result list.
- 3. Select Approval workflow overview.

Copying approval workflows

You can copy default approval workflows in order to customize them.

To copy an approval workflow

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval** workflows category.
- 2. Select an approval workflow in the result list and run the **Change master data** task.
- 3. Select the Copy workflow task.
- 4. Enter a name for the copy.
- 5. Click **OK** to start copying.

- OR -

Click Cancel to cancel copying.

6. To edit the copy immediately, click Yes.

- OR -

To edit the copy later, click No.

Deleting approval workflows

The approval workflow can only be deleted if it is not assigned to an approval policy.



To delete an approval workflow

- 1. Remove all assignments to approval policies.
 - a. Check to which approval policies the approval workflow is assigned.
 - b. Go to the master data form for the approval policy and assign a different approval workflow.
- 2. In the Manager, select the **Attestation | Basic configuration data | Approval** workflows category.
- 3. Select an approval workflow in the result list.
- 4. Click 🛃.
- 5. Confirm the security prompt with **Yes**.

Detailed information about this topic

- The approval workflow overview on page 55
- General master data for approval policies on page 43

Default approval workflows

One Identity Manager provides a default approval workflow for default attestation of new users and recertification of all employees stored in the One Identity Manager database. Moreover, default approval workflows are supplied through which different roles and system entitlements mapped in the Unified Namespace can be attested. You can use default approval policies for creating attestation policies in the Web Portal.

To edit default approval workflows

• In the Manager, select the Attestation | Basic configuration data | Approval workflows | Predefined category.

For detailed information about using default approval workflows, see the *One Identity Manager Web Portal User Guide*.

Related topics

- User attestation and recertification on page 121
- Default attestation and withdrawal of entitlements on page 112

Selecting attestors

One Identity Manager can make approvals automatically in an attestation procedure or through attestors. An attestor is an employee or a group of employees who can grant or



deny an attestation case within an attestation procedure. It takes several approval procedures to grant or deny approval. You specify in the approval step which approval procedure should be used.

If several people are determined to be approvers by an approval procedure, the number given in the approval step specifies how many people must approve the step. A request can only be passed up to next level afterwards. The attestation procedure is aborted if an approver cannot be found for an approval step.

One Identity Manager provides approval procedures by default. You can also define your own approval procedures.

The DBQueue Processor calculates which employee is authorized as an approver and in which approval level. Take into account the special cases for each approval procedure when setting up the approval workflows to determine those authorized to grant approval.

Default approval procedures

To display default approval procedures

 Select the Attestation | Basic configuration data | Approval procedures | Predefined category.

The following approval procedures are defined to select the responsible attestors, by default.

	Procedure Name	Attestors
	AA - Attestor for the role to attest	Attestor of the organization (department, cost center, location), business role, or IT Shop if assignments of system entitlements or system roles to roles are attested.
		 Attestors for departments, cost centers and locations must be assigned to the Identity Management Organ- izations Attestors application role.
		 Attestors for business roles must be assigned to the Identity Management Business roles Attestors application role.
		 Attestors for requests must be assigned to the Request & Fulfilment IT Shop Attestors application role.
		For more information, see Using attestation objects to find attestors on page 62.
	AD - Attestor of recipient's	Attestor of the department to which the attestation object is primarily assigned.
department	Attestors for departments must be assigned to the Identity	

Table 23: Approval procedures for attestation



Procedure Name	Attestors
	Management Organizations Attestors application role.
	For more information, see Using roles of employees to be attested to find attestors on page 62.
AL - Attestor for recipient's location	Attestor of the location to which the attestation object is primarily assigned.
	 Attestors for locations must be assigned to the Identity Management Organizations Attestors application role.
	For more information, see Using roles of employees to be attested to find attestors on page 62.
AM - Manager of account's person	Manager of the employee connected to the user account that is to be attested
	For more information, see Using persons responsible for attestation objects to find attestors on page 65.
AN - Attestor for the system entitlement to attest	Attestor of the system entitlement or system role if assignments of system entitlements or system roles to roles are attested. Attestors are determined through the assigned service item.
	 Attestors must be assigned to the Request & Fulfillment IT Shop Attestors application role.
	For more information, see Using attestation objects to find attestors on page 62.
AO - Attestor for recipient's primary	Attestor of the business role to which the attestation object is primarily assigned.
role	Attestors for business roles must be assigned to the Identity Management Business roles Attestors application role.
	For more information, see Using roles of employees to be attested to find attestors on page 62.
AP - Attestor for recipient's cost	Attestor of the cost center to which the attestation object is primarily assigned.
center	 Attestors for cost centers must be assigned to the Identity Management Organizations Attestors application role.
	For more information, see Using roles of employees to be attested to find attestors on page 62.
AR - Attestor for attestation	Attestor for the compliance rule to be attested.



Procedure Name	Attestors
compliance rule	 Attestors must be assigned to the Identity & Access Governance Identity Audit Attestors application role.
	For more information, see Using attestation objects to find attestors on page 62.
AS - Approver for	All employees assigned to the attestation policy as approver.
attestation policy	For more information, see Using attestation policies to find attestors on page 62.
AT - Attestor for the organization to be	Attestor of the organization (department, cost center, location), business role, or IT Shop to be attested.
attested	 Attestors for departments, cost centers and locations must be assigned to the Identity Management Organ- izations Attestors application role.
	 Attestors for business roles must be assigned to the Identity Management Business roles Attestors application role.
	 Attestors for requests must be assigned to the Request & Fulfilment IT Shop Attestors application role.
	For more information, see Using attestation objects to find attestors on page 62.
AY - Attestor for the	Attestor of the company policy to be attested.
company policy to be attested	 Attestors must be assigned to the Identity & Access Governance Company policies Attestors application role.
	For more information, see Using attestation objects to find attestors on page 62.
CD - Calculated	-
approval	For more information, see Calculated approval on page 69.
CM - Recipient's	Manager of the employee to be attested.
manager	For more information, see Using attestation object managers to find attestors on page 64.
DM - Manager of recipient's	Department manager/deputy if employees of secondary member- ships are attested in departments.
department	For more information, see Using attestation object managers to find attestors on page 64.
ED - Department	Employee's department manager whose system entitlements are



Procedure Name	Attestors
manager for	to be attested.
permission attestation	For more information, see Using persons responsible for attestation objects to find attestors on page 65.
EM - Employee manager for	Employee's manager whose system entitlements are to be attested.
permission attestation	For more information, see Using persons responsible for attestation objects to find attestors on page 65.
EN - Target system	Target system manager of the system entitlements to be attested.
manager of the permission for attestation	For more information, see Using persons responsible for attestation objects to find attestors on page 65.
EO - Product owner of the system	Product owner whose system entitlements or system roles are to be attested.
entitlement to be attested	For more information, see Using persons responsible for attestation objects to find attestors on page 65.
EX - Approvals to be	-
made externally	For more information, see Approvals to be made externally on page 70.
LM - Manager of recipient's location	Location manager/deputy if employees of secondary memberships are attested in locations.
	For more information, see Using attestation object managers to find attestors on page 64.
MD - Department manager of	Manager of the main department of the employee who is connected to the user account to be attested
account's person	For more information, see Using persons responsible for attest- ation objects to find attestors on page 65.
MO - Role owner	Business role manager/deputy if employees of secondary member- ships are attested in roles.
	For more information, see Using attestation object managers to find attestors on page 64.
OA - product owner	All members of the assigned application role if service items, system entitlements or system roles are attested.
	For more information, see Using product owners to find attestors on page 67.
OM - Manager of a	Manager of the role selected in the approval workflow.
specific role	For more information, see Using a specified role to find attestors on page 67.



Procedure Name	Attestors
OP - Owner of a privileged object	All employees that can be determined as owners of the privileged request.
	For more information, see Using owners of a privileged object to find attestors on page 68.
OR - Members of a	All employees that are assigned to a secondary business role.
certain role	For more information, see Using a specified role to find attestors on page 67.
PA - Secondary owner of Active	All employees to be found through the additional owner of the requested Active Directory group.
Directory group	For more information, see Using additional Active Directory group owners to find attestors on page 68.
PM - Manager of recipient's cost	Cost center manager/deputy if secondary memberships in cost centers are attested.
center	For more information, see Using attestation object managers to find attestors on page 64.
PO - Proposed owner	Proposed owner of the attestation object
	For more information, see Using owners of the attestation objects to find attestors on page 68.
RE - Manager of	System role manager to be attested.
system roles to be attested	For more information, see Using attestation object managers to find attestors on page 64.
RM - Role manager for attesting	Manager of role to be attested if secondary memberships in roles are attested.
memberships	For more information, see Using attestation object managers to find attestors on page 64.
RR - Role manager	Manager of role to be attested.
for attesting roles	For more information, see Using attestation object managers to find attestors on page 64.
SO - Target system manager of the	Target system manager of system entitlement or user account to be attested.
permission for attestation	For more information, see Using persons responsible for attestation objects to find attestors on page 65.
WC - Waiting for	-
further approval	For more information, see Waiting for further approval on page 71.



Using attestation policies to find attestors

Use the AS approval procedure if you want to fix attestors for any object to an attestation policy. This approval procedure finds all employees that are assigned to the attestation procedure as approvers.

Use this procedure to allow any objects to be attested by any of the specified employees. These employees must be assigned to the attestation policy as approvers. The attestor can also be entered when you create attestation policies in the Web Portal. For detailed information, see *One Identity Manager Web Portal User Guide*.

Related topics

Assigning approvers on page 29

Using roles of employees to be attested to find attestors

Installed modules: Business Roles Module (for approval procedure AO).

If you want to attest company resource assignments to employees or their requests, use the AD, AL, AO, or AP approval procedures. The attestors found are members of the **Attestor** application role.

Attestation objects are employees (Person table) or request recipients (PersonWantsOrg table). These approval procedures determine the role (department, location, business role, cost center) for each attestation object to which the attestation object is primarily assigned. If the primarily assigned role is not directly assigned an attestor, the approval procedure finds the the attestator's parents roles. If still no attestor can be determined, the attestation case is presented to the attestor of the associated role class for approval.

NOTE: When attestors are found using the AO approval procedure and when "bottom-up" inheritance is defined for business roles, note the following:

• If there is no attestor given for the primary business role, attestors are taken from the child business role.

Related topics

• Default approval procedures on page 57

Using attestation objects to find attestors

Use the AR, AY, or AT approval procedures if you want to attest the validity of compliance rules, rule violations, company policies, policy violations, or of departments, locations, cost centers, or business roles. The AT procedure is also suitable for attesting assignments



to IT Shop structures (shops, shopping centers, or shelves). Use the AA or AN approval procedures to attest system entitlement or system role assignments to departments, locations, cost centers, business roles or IT Shop structures. The attestors found are members of the **Attestor** application role.

	Attestation base objects	Available in Module	
AR	Rules (ComplianceRule)	Compliance Rules	
	Rule violations (PersonInNonCompliance)	Module	
AY	Company policies (QERPolicy)	Company Policies	
	Policy violations (QERPolicyHasObject)	Module	
AT	Departments (Department)		
	IT Shop Structures (ITShopOrg)		
	Locations (Locality)		
	Business roles (0rg)		
	Cost centers (ProfitCenter)		
	IT Shop Templates (ITShopSrc)		
AA, AN	System entitlement or target system group assignments to roles (<basetree>HasUNSGroupB,</basetree>	Target System Base Module	
	<basetree>HasADSGroup, <basetree>HasEBSResp,)</basetree></basetree>		

System role assignments to roles (<BaseTree>HasESet)

These approval procedures determine the attestors to which the attestation object is assigned. The AA approval procedure finds the attestor using the role (departments, locations, business roles, cost centers) or IT Shop structures (IT Shop templates). The AN approval procedure finds the attestor using the service item assigned to the system entitlement or target system group.

Furthermore, the following also applies to the AT and AA approval procedures: If an attestor is not directly assigned to the attestation object, the approval procedure finds the attestor of the parent roles/IT Shop structures. If still no attestor can be determined, the attestation case is presented to the attestor of the associated role class for approval.

NOTE: If the attestation base object is a business role or a business role assignment and bottom-up inheritance is defined for the associated role classes, the following applies:

• If there is no attestor assigned to the attestation object, the approval procedure finds attestors from the attestors of subordinate roles.

Related topics

Default approval procedures on page 57



Using attestation object managers to find attestors

If you want to have employees, user accounts, roles, system roles, role memberships, assignments of system roles, or entitlements for employees, roles, or IT Shop structures attested through their managers, use the CM, DM, LM, MO, RM, RR, or RE approval procedures.

Approval procedure	Attestation base objects	Available in Module	
СМ	Employees (Person)		
	Employees: memberships in roles and organizations (PersonInBaseTree)		
DM	Employees (Person)		
	Employees: department memberships (PersonInDepartment)		
LM	Employees (Person)		
	Employees: location memberships (PersonInLocality)		
MO	Employees (Person)	Business	
	Employees: business role memberships (PersonInOrg)	Roles Module	
PM	Employees (Person)		
	Employees: cost center memberships (PersonInProfitCenter)		
RE	System roles (ESet)	System	
	Employees: system role assignments (PersonHasESet)	Roles Module	
	Departments: system role assignments(DepartmentHasESet)	riodule	
	Business roles: system role assignments (OrgHasESet)		
	IT Shop structures: system role assignments (ITShop0rgHasESet)		
	IT Shop templates: system role assignments (ITShopSrcOrgHasESet)		
	Cost centers: system role assignments (ProfitCenterHasESet)		
	Locations: system role assignments (LocalityHasESet)		
RM	Employees: department memberships (PersonInDepartment)		
	Employees: IT Shop structure memberships (PersonInITShop0rg)		
	Employees: location memberships (PersonInLocality)		



Approval procedure	Attestation base objects	Available in Module
	Employees: business role memberships (PersonInOrg)	
	Employees: cost center memberships (PersonInProfitCenter)	
RR	Departments (Department)	
	IT Shop Structures (ITShop0rg)	
	Locations (Locality)	
	Business roles (0rg)	
	Cost centers (ProfitCenter)	
	IT Shop Templates (ITShopSrc)	
	All system entitlement or system role assignments to roles; for example Roles and organizations: Active Directory group assignments (BaseTreeHasADSGroup) or Locations: EBS entitlement assignments (LocalityHasEBSResp)	

These approval procedures find the manager associated with every attestation object. In the RE approval procedure, the system role manager is determined as attestor; in the RM and RR approval procedures, the role/IT Shop structure manager is determined. The approval procedures CM, DM, LM, MO, and PM find the department manager and deputy manager of the role in which the attesting employee is a member.

Using persons responsible for attestation objects to find attestors

If you want to attest system entitlements and the user accounts assigned to them, use the ED, EM, EN, EO, or SO approval policies. Use the approval procedures AM, MD, or SO to attest user accounts.

Attestation objects are user accounts or system entitlements and the user accounts assigned to them as well as system roles that have system entitlements or system roles assigned to them. The approval procedures determine the following attestors.

	Attestation base objects	Attestors	Available in Module
AM	User accounts (UNSAccount)	Employee's department manager to whom the user account is connected.	Target System Base Module



	Attestation base objects	Attestors	Available in Module
ED	User accounts: system entitlement assign- ments (UNSAccountInUNSGroup)	Employee's department manager (and deputy manager) to whom the user account is connected. The primary department assigned in this case.	Target System Base Module
EM	User accounts: system entitlement assign- ments (UNSAccountInUNSGroup)	Employee's department manager to whom the user account is connected.	Target System Base Module
EN	User accounts: system entitlement assign- ments (UNSAccountInUNSGroup) System entitlements (UNSGroup)	Target system manager of the target system area to which the system entitlement belongs.	Target System Base Module
EO	System roles: assignments (ESetHasEntitlement) All user account assignments to system entitlements; for example, User accounts: system entitlement assign- ments (UNSAccountInUNSGroup) or SAP user accounts: assignments to roles (SAPUserInSAPRole) All system entitlement or system role assignments to roles; for example, Roles and organizations: Active Directory group assignments (BaseTreeHasADSGroup) or Locations: EBS entitlement assign- ments (LocalityHasEBSResp)	Product owner of the service item to which the system entitlement or system role is assigned.	Target System Base Module or System Roles Module
MD	User accounts (UNSAccount)	Employee's department manager (and deputy manager) to whom the user account is connected. The primary department assigned in this case.	Target System Base Module
SO	User accounts: system entitlement assign- ments (UNSAccountInUNSGroup) User accounts (UNSAccount)	Target system manager for the target system to which the system entitle- ment or user account	Target System Base Module



Attestation base objects	Attestors	Available in Module
System entitlements: assignments to system entitlements (UNSGroupInUNSGroup)	belongs.	

Using a specified role to find attestors

If the attestors for any object are specified in a certain role, use the OR or OM approval procedure. You can allow any objects to be attested by employees from any role using these approval procedures. In the approval step, specify the role by means of which the attestors are to be determined. The approval procedures determine the following attestors.

	Selectable Roles	Attestors
OM	Departments (Department)	Manager and deputy manager of the role specified in the approval step.
	Cost centers (ProfitCenter)	
	Locations (Locality)	
	Business roles (0rg)	
OR	Departments (Department)	All secondary members of the role specified in the approval step.
	Cost centers (ProfitCenter)	
	Locations (Locality)	
	Business roles (0rg)	
	Application roles (AERole)	

Using product owners to find attestors

Use the approval procedure OA to detemine whether product owners can be attestors. The following objects can be attested with this procedure:

- Service items
- System entitlements
- System entitlement assignments to user accounts or system entitlements
- System role assignments to employees

Prerequisites:



- A service item must be assigned to the system entitlements and system roles.
- An application role for product owners must be assigned to the service item.

All employees who are assigned this application role are determined as attestors.

Using owners of a privileged object to find attestors

Installed modules: Privileged Account Governance Module

Use the OP approval procedure if you want to allow privileged objects in a Privileged Account Management system, for example, PAM assets or PAM directory accounts, to be attested by their owners. The owners attest the possible user accord to these privileged objects. The owners of the privileged objects must have the **Privileged Account Governance | Asset and account owners** application role or a child application role.

Using additional Active Directory group owners to find attestors

Installed modules: Active Roles Module

If the Active Directory group is attested, the attestor can be determined through additional owners of this Active Directory group. Use the PA approval procedure for this purpose. This finds all employees that are:

- A member in the assigned Active Directory group through their Active Directory user account
- Linked to the assigned Active Directory user account

NOTE: Only use the PA approval procedure if the **TargetSystem | ADS | ARS_SSM** configuration parameter is enabled. The column **Additional owners** is only available in this case.

Using owners of the attestation objects to find attestors

When you assign new owners to devices or system entitlements in the Web Portal, the new owner should agree with this assignment. An attestation with the PO approval procedure is carried out for this purpose.



Calculated approval

NOTE: Only one approval step can be defined with the CD approval procedure per approval level.

If you want to make attestation dependent on specific conditions, use the CD approval procedure. This procedure does not determine an attestor. One Identity Manager makes the decision depending on the condition that is formulated in the approval step.

You can use the procedure for any attestation base objects. You create a condition in the approval step. If the condition returns a result, the approval step is approved through the One Identity Manager. If the condition does not return a result, the approval step is denied by the One Identity Manager. If there are no further approval steps, the approval procedure is either finally granted or denied.

To enter a condition for the CD approval procedure

1. Edit the approval step properties.

For more information, see Editing approval levels on page 49.

2. In the **Condition** input field, enter a valid WHERE clause for database queries. You can enter the SQL query directly or with a wizard. In the condition, you reference the actual attestation case using the <code>@UID_AttestationCase</code> variable.

Example of a simple approval workflow with the CD approval procedure:

External employees should be attestation by their managers. If no manager is assigned, the members of a designated application role must attest the employees.

You can find all external employees, who have managers assigned to them by using the CD approval procedure and the following condition.

EXISTS

(SELECT 1 FROM

(SELECT xobjectkey FROM Person WHERE (IsExternal = 1)
AND (EXISTS
(SELECT 1 FROM
 (SELECT UID_Person FROM Person WHERE 1 = 1) as X
WHERE X.UID_Person = Person.UID_PersonHead))) as X

WHERE X.xobjectkey = AttestationCase.ObjectKeyBase)

If the condition is fulfilled, the external employee's manager can attest the employee. To do this, add an approval step in the positive approval path with the CM approval procedure.

If the condition is not fulfilled, the employee is attested by the member of a designated application role. To do this, add an approval step in the negative approval path with the OR approval procedure and assign the application role.



Approvals to be made externally

Use external approvals (EX approval procedure) if an attestation needs to be approved as soon as a defined event from outside One Identity Manager takes place. You can also use this procedure to allow any number of objects to be attested by employees who do not have access to One Identity Manager.

Specify an event in the approval step that triggers an external approval. The event triggers a process that initiates the external approval for the attestation case and evaluates the result of the approval decision. The approval process waits for the external decision to be passed to One Identity Manager. Define the subsequent approval steps depending on the result of the external approval.

To use an approval procedure

- 1. Define your own processes that:
 - Triggers an external approval.
 - Analyzes the results of the external approval.
 - Grants or denies approval in the subsequent external approval step in One Identity Manager.
- 2. Defines an event that starts the process for external approval. Enter the result in **Result** in the approval step.

If the external event occurs, the approval step status in One Identity Manager must be changed. Use the CallMethod process task with the MakeDecision method for this. Pass the following parameters to the process task:

```
MethodName: Value = "MakeDecision"
ObjectType: Value = "AttestationCase"
Param1: Value = "sa"
Param2: Value = <approval> ("true" = granted; "false" = denied)
Param3: Value = <reason for approval decision>
Param4: Value = <standard reason>
Param5: Value = <number approval steps> (PWODecisionStep.SubLevelNumber)
WhereClause: Value = "UID_AttestationCase ='"& $UID_AttestationCase$ &"'"
```

Use these parameters to specify which attestation case is to be approved by external approval (WhereClause). Param1 specifies the attestor. The attestor is always the **sa** system user. Param2 passes down the approval decision. If the attestation was granted, a value of **True** must be returned. If the attestation was denied, a value of **False** must be returned. Use Param3 to pass a reason text for the approval decision; use Param4 to pass a predefined standard reason. If more than one external approval steps have been defined in an approval level, use Param5 to pass the approval step count. This ensures the approval is aligned with the correct approval step.

Use the Process Editor to define and edit processes.



Example

All compliance rules should be checked and attested by an external assessor. The attestation object data should be made available as a PDF on an external share. The assessor should save the result of the attestation in a text file on the external share. Use this approval procedure to make external approvals and define:

- A P1 process that saves a PDF report with data about the attestation object data and the attestation procedure on an external share
- An E1 event that starts the P1 process

In the approval step, enter E1 in the **Event** field, and enter P1 in the process as the trigger for the external decision.

- A P2 process that checks the share for new text files, evaluates the content, and calls the One Identity Manager CallMethod process task the method MakeDecision method
- An E2 event that starts the P2 process
- A schedule that starts the E2 event on a regular basis

For detailed information about creating processes, see the *One Identity Manager Configuration Guide*. For detailed information about setting up schedules, see the *One Identity Manager Operational Guide*.

Detailed information about this topic

• Properties of an approval step on page 50

Waiting for further approval

NOTE: Only one approval step can be defined with the WC approval procedure per approval level.

If you want to ensure that a specific data state exists in One Identity Manager before an attestation case is finally approved, then use the WC approval procedure. Use a condition to specify which prerequisites have to be fulfilled so that attestation can take place. The condition is evaluated as a function call, which must accept the attestation case UID as a parameter (AttestationCase.UID_AttestationCase). You use this UID to reference the attestation object. The function must define three return values as integer values. One of the following actions is carried out depending on the function's return value.

Table 24: Return value for deferred approval

Return value	Action
Return value > 0	The condition is fulfilled. Deferred approval has completed successfully. The next approval step (in case of success) is carried out.
Return	The condition is not yet fulfilled. Approval is rolled back and is retested the



Return Action value

value = 0 next time DBQueue Processor runs.

Return The condition is not fulfilled. Deferred approval has failed. The next approval value < 0 step (in case of failure) is carried out.

To use an approval procedure

- 1. Create a database function which tests the condition for the attestation.
- 2. Create an approval step with the WC approval procedure. Enter the function call in **Condition**.

Syntax: dbo.<function name>

- 3. Specify an approval step in the case of success. Use the approval procedure with which One Identity Manager can determine the attestors.
- 4. Specify an approval step in the case of failure.

Setting up approval procedures

You can create your own approval procedures if the default approval procedures for finding the responsible attestors do not meet your requirements. The condition through which the attestors are determined is formulated as a database query. Several queries may be combined into one condition.

To set up an approval procedure

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval procedures** category.
- 2. Select an approval procedure in the result list and run the **Change master data** task.

- OR -

Click 🖬 in the result list.

- 3. Edit the approval procedure master data.
- 4. Save the changes.

To edit the condition

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval procedures** category.
- 2. Select an approval procedure from the result list.
- 3. Select Change queries for approver selection.



Detailed information about this topic

- General master data for an approval procedure on page 73
- Queries for finding attestors on page 73

General master data for an approval procedure

Enter the following master data for an approval procedure.

Property	Description	
Approval procedure		
Description	Approval procedure identifier.	
DBQueue Processor task	Approvals can either be made automatically through a DBQueue Processor calculation task or by specified approvers. Assign a custom DBQueue Processor task if the approval procedure should make an automatic approval decision.	
	You cannot assign a DBQueue Processor task if a query is entered for determining the attestors.	
Max. number approvers	Maximum number of attestors to be determined by the approval procedure. Specify how many employees must really make approval decisions in the approval steps used by this approval procedure.	
Sort order	Value for sorting approval procedures in the menu. Specify the value 10 to display this approval procedure at the top of the menu when you set up an approval step.	

Table 25: General master data for an approval procedure

Related topics

• Properties of an approval step on page 50

Queries for finding attestors

The condition through which the attestors are determined is formulated as a database query. Several queries may be combined into one condition. This adds all employees determined by single queries to the group of attestors.



To edit the condition

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval procedures** category.
- 2. Select an approval procedure from the result list.
- 3. Select Change queries for approver selection.

To create single queries

1. Click Add.

This inserts a new row in the table.

- 2. Mark this row. Enter the query properties.
- 3. Add more queries if required.
- 4. Save the changes.

To edit a single query

- 1. Select the query you want to edit in the table. Edit the query's properties.
- 2. Save the changes.

To remove single queries

- 1. Select the query you want to remove in the table.
- 2. Click **Delete**.
- 3. Save the changes.

Table 26: Query properties

Property	Description
Approver selection	Query identifier that determines the attestors.
Query	Database query for determining the attestors.
	The database query must be formulated as a select statement. The column selected by the database query must return a UID_ Person. Every query must return a value for UID_PWORulerOrigin. The query returns one or more employees to whom the attest- ation case is presented for approval. If the query fails to return a result, the attestation procedure is aborted.
	A query contains exactly one select statement. To combine several select statements, create several queries.
	If a DBQueue Processor task is assigned, you cannot enter a query to determine attestors.

You can, for example, determine predefined attestors with the query (example 1). The attestor can also be found dynamically depending on the attestation case to approve. To do



this, within the database query, using the @UID_AttestationCase variable to access the attestation case (example 2).

Example 1

The attestation cases should be approved by a specific attestor.

```
Query: select UID_Person, null as UID_PWORulerOrigin from Person where InternalName='Bloggs, Jan'
```

Example 2

All active compliance rules should be attested by the respective rule supervisor.

Query: select pia.UID_Person, null as UID_PWORulerOrigin from AttestationCase ac

join ComplianceRule cr on cr.XObjectKey = ac.ObjectKeyBase and cr.IsWorkingCopy = '0'

join PersonInBaseTree pia on pia.UID_Org = cr.UID_OrgResponsible and pia.XOrigin > 0

where ac.UID_AttestationCase = @UID_AttestationCase

Taking delegation into account

To include delegation when determining attestors, use the query to also determine the employees to whom a responsibility has been delegated. If the managers of hierarchical roles are to make the attestation decision, determine the attestors from the HelperHeadOrg table. This table groups all hierarchical role managers, their deputy managers, and employees to whom a responsibility has been delegated. If the members of business or application roles are to make the approval decision, determine the approvers from the PersonInBaseTree table. This table groups all hierarchical role members and employees to whom a responsibility has been delegated.

Determine the UID_PWORulerOrigin in order to notify delegators when the recipient of the delegation has made a decision on an attestation case and thus allow the Web Portal to show if the attestor was originally delegated.

To determine the UID_PWORulerOrigin of the delegation

• Determine the UID_PersonWantsOrg of the delegation and copy this value as UID_PWORulerOrigin to the query. Use the dbo.QER_FGIPWORulerOrigin table function to do this.

select dbo.QER_FGIPWORulerOrigin(XObjectKey) as UID_PWORulerOrigin

Modified query from example 2:

select pia.UID_Person, dbo.QER_FGIPWORulerOrigin(pia.XObjectKey) as UID_ PWORulerOrigin from AttestationCase ac

join ComplianceRule cr on cr.XObjectKey = ac.ObjectKeyBase and



```
cr.IsWorkingCopy = '0'
join PersonInBaseTree pia on pia.UID_Org = cr.UID_OrgResponsible and
pia.XOrigin > 0
where ac.UID_AttestationCase = @UID_AttestationCase
```

Additional tasks for approval procedures

After you have entered the master data, you can run the following tasks.

Overview of the approval procedure

To obtain an overview of an approval procedure

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval procedures** category.
- 2. Select an approval procedure from the result list.
- 3. Select the Approval procedure overview task.

Specifying permitted approval procedures for tables

You can only assign selected approval policies to attestation procedures. The approval policies permitted depend on the approval procedures applied in the approval policies and on the table that forms the attestation base object for an attestation procedure. You must specify which tables are permitted for use with custom approval procedures.

To specify the tables that permit this approval procedure

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval procedures** category.
- 2. Select an approval procedure from the result list.
- 3. Select the **Assign tables** task.

In **Add assignments**, assign the tables to which the approval procedure can be assigned.

TIP: In **Remove assignments**, you can remove the assignment of tables.

To remove an assignment

- Select the table and double-click 𝔄.
- 4. Save the changes.



You can see which tables allow an approval procedure on the approval procedure overview form.

Related topics

- Assigning approval policies on page 16
- Overview of the approval procedure on page 76

Copying an approval procedure

You can copy default approval procedures in order to customize them.

To copy an approval procedure

- 1. In the Manager, select the **Attestation | Basic configuration data | Approval procedures** category.
- 2. Select an approval procedure in the result list. Select the **Change master data** task.
- 3. Select the Create copy task.
- 4. Confirm the security prompt with **Yes**.
- 5. Enter the short name for the copy.

The short name for an approval procedure consists of a maximum of two characters.

- 6. Click **OK** to start copying.
 - OR -

Click **Cancel** to cancel copying.

Deleting approval procedures

To delete an approval procedure

- 1. Remove all assignments to approval steps.
 - a. On the approval procedure overview form, check which approval steps are assigned to the approval procedure.
 - b. Switch to the approval workflow and assign another approval procedure to the approval step.
- 2. In the Manager, select the **Attestation | Basic configuration data | Approval procedures** category.
- 3. Select an approval procedure from the result list.
- 4. Click 🛃.
- 5. Confirm the security prompt with **Yes**.



Related topics

• Overview of the approval procedure on page 76

Determining the responsible attestors

The DBQueue Processor calculates which employee is authorized as an approver and in which approval level. Once an attestation is triggered, the attestors are determined for every approval step of the workflow to be processed. Changes to responsibilities may lead to an employee no longer being authorized as an approver for an attestation that is not yet finally approved. In this case, the attestors must be recalculated. The following changes can trigger recalculation of pending attestations:

- Approval policy, workflow, step, or procedure changes.
- An authorized approver loses their responsibility in One Identity Manager, for example, if a change is made to the department manager, attestation policy approver, or target system manager.
- An employee obtains responsibilities in One Identity Manager and therefore is authorized as an approver, for example as the manager of the employee to be attested.
- An employee authorized as an approver is deactivated.

Once an employee's responsibilities have changed in One Identity Manager, a task for recalculating the attestors is queued in the DBQueue. All approval steps of the pending attestation cases are also recalculated by default. Approval steps that have already been approved remain approved, even if their attestor has changed. Recalculating attestors may take a long time depending on the configuration of the system environment and the amount of data to be processed. To optimize this processing time, you can specify the approval steps for which the attestors are to be recalculated.

To configure recalculation of the attestors

• In the Designer, set the **QER | Attestation | ReducedApproverCalculation** configuration parameter and select one of the following options as the value.

Option	Description
No	All approval steps are recalculated. This behavior also applies if the configuration parameter is not set.
	Advantage: All valid attestors are displayed in the approval process. The rest of the approval sequence is transparent.
	Disadvantage: Recalculating attestors may take a long time.
CurrentLevel	Only the attestors for the approval level that is currently to be edited

Table 27: Options for recalculating attestors



	Option	Description
		are recalculated. Once an approval level has been approved, the attestors are determined for the next approval level.
		Advantage: The number of approval levels to calculate is lower. Calculating the attestors may be faster.
		TIP:Use this option if performance problems occur in your environment in connection with the recalculation of attestors.
		Disadvantage: The originally calculated attestors are still displayed in the approval sequence for each subsequent approval step, even though they may no longer have approval authorization. The rest of the approval sequence is not correctly represented.
	NoRecalc	No recalculation of attestors. The previous attestors remain authorized to approve the current approval level. Once an approval level has been approved, the attestors are determined for the next approval level.
		Advantage: The number of approval levels to calculate is lower. Calculating the attestors may be faster.
		TIP: Use this option if performance problems occur in your environment in connection with the recalculation of attestors, even though the CurrentLevel option is used.
		Disadvantage: The originally calculated attestors are still displayed in the approval sequence for each subsequent approval step, even though they may no longer have approval authorization. The rest of the approval sequence is not correctly represented. Employees that are no longer authorized can approve the current approval level.
		In the worst-case scenario, the only attestors originally calculated here now have no access to One Identity Manager, for example, because they have left the company. The approval level cannot be approved.
		To see approval steps of this type through
		 Define a timeout and timeout behavior when you set up the approval workflows on the approval steps.
		- OR -
		 When setting up the attestation, assign members to the chief approval team. These members can access pending attestation cases at any time.
Deta	Detailed information about this topic	

- Properties of an approval step on page 50
- Chief approval team on page 23



Related topics

• Modifying approval workflows for pending attestation cases on page 95

Setting up multi-factor authentication for attestation

You can set up additional authentication for particularly security critical attestations, which requires every attestor to enter a security code for attesting. Define which attestation policies require this authentication in your attestation policies.

Use One Identity Manager One Identity Starling Two-Factor Authentication for multi-factor authentication. The authentication information required is defined in the subparameters under the **QER | Person | Starling** or the **QER | Person | Defender** configuration parameter. For detailed information about setting up multi-factor authentication, see the *One Identity Manager Authorization and Authentication Guide*.

To be able to use multi-factor authentication

- 1. Set up multi-factor authentication as described in the *One Identity Manager Authorization and Authentication Guide*.
- 2. In the Manager, select the attestation policies for which the multi-factor authentication will be used.
- 3. Enable the Approval by multi-factor authentication option.

Multi-factor authentication cannot be used for default attestation policies.

Once the **Approval by multi-factor authentication** option is set on an attestation policy, a security code is requested in each approval step of the approval process. This means that every employee who is determined to be an attestor for this attestation policy, must have a Starling 2FA token.

IMPORTANT: An attestation cannot be sent by email if multi-factor authentication is configured for the attestation policy. Attestation emails for such attestations produce an error message.

For detailed information about multi-factor authentication, see the One Identity Manager Web Portal User Guide.

Related topics

- General master data for attestation policies on page 25
- Attestation by mail on page 108



Prevent attestation by employee awaiting attestation

The attestation object can also be determined as the attestor in an attestation case. which means the employees to be attested can attest themselves. To prevent this, set the **QER** | **Attestation | PersonToAttestNoDecide** configuration parameter.

NOTE:

- Changing the configuration parameter only affects new attestation cases. Attestors are not recalculated for existing attestation cases.
- The configuration parameter setting also applies for fallback approvers; it does not apply to the chief approval team.
- If the **Approval by affected employee** option is set on an approval step, this configuration parameter has no effect.

To prevent employees from attesting themselves

• In Designer, set the **QER | Attestation | PersonToAttestNoDecide** configuration parameter.

This configuration parameter affects all attestation cases in which employees included in the attestation object or in object relations, are attestors at the same time. The following employees are removed from the group of attestors.

- Employees included in AttestationCase.ObjectKeyBase
- Employees included in AttestationCase.UID_ObjectKey1, ObjectKey2, or ObjectKey3
- Employees' main identities
- All subidentities of these main identities

If the configuration parameter is not set or if **Approval by affected employee** is enabled for the approval step, these employees can attest themselves.

Related topics

Properties of an approval step on page 50

Managing attestation cases

During attestation, you may find it necessary to assign someone else as default attestor responsible for the attestation because, for example, the actual attestor is absent. You may require additional information about an attestation object. The One Identity Manager offers different possibilities to intervene in an open attestation case.



Getting more information

An attestor has the option to gather more information about an attestation case. This ability does not, however, replace the granting or denying approval of an attestation case. There is no additional approval step required in the approval workflow to obtain the information.

Attestors can request information from any employee. The attestation case is put on hold while the query is pending. Once the employee requested has supplied the required information and the attestors have made an decision on the approval step, hold status is revoked. Attestors can recall a pending query at any time. The request is taken off hold. The query and answer are logged in the approval sequence and made available to the attestors.

NOTE: Hold status is revoked if the attestor who asked a question is removed as an approver. The queried employee does not have to answer and the attestation process proceeds.

Email notification to the employees involved can be sent using unanswered inquiries.

For detailed information about queries, see the One Identity Manager Web Portal User Guide

Detailed information about this topic

• Email notification: Notifications with questions on page 106

Appointing other attestors

Once an approval level in the approval workflow has been reached, the attestors at this level can appoint another employee to handle the approval. To do this, you have the options described below:

• Rerouting approvals

The attestor appoints another approval level to carry out attestations. To do this, set up a connection to the approval level in the approval workflow to which an approval decision can be rerouted.

Appointing additional attestors

The attestor appoints another employee to carry out the attestation. The other attestor must make an approval decision in addition to the known attestors. To do this, enable the **Additional approver possible** option in the approval step.

The additional attestor can reject the approval and return the attestation case to the original attestor. The original attestor is informed about this by email. The original attestor can appoint another additional attestor.

Delegate approval

The attestor appoints another employee with the attestation. This employee is added to the current approval step as the attestor. This employee then makes the approval



decision instead of the attestor who made the delegation. To do this, enable the **Approval can be delegated** option in the approval step.

The current attestor can reject the approval and return the attestation case to the original attestor. The original attestor can withdraw the delegation and delegate a different employee, for example, if the other attestor is not available.

Email notifications can be sent to the original attestors and the others.

Detailed information about this topic

- Connecting approval levels on page 54
- Editing approval levels on page 49
- Properties of an approval step on page 50

Related topics

- Email notification: Delegating attestations on page 105
- Email notification: Rejecting approvals on page 105
- Email notification: Notifications from additional attestors on page 106

Escalating an attestation case

Approval steps can be automatically escalated once the specified timeout is exceeded. The attestation case is presented again to another approval body. The attestation case can subsequently be processed again in the normal approval workflow.

To configure escalation of an approval step

- 1. Open the approval workflow in the Workflow Editor.
- 2. Add an additional approval level with one approval step for escalation.
- 3. Connect the approval step that is going to be escalated when the time period is exceeded with the new approval step. Use the connection point for escalation to do this.






Figure 3: Example of an approval workflow with escalation

4. Configure the behavior for the approval step to be escalated when it times out.

Table 28: Properties for escalation on timeout

Property Meaning

TimeOut (working hours)	Number of working hours to elapse after which the approval step is automatically granted or denied approval.
	The timeout is check every 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.
	The working hours of the respective approver are taken into account when the time is calculated.
	NOTE: Ensure that a state, county, or both is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about calculating employees' working hours, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .
	If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.
	If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.
	If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is



Property Meaning

	not recalculated.
Timeout	Action that is executed if the timeout expires.
behavior	 Escalation: The attestation case is escalated. The escalation approval level is called.

In the event of an escalation, email notifications can be sent to the new approvers and other employees.

Related topics

- Email notification: Demanding attestation
- Email notification: Escalation of attestation cases on page 105

Attestors cannot be established

You can specify a fallback approver if attestation cases cannot be approved because no attestors are available. An attestation case is then always assigned to the fallback approver for attestation if no attestor can be found in an approval step in the specified approval procedure.

To specify fallback approvers, define application roles and assign these to an approval step. Different attestation groups in the approval steps may also require different fallback approvers. Specify different application role for this, to which you can assign employees who can be determined as fallback approvers in the approval process. For more detailed information, see the *One Identity Manager Authorization and Authentication Guide*.

To specify fallback approvers for an approval step

• Enter the following data for the approval step.

Table 29: Approval step properties for fallback approvers

Pro	perty	Mea	ning
	PCICY		

Fallback approver	Application role whose members are authorized to approve attestation cases if an attestor cannot be determined through the approval procedure. Assign an application from the menu.
	To create a new application role, click 🗐. Enter the application role name and assign a parent application role. For detailed information, see the One Identity Manager Authorization and Authentication Guide.
	NOTE: The number of approvers is not applied to the fallback approvers. The approval step is considered approved the moment as soon as one fallback approver has approved the request.



Attestation sequence with fallback approvers

- 1. No attestor can be found for an approval step in an approval process. The attestation is assigned to all members of the fallback approver application role.
- 2. Once a fallback approver has approved an attestation case, it is presented to the attestors at the next approval level.

NOTE: You can specify in the approval step how many attestors are required for approval in this step. This limit is NOT valid for the chief approval team. The approval step is considered to be approved as soon as ONE fallback approver has approved the attestation.

3. The attestation case is aborted if no fallback approver can be found.

Fallback approvers can make approval decisions on attestation cases for all manual approval steps. Fallback approvals are not permitted for approval steps using the CD, EX, and WC approval procedures.

Related topics

- Editing approval levels on page 49
- Selecting attestors on page 56
- Attestation through chief approval team on page 89

Automatic approval on timeout

Attestation cases can be automatically granted or denied approval once a specified time period has been exceeded.



To configure automatic approval if the timeout expires

• Enter the following data for the approval step.

Table 30: Properties for automatic approval on timeout

Property	Meaning
TimeOut (working	Number of working hours to elapse after which the approval step is automatically granted or denied approval.
hours)	The timeout is check every 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.
	The working hours of the respective approver are taken into account when the time is calculated.
	NOTE: Ensure that a state, county, or both is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about calculating employees' working hours, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .
	If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.
	If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.
	If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.
Timeout	Action, which is executed if the timeout expires.
behavior	 Approved: The attestation case is approved in this approval step. The next approval level is called.
	 Deny: The attestation case is denied in this approval step. The approval level for denying is called.

When the approval decision for an attestation case is made automatically, other people can be notified by email.

Related topics

- Email notification: Granting or denying attestation cases on page 102
- Editing approval levels on page 49



Aborting an attestation case on timeout

Attestation cases can be automatically aborted once a specified time period has been exceeded. The abort takes place when either a single approval step or the entire approval process has exceeded the timeout.

To configure an abort after the timeout of a single approval step has been exceeded

• Enter the following data for the approval step.

Table 31: Properties of the approval step for abort on timeout

Property	Meaning
TimeOut (working	Number of working hours to elapse after which the approval step is automatically granted or denied approval.
hours)	The timeout is check every 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.
	The working hours of the respective approver are taken into account when the time is calculated.
	NOTE: Ensure that a state, county, or both is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about calculating employees' working hours, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .
	If more than one approver was found, the an approval decision for the approval step is not automatically made until the timeout for all approvers has been exceeded. The same applies if an additional approver has been assigned.
	If an approver delegated approval, the time point for automatic approval is recalculated for the new approver. If this approval is rejected, the time point for automatic approval is recalculated for the original approver.
	If an approver is queried, the approval decision must be made within the defined timeout anyway. The time point for automatic approval is not recalculated.
Timeout	Action, which is executed if the timeout expires.
behavior	 Abort: The approval step and, therefore, the attestation case, are canceled.



To configure abort on timeout for the entire approval process

• Enter the following data for the approval workflow.

Table 32: Properties of the approval workflow for abort on timeout

FI	operty	rieaning
abo	stem ort ays)	Number of days to elapse after which the approval workflow, and therefore the system, automatically ends the entire attestation procedure.

When an attestation case is aborted, other people can be notified by email.

Related topics

- Email notification: Aborting attestation cases
- Editing approval levels on page 49

Property Meaning

• Setting up approval workflows on page 48

Attestation through chief approval team

Sometimes, approval decisions cannot be made for attestation cases because an attestor is not available or does not have access to One Identity Manager tools. To complete these attestations, you can define a chief approval team whose members are authorized to intervene in the approval process at any time.

The chief approval team is authorized to approve, deny, or abort attestations in special cases or to appoint other attestors.

IMPORTANT:

- The four-eye principle can be broken like this because chief approval team members can make approval decisions for attestation cases at any time. Specify, on a custom basis, in which special cases the chief approval team may intervene in the approval process.
- The chief approval team is authorized to attest its own members. The configuration parameter setting **QER | Attestation | PersonToAttestNoDecide** does not apply to the chief approval team.
- In the approval step, you can specify how many attestors must make a decision on this approval step. This limit is not valid for the chief approval team. The approval decision is considered to be made as soon as one member of the chief approval team has decided on the attestation.

The chief approval team can approve attestations for all manual approval steps. The following applies:



- Chief approval team decisions are not permitted for approval steps using the CD, EX, and WC approval procedures.
- If a member of the chief approval team is also named as a regular attestor for an approval step, they can only make an approval decision for this step as a regular attestor.
- The chief approval team can also make an approval decision if a regular attestor has submitted a query and the attestation is in hold status.

To add members to the chief approval team

- 1. In the Manager, select the **Attestation | Basic configuration data | Chief approval team** category.
- 2. Select the Assign employees task.

In **Add assignments**, assign the employees who are authorized to approve all attestations.

TIP: In **Remove assignments**, you can remove the assignment of employees.

To remove an assignment

- Select the employee and double-click 𝔄.
- 3. Save the changes.

Related topics

Chief approval team on page 23



Attestation sequence

Once attestation is automatically or manually started, One Identity Manager creates an attestation case for each attestation object. Attestation cases record the entire attestation sequence. Each attestation step in the attestation case can be audit-proof reconstructed.

You can view the attestation cases in the navigation view under the **Attestation runs** | <**attestation policy**> menu item. This is where you can monitor the status of the attestation cases. Attestation cases that were not yet subject to approval are grouped under **Pending attestations**. You can see the attestation cases that have been closed by attestors or One Identity Manager grouped under **Completed attestations**.

NOTE: Attestation cases are edited in the Web Portal. For detailed information, see *One Identity Manager Web Portal User Guide*.

Attestation is complete when the attestation case has been granted or denied approval. You specify how to deal with granted or denied attestations on a company basis.

TIP: One Identity Manager provides various default attestation procedures for different data situations and default attestation procedures. If you use these default attestation procedures, you can configure how you deal with denied attestations.

For more information, see Default attestation and withdrawal of entitlements on page 112.

Starting attestation

There are two ways for you to add attestation cases in the One Identity Manager. You can trigger attestation through a scheduled task or start selected objects individually.

Prerequisite

• The attestation policy for this attestation is set.

To start attestation using a scheduled task

- 1. In the Manager, select **Attestation | Attestation policies**.
- 2. Select the attestation policy in the result list and run **Change master data**.
- 3. Enable the schedule entered in **Calculation schedule**.



- a. In the navigation view, select **Basic configuration data | Schedules**.
- b. Select the schedule in the result list and run Change master data.
- c. Set Enabled.
- d. Save the changes.

To start attestation for the selected objects

- 1. In the Manager, select the **Attestation | Attestation policies** category.
- 2. Select the attestation policy in the result list. Select the **Change master data** task.
- 3. Select the **Run attestation cases for single objects...** task.

This opens a separate window.

- 4. In the **Attestation** column, select every object for which attestation is to be run.
- 5. Click Run.

Attestation cases are generated for the selected attestation objects. As soon as DBQueue Processor has processed the task, you will see the newly created attestation cases in the navigation view under the **Attestation runs | <attestation policy> | Attestation runs | <year> | <month> | <day> | Pending attestations menu item.**

6. Click Close.

NOTE: Under certain circumstances, old, closed attestation cases are deleted from the One Identity Manager database when new attestation cases are added.

For more detailed information about configuring schedules, see the One Identity Manager Operational Guide.

Detailed information about this topic

- General master data for attestation policies on page 25
- Schedules on page 17

Related topics

- Running attestation for single objects on page 31
- Determining the responsible attestors on page 78
- Deleting attestation cases on page 97

Additional tasks for attestation cases

Once you have started attestation for an attestation policy, you can monitor the attestation case in One Identity Manager. The task view contains different forms with which you can run the following tasks.



Attestation case overview

The overview form supplies you with the most important information about an attestation case. Here you can see the time by which an attestation case will be processed, depending on the processing time. One Identity Manager does not stipulate which actions are carried out if processing times out. Define your own custom actions or evaluations to deal with this situation.

To obtain an overview of an attestation case

- In the Manager, select the Attestation | Attestation runs | <attestation policy> | Attestation runs | <year> | <month> | <day> category.
- 2. Select the **Pending attestations** or the **Completed attestations** filter.
- 3. Select an attestation case from the result list.
- 4. Select **Attestation case overview**.

Approval sequence

For pending attestation cases, see the current status of the approval process. The approval sequence is shown as soon as the DBQueue Processor has determined the attestors for the first approval step. In the approval workflow, you can view the approval sequence, the results of each approval step, and the attestors found. If the approval procedure could not find an attestor, the attestation case is canceled by the system.

To display the approval sequence of a pending attestation case

- In the Manager, select the Attestation | Attestation runs | <attestation policy> | Attestation runs | <year> | <month> | <day> | Pending attestations category.
- 2. Select an attestation case from the result list.
- 3. Select the **Approval sequence** task.

Each approval level of an approval workflow is represented by a special control. The attestors responsible for a particular approval step are shown in a tooltip. Pending attestation questions are also shown in tooltips. These elements are shown in color, the color code reflecting the current status of the approval level.

Table 33: Meaning of the colors in an approval sequence(in order of decreasing importance)

Color Meaning

Blue	This approval level is currently being processed.
Green	This approval level has been granted approval.



	Color	Meaning
	Red	This approval level has been denied approval.
	Yellow	This approval level has been deferred due to a question.
	Gray	This approval level has not (yet) been reached.

Attestation history

The attestation history displays each step of an attestation case. Here you can follow all the approvals in the approval process in a chronological sequence. The attestation history is displayed for pending and closed attestations.

To display an attestation case in the attestation history

- 1. In the Manager, select the **Attestation | Attestation runs | <attestation** policy> | **Attestation runs | <year> | <month> | <day>** category.
- 2. Select the **Pending attestations** or the **Completed attestations** filter.
- 3. Select an attestation case from the result list.
- 4. Select the **Attestation history** report.

These elements are colored. The color code reflects the status of the approval steps.

Table 34: Meaning of colors in the attestation history
--

Color	Meaning
Yellow	Attestation case set up.
Green	Attestor has approved.
Red	Attestor has denied.
	Attestation has been escalated.
	Approver has recalled the approval decision
Gray	Attestation has been aborted.
	Case has been assigned to an extra attestor.
	Additional attestor has withdrawn approval decision.
	Approval has been delegated.
	New attestor has withdrawn the delegation.
Orange	Attestor has a question.
	The query has been answered.
	Query was aborted due to change of approver



Color Meaning

Blue Approver has rerouted approval. The approval step was reset automatically.

Modifying approval workflows for pending attestation cases

When approval workflows are changed, a decision must be made as to whether these changes should be applied to pending attestation cases. Configuration parameters are used to define the desired procedure.

Scenario: Another approval workflow was stored with the approval policy

The newly stored workflow is only used in new requests. If changes have been made to the approval workflow in an approval policy, any pending approval procedures are continued by default with the original workflow. The newly stored workflow is only used in new attestation cases. You can configure different behavior.

To specify how to handle pending attestation cases

- In the Designer, enable the **QER | Attestation | OnWorkflowAssign** configuration parameter and select one of the following values.
 - **CONTINUE**: Ongoing approval processes are continued with the originally applicable workflow. The newly stored workflow is only used in new attestation cases.

This behavior also applies if the configuration parameter is not set.

- **RESET**: In ongoing approval processes, all approval decisions already taken are reset. The approval processes are restarted with the newly stored workflow. The attestation cases are run through the approval process again.
- ABORT: Ongoing approval processes are aborted. All pending attestation cases are closed. The next automatic or manual start of the attestation uses the new approval workflow.

A working copy of the originally applicable workflow is saved. The working copy is retained as long as it is used in ongoing approval processes. All unused working copies are regularly deleted using the **Maintenance approval workflows** schedule.

Scenario: A change was made to an approval workflow in use

If changes have been made to an approval workflow that is being used in pending attestation cases, any pending approval processes are continued by default with the original workflow. The changes to the approval workflow are only implemented for new attestation cases. You can configure different behavior.



To specify how to handle pending attestation cases

- In the Designer, enable the **QER | Attestation | OnWorkflowUpdate** configuration parameter and select one of the following values.
 - **CONTINUE**: Ongoing approval processes are continued with the originally applicable approval workflow. The changes to the approval workflow are only implemented for new attestation cases.

This behavior also applies if the configuration parameter is not set.

- **RESET**: In ongoing approval processes, all approval decisions already taken are reset. The approval processes are restarted with the changed approval workflow. The attestation cases are run through the approval process again.
- **ABORT**: Ongoing approval processes are aborted. All pending attestation cases are closed. The next automatic or manual start of the attestation uses the changed approval workflow.

A working copy of the approval workflow that contains the original version is saved. This working copy is retained as long as it is used in ongoing approval processes. All unused working copies are regularly deleted using the **Maintenance approval workflows** schedule.

Related topics

• Determining the responsible attestors on page 78

Closing attestation cases for deactivated employees

Pending attestation cases must still be processed even if they have permanently deactivated in the meantime. This is not required very often because the affected employee may have, for example, left the company. In this case, you can use the option to close an employee's pending attestation cases automatically, if the employee is permanently disabled.

To close attestation cases automatically

• In the Designer, set the **QER | Attestation | AutoCloseInactivePerson** configuration parameter.

The configuration parameter only applies if the employee to be attested is deactivated after the attestation case was created.

The configuration parameter does not apply if the employee is temporarily deactivated.

TIP: Write a corresponding condition for finding the attestation object on the attestation policies to prevent attestation cases being created for deactivated employees. For more information, see General master data for attestation policies on page 25.



Deleting attestation cases

The AttestationCase table expands very quickly when attestation is performed regularly. To limit the number of attestation cases in the One Identity Manager database, you can delete obsolete, closed attestation cases from the database. The attestation case properties are logged and then the attestation cases are deleted. The same number of attestation cases remain in the database as are specified in the attestation policy. For more detailed information about logging data changes tags, see the One Identity Manager Configuration Guide.

NOTE: Ensure that the logged request procedures are archived for audit reasons. For more detailed information about the archiving process, see the One Identity Manager Data Archiving Administration Guide.

Prerequisites

- The **Common | ProcessState | PropertyLog** configuration parameter is enabled.
- The attestation policy is enabled.

To delete attestation cases automatically

- 1. Set the Log changes when deleting option on at least three columns in the AttestationCase table.
 - a. In Designer, select the Database schema | Tables | AttestationCase category.
 - b. Select the **Show table definition** task.

This opens the Schema Editor.

- c. Select a column in the Schema Editor.
- d. In the edit view of the schema editor, select the **More** tab.
- e. Set the option Log changes when deleting.
- f. Repeat steps (c) to (e) for all columns that are to be recorded on deletion. There must be at least three.
- q. Click on **Commit to database** and save the changes.

The changes take effect as soon as the DBQueue Processor has performed the calculation tasks.

- 2. Set the Log changes when deleting option on at least three columns in the AttestationHistory table.
 - a. In Designer, select the **Database schema** | **Tables** | AttestationHistory category.
 - b. Repeat the steps 1(b) to 1(h) for the AttestationHistory table.
- 3. Enter the number of obsolete cases in the attestation policies.
 - a. In the Manager, select the **Attestation | Attestation policies** category.
 - b. Select the attestation policy in the result list whose attestation cases should be



deleted.

- c. Select the Change master data task.
- d. In the **Obsolete tasks limit** field, enter a value greater than 0.
- e. Save the changes.

TIP: If you want to prevent attestation cases being deleted for certain attestation policies, enter the value **0** for the obsolete task limit for these attestation policies.

Attestation cases are deleted once

- A new attestation is started for an attestation policy.
 - OR -
- An attestation policy is disabled.

One Identity Manager tests how many closed attestation cases exists in the database for each attestation object of this attestation policy. If the number is more than the number of obsolete attestation cases:

• The attestation case properties and their approval sequence are recorded.

All columns are recorded, which are marked for logging on deletion.

• The attestation cases are deleted.

The same number of attestation cases remain in the database as are specified in the obsolete tasks limit.

NOTE: Closed attestation cases are also deleted in the case of disabled attestation policies if the **Common | ProcessState | PropertyLog** configuration parameter is not set. In this case, the deleted attestation cases are not logged.

Related topics

General master data for attestation policies on page 25

Notifications in the attestation process

In an attestation process, various email notifications can be sent to attestors and other employees. The notification procedure uses mail templates to create notifications. The mail text in a mail template is defined in several languages. This ensures that the language of the recipient is taken into account when the email is generated. Mail templates are supplied in the default installation with which you can configure the notification procedure.

Messages are not sent to the chief approval team by default. Fallback approvers are only notified if not enough approvers could be found for an approval step.



To use notification in the request process

- 1. Ensure that the email notification system is configured in One Identity Manager. For more detailed information, see the *One Identity Manager Installation Guide*.
- 2. In the Designer, set the **QER | Attestation | DefaultSenderAddress** configuration parameter and enter the sender address used to send the email notifications.
- 3. Ensure that all employees have a default email address. Notifications are sent to this address. For more detailed information, see the *One Identity Manager Identity Management Base Module Administration Guide*.
- 4. Ensure that a language can be determined for all employees. Only then can they receive email notifications in their own language. For more detailed information, see the *One Identity Manager Identity Management Base Module Administration Guide*.
- 5. Configure the notification procedure.

Related topics

Custom mail templates for notifications on page 34

Demanding attestation

When a new attestation case is made, the attestor is notified by mail. Demands for attestation can be configured separately for each approval step.

Prerequisite

• The **QER** | **Attestation** | **MailTemplateIdents** | **RequestApproverByCollection** configuration parameter is not set.

To set up the notification procedure

• On the Mail templates tab of the approval step, enter the following data:

Mail template request: Attestation - approval required

TIP: To allow approval by email, select the **Attestation - approval required (by email)** mail template.

NOTE: You can schedule demands for attestation to send a general notification if there are attestations pending. This replaces single demands for attestation at each approval step.

Related topics

- Email notification: Scheduling attestation demands on page 101
- Attestation by mail on page 108
- Editing approval steps on page 50



Reminding attestors

If an attestor has not made a decision by the time the reminder timeout expires, notification can be sent by email as a reminder. The attestors work time applies to the time calculation.

Prerequisite

• The **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter is not set.

To set up the notification procedure

- -

• Enter the following data for the approval step.

.

Table 35: Properties of the approval step for notification

	Property	Meaning
	Reminder interval (hours)	Number of working hours to elapse after which the attestor is notified by mail that there are still pending attestation cases for attestation.
		The reminder interval is set to 30 minutes, by default. To change this interval, modify the Checks reminder interval and timeout of attestation cases schedule.
		NOTE: Ensure that a state, county, or both is entered into the employee's master data for determining the correct working hours. If this information is missing, a fallback is used to calculate the working hours. For more detailed information about calculating employees' working hours, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .
		If more than one attestor was found, each attestor will be notified. The same applies if an additional attestor has been assigned.
		If an attestor delegated the approval, the time point for reminding the delegation recipient is recalculated. The delegation recipient and all the other attestors are notified. The original attestor is not notified.
		If an attestor has made an inquiry, the time point for reminding the queried employee is recalculated. As long as the inquiry has not been answered, only this employee is notified.
	Mail template reminder	Select the Attestation - Remind approver mail template. TIP: To allow approval by email, select the Attestation - remind approver (by email) mail template.

NOTE: You can schedule demands for attestation to send a general notification if there are attestations pending. This replaces single demands for attestation at each approval step.



Related topics

- Email notification: Scheduling attestation demands on page 101
- Attestation by mail on page 108
- Editing approval steps on page 50

Scheduling attestation demands

Attestors can be regularly notified of attestation cases that are pending. These regular notifications replace the individual prompts and attestation reminders that are configured in the approval step.

To send regular notifications about pending attestations

1. Enable the **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter in the Designer.

By default, a notification is sent with the **Attestation - pending requests for approver** mail template.

TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter.

2. In the Designer, configure and enable the **Inform approver about pending attestations** schedule.

For detailed information, see One Identity Manager Operational Guide.

Reminding attestors about attestation objects

The hierarchical role manager and those responsible for system entitlements or system roles can view all pending attestation cases for this object in the Web Portal. If necessary, they can also send reminders to attestors of selected attestation objects.

To send notification about a specific attestation object

• In the Designer, set the **QER | Attestation | MailTemplateIdents | RemindApproverByObject** configuration parameter.

By default, notification is sent using the **Attestation - remind approver of all open object attestations** template.

TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter.

To send notifications user the Web Portal. For detailed information, see *One Identity Manager Web Portal User Guide*.



Granting or denying attestation cases

When an attestation case is granted approval or denied it, other employees receive notification. Notification may occur after approval or denial of a single approval step or once the entire approval process is complete. You can specify the recipient of the notification as required by the company.

Attestation cases can be automatically granted or denied approval once a specified time period has been exceeded. Notification is sent in the same way in this case.

To set up the notification procedure

- 1. Create custom mail templates for sending notification if attestation cases have been granted or denied approval.
- 2. Create company specific processes for notifications.
- 3. If notification should be sent immediately after an approval decision is made for a single approval step, enter the following data on the **Mail templates** tab of the approval step.

Property	Meaning	
Mail template approved	Mail template to be used for email notification when an approval step is approved.	
Mail template denied	Mail template to be used for email notification when an approval step is denied.	

Table 36: Properties of the approval step for notification

- OR -

If notification should be sent after the entire approval procedure is complete, enter the following data in the approval policy.

Table 37: Properties of an approval policy for notifications

Property	Meaning	
Mail template approved	Mail template to be used for email notifications when an attest- ation case is approved.	
Mail template denied	Mail template to be used for email notifications when an attest- ation case is denied.	

Detailed information about this topic

- Custom mail templates for notifications on page 34
- Custom notification processes on page 40



- Editing approval steps on page 50
- Approval policies for attestations on page 42

Notifying delegates

If required, a delegator can receive notifications if the recipient of the delegation has made an approval decision in an attestation case. A notification is sent once an employee has been determined as an attestor due to delegation and has made an approval decision for the attestation case.

To send a notification when the employee who was delegated an approval approves or denies the attestation.

• In the Designer, set the **QER | ITShop | Delegation | MailTemplateIdents | InformDelegatorAboutDecisionAttestation** configuration parameter.

By default, a notification is sent with the **Delegation - inform delegator about decided attestation** mail template.

TIP: To use custom mail templates for emails of this type, change the value of the configuration parameter.

Delegations are taken into account in the following default approval procedures.

Delegation of	Approval procedure
Department responsibilities	DM, ED
Cost center responsibilities	РМ
Location responsibilities	LM
Business role responsibilities	MO, OM, RM, RR
Employee responsibilities	CM, EM
Memberships in business roles	OR
Memberships in application roles	AA, AD, AL, AN, AO, AP, AR, AS, AT, AY, EN, EO, OA, SO

Table 38: Delegation relevant default approval procedures

Example

Jon Blogs is responsible for the R1 business role. He delegates his responsibility for the business role to Clara Harris. Clara Harris is herself responsible for R2 business



role.

A member of R1 business role is to be attested. Jon Bloggs is established as an attestor through the **OM - Manager of a specific role** approval process. The attestation case is assigned to Clara Harris for approval through delegation. Jon Blogs is notified as soon as Clara Harris has made her approval decision for the attestation case.

A member of R2 business role is to be attested. Clara Harris is established as an attestor through the **OM** - **Manager of a specific role** approval process. No notification is sent because Clara Harris does not make the approval decision due to delegation.

For more detailed information about delegating responsibilities, see the *One Identity Manager IT Shop Administration Guide*.

Related topics

- Default approval procedures on page 57
- Notifications from additional attestors on page 106

Aborting attestation cases

Email notifications can be sent to other employees when an attestation case is aborted. You can specify the recipient of the notification as required by the company.

To set up the notification procedure

- 1. Create custom mail templates for sending notification if attestation cases have been aborted.
- 2. Create company specific processes for notifications.
- 3. Enter the following data for the approval policy:

Mail template aborted: Mail template to be used for email notifications when an attestation case is aborted.

Detailed information about this topic

- Custom mail templates for notifications on page 34
- Custom notification processes on page 40



104

Escalation of attestation cases

Email notifications can be sent to the attestation policy's owner when an attestation case is escalated.

To set up the notification procedure

1. On the **Mail templates** tab of the approval step, enter the following data:

Mail template escalation: Attestation - Escalation

2. Assign an owner to the attestation policies.

Related topics

- Escalating an attestation case on page 83
- General master data for attestation policies on page 25
- Editing approval steps on page 50

Delegating attestations

If, in an approval step, other attestors can be authorized to make the approval decision, the additional attestors can be prompted to approve by email. The same applies if the attestation can be delegated.

To set up the notification procedure

• On the Mail templates tab of the approval step, enter the following data:

Mail template delegation: Attestation - Delegated/additional approval

TIP: To enable approval by email, select the **Attestation** - **delegated/additional approval (by email)** mail template.

Related topics

- Attestation by mail on page 108
- Appointing other attestors on page 82
- Editing approval steps on page 50

Rejecting approvals

The original attestor must be notified if an additional attestor or employee to whom an attestation has been delegated refuses the approval decision.



To set up the notification procedure

• On the Mail templates tab of the approval step, enter the following data:

Mail template rejection: Attestation - Reject approval

TIP: If you allow approval by email, select the mail template **Attestation - reject approval (by mail)**.

Related topics

- Attestation by mail on page 108
- Appointing other attestors on page 82
- Editing approval steps on page 50

Notifications with questions

Employees can be notified when a question about an attestation is asked. Similarly, the attestors can also be notified as soon as the question is answered.

To send a notification when an attestor asks a question

• In the Designer, enable the **QER | Attestation | MailTemplateIdents | QueryFromApprover** configuration parameter.

A notification is sent by default with the **Attestation - question** mail template.

To send a notification to the attestor when the queried employee answers a question

• In the Designer, set the **QER | Attestation | MailTemplateIdents | AnswerToApprover** configuration parameter.

A notification is sent by default with the **Attestation - answer** mail template.

TIP: To use custom mail templates for emails of this type, change the value of the configuration parameter.

Notifications from additional attestors

The original attestor can be notified when an additional attestor or an employee who has been delegated an attestation has granted or denied the attestation. This mail is send the moment the approval step has been decided.



106

To send a notification when the additional attestor approves or rejects the attestation

• In the Designer, set the **QER | Attestation | MailTemplateIdents | InformAddingPerson** configuration parameter.

A notification is sent by default with the **attestation - approval of added step** mail template.

To send a notification when the employee who was delegated an approval approves or denies the attestation.

• In the Designer, set the **QER | Attestation | MailTemplateIdents | InformDelegatingPerson** configuration parameter.

A notification is sent by default with the **attestation - approval of delegated step** mail template.

TIP: To use custom mail templates for emails of this type, change the value of the configuration parameter.

Link for verifying new external users

If a new user logs in to the Web Portal or new external employees need to be certified, they receive an email containing a link to the Password Reset Portal. Using the link, employees verify their contact email address, set a password and password questions.

To send notification with a verification link

• In the Designer, set the **QER | Attestation | MailTemplateIdents | NewExternalUserVerification** configuration parameter.

By default, notification is sent using the **Attestation - new external user verification link** mail template.

TIP: To use something other than the default mail template for these notifications, change the value of the configuration parameter.

Detailed information about this topic

- User attestation and recertification on page 121
- Self-registration of new users in the Web Portal on page 124
- Adding new employees using a manager or employee administrator on page 126

Default mail templates

One Identity Manager supplies mail templates by default. These mail templates are available in English and German. If you require the mail body in other languages, you can



107

add mail definitions for these languages to the default mail template.

To edit a default mail template

• In the Manager, select the **Attestation | Basic configuration data | Mail templates | Predefined** category.

Related topics

• Custom mail templates for notifications on page 34

Attestation by mail

To provide attestors who are temporarily unable to access One Identity Manager tools with the option of making attestation case decisions, you can set up attestation by email. In this process, attestors are notified by email when an attestation case is pending their approval. Approvers can use the links in the email to make approval decisions without having to connect to the Web Portal. This generates an email that contains the approval decision and in which attestors can state the reasons for their approval decision. This email is sent to a central Microsoft Exchange mailbox. One Identity Manager checks this mailbox regularly, evaluates the incoming emails and updates the status of the attestation cases correspondingly.

IMPORTANT: An attestation cannot be sent by email if multi-factor authentication is configured for the attestation policy. Attestation emails for such attestations produce an error message.

Prerequisites

- 1. The Microsoft Exchange environment is configured with:
 - Microsoft Exchange Client Access Server version 2007, Service Pack 1 or higher
 - Microsoft Exchange Web Service .NET API Version 1.2.1, 32-bit
- The user account used by One Identity Manager Service to register with the Microsoft Exchange environment requires full access to the mailbox given in the QER | Attestation | MailApproval | Inbox configuration parameter.
- 3. The **QER | Attestation | MailTemplateIdents | RequestApproverByCollection** configuration parameter is not set.

To set up attestation by email

- 1. In the Designer, set the **QER | Attestation | MailApproval | Inbox** configuration parameter and enter the mailbox to which the approval mails are to be sent.
- 2. Set up mailbox access.



a. By default, One Identity Manager uses the One Identity Manager Service user account to log in to the Microsoft Exchange Server and access the mailbox.

- OR -

b. You enter a separate user account for logging in to the Microsoft Exchange Server for mailbox access. Enabled the following configuration parameters to do this.

Table 39: Configuration parameters for logging in to MicrosoftExchange Server

Configuration parameter	Meaning
QER Attestation MailApproval Account	Name of the user account.
QER Attestation MailApproval Domain	User account's user account.
QER Attestation MailApproval Password	Password of the user account.

3. In the Designer, set the **QER | Attestation | MailTemplateIdents | ITShopApproval** configuration parameter.

The mail template used to create the attestation mail is stored with this configuration parameter. You can use the default mail template or add a custom mail template.

TIP: To use a company-specific mail template for attestation mails, change the value of the configuration parameter. In this case, also change the VI_MailApproval_ProcessMail script.

4. Assign the following mail templates to the approval steps.

Table 40: Mail templates for approval by mail

Property	Mail template
Mail template request	Attestation - approval required (by mail)
Mail template reminder	Attestation - remind approver (by mail)
Mail template delegation	Attestation - delegated/additional approval (by mail)
Mail template rejection	Attestation - reject approval (by mail)

5. In the Designer, configure and enable the **Processes attestation mail approvals** schedule.

Based on this schedule, One Identity Manager regularly checks the mailbox for new attestation mails. The mailbox is checked every 15 minutes. You can change how frequently it checks, by altering the interval in the schedule as required.



To clean up a mail box

• In the Designer, set the **QER | Attestation | MailApproval | DeleteMode** configuration parameter and select one of the following values.

	-
Value	Method
HardDelete	The processed email is immediately deleted.
MoveToDeletedItems	The processed email is moved to the Deleted objects mailbox folder.
SoftDelete	The processed email is moved to the Active Directory recycling bin and can be restored if necessary.

Table 41: Mailbox cleanup

NOTE: If you use the MoveToDeletedItems or SoftDelete cleanup method, you should empty the **Deleted objects** folder and the Active Directory recycling bin on a regular basis.

Related topics

- Processing attestation mails on page 110
- Custom mail templates for notifications on page 34
- Demanding attestation on page 99
- Reminding attestors on page 100
- Delegating attestations on page 105
- Rejecting approvals on page 105
- Setting up multi-factor authentication for attestation on page 80

Processing attestation mails

The **Processes attestation mail approvals** schedule starts the VI_Attestation_ Process Approval Inbox process. This process runs the VI_MailApproval_ProcessInBox script, which searches the mailbox for new attestation mails and updates the attestation cases in the One Identity Manager database. The contents of the attestation mail are processed at the same time.

NOTE: The validity of the email certificate is checked with the VID_ValidateCertificate script. You can customize this script to suit your security requirements. Take into account that this script is also used for attestations by email.

If an self-signed root certification authority is used, the user account under which the One Identity Manager Service is running, must trust the root certificate.

TIP: VI_MailApproval_ProcessInBox finds the Exchange Web Service URL, which uses



110

AutoDiscover through the given mailbox as default. This assumes that the AutoDiscover service is running.

If this is not possible, enter the URL in the QER\Attestation\MailApproval\ExchangeURI configuration parameter.

Attestation mails are processed with the VI_MailApproval_ProcessMail script. The script finds the relevant approval decision, sets the **Approved** option if approval is granted, and stores the reason for the approval decision with the attestation cases. The attestor is found through the sender address. Then the attestation mail is removed from the mailbox depending on the selected cleanup method.

NOTE: If you use a custom mail template for the attestation mail, check the script and modify it as required. Take into account that this script is also used for approval decisions for IT Shop requests by email.



Default attestation and withdrawal of entitlements

One Identity Manager provide various default attestation procedures for different data situations and default attestation procedures.

Data situations for default attestations:

- System entitlements owned by an employee
- System entitlements assigned to system entitlements
- System entitlements assigned to hierarchical roles
- System roles assigned to an employee
- Company resources assigned to system roles
- System roles assigned to hierarchical roles
- Business and application role memberships
- Employee master data for a new One Identity Manager user
- Employee master data for an existing One Identity Manager user

The attestation polices required for attesting employee master data are also supplied by default. You can also use the default supplied attestation policies without modifying them. The prerequisites and the attestation sequence for employee data are described in User attestation and recertification.

You can set up attestation policies easily in the Web Portal using default attestation procedures for other data situations. You can also use the default attestation policies supplied without customizing them. Furthermore, you can configure how to deal with denied attestations that are based on these default attestation procedures. If your specific data situation allows, denied entitlements can be removed by One Identity Manager following the attestation.

To remove denied permissions automatically

- 1. In the Designer, set the **QER | Attestation | AutoRemovalScope** configuration parameter and the configuration subparameters.
- 2. If the entitlements were obtained through IT Shop, specify whether these requests should be unsubscribed or canceled. To do this, set the **QER | Attestation |**



AutoRemovalScope | PWOMethodName configuration parameter and select a value.

- **Abort**: Requests are aborted. In this case, they do not go through a cancelation workflow. The requested entitlements are withdrawn without additional checks.
- **Unsubscribe**: Requests are unsubscribed. They go through the cancelation workflow defined in the approval policies. Withdrawal of the entitlement can thus be subjected to an additional check.

If the cancelation is denied, the entitlement is not withdrawn even though the attestation has been denied.

If the configuration parameter is not set, the requests are aborted.

IMPORTANT: If role memberships or system roles are removed from an employee they lose the unapproved entitlement. They also lose all other company resources inherited through this role. These may be other system entitlements or account definitions. If necessary, system entitlements are removed and company resources are deleted from the employee.

Check whether your data situation allows automatic withdrawal of entitlements before you enable configuration parameters under **QER | Attestation | AutoRemovalScope**.

Automatic removal of entitlements is triggered by an additional approval step with the EX approval procedure in the default approval workflows.

Attestation sequence with subsequence withdrawal of denied entitlements:

- 1. Attestation is carried out using a default attestation procedure.
- 2. The attestor denies attestation. The approval step is not granted approval and approval is passed on the next approval level with the EX approval procedure.
- 3. The approval step triggers the AUTOREMOVE event. This runs the VI_Attestation_ AttestationCase_AutoRemoveMembership process.
- 4. The process runs the VI_AttestationCase_RemoveMembership script. This removes the affected entitlement depending on which configuration parameters are set.
- 5. The script sets the approval step status to **Denied**. This means the entire attestation case is finally denied.
- 6. Tasks to recalculate inheritance are entered in the DBQueue.

Detailed information about this topic

- System entitlements attestation on page 114
- System role attestation on page 116
- Application role attestation on page 119
- Business role attestation on page 119



System entitlements attestation

Installed modules: Target System Base Module

When you use the **System entitlement memberships attestation** default attestation policy or have set up attestation policies with the **System entitlement memberships attestation** default attestation procedure, you can configure automatic removal of system entitlements through the **QER | Attestation | AutoRemovalScope | GroupMembership** configuration parameter. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the system entitlement.

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope GroupMembership RemoveDirect	Direct membership of the user account in the system entitle- ment, is removed.
QER Attestation AutoRemovalScope GroupMembership RemovePrimaryRole	If membership in the system entitlement was inherited through a primary role, the role is withdrawn from the employee. This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope GroupMembership RemoveRequestedRole	If membership of the system entitlement was inherited through a requested role, the role request is canceled or unsubscribed. This removes all indirect assignments obtained by the employee through this role. Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.
QER Attestation AutoRemovalScope GroupMembership RemoveDelegatedRole	If membership in the system entitlement was inherited through a delegated role, delegation of this role is canceled or unsub- scribed. This removes all indirect assignments obtained by the employee through this role. Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.
QER Attestation	If membership of the system entitlement was requested

Table 42: Effect of configuration parameters when attestation denied



Configuration parameter	Effect when set
AutoRemovalScope GroupMembership RemoveRequested	through the IT Shop, the request is canceled or unsubscribed.
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.
QER Attestation AutoRemovalScope GroupMembership RemoveSystemRole	System roles incorporating the system entitlements are withdrawn from the employee.
	This removes all indirect assignments obtained by the employee through this system role.
	This configuration parameter is only available if the System Roles Module is installed.
QER Attestation AutoRemovalScope GroupMembership RemoveDirectRole	The system entitlement assignment to hierarchical roles is removed and
	Therefore removes the system entitlement assignment to all user accounts whose associated employees inherit assignments from these roles.
	IMPORTANT: Employees whose attestation has been approved can lose the system entitlement through this.
	Check the side-effects of this configuration parameter in your situation before you set it.

When you use the **Attestation of assignments to system entitlements** default attestation policy or have set up attestation policies with the **Attestation of assignments to system entitlements** default attestation procedure, you can configure automatic removal of system entitlements through the **QER | Attestation | AutoRemovalScope | UNSGroupInUNSGroup** configuration parameter.

Table 43: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set	
QER Attestation AutoRemovalScope UNSGroupInUNSGroup RemoveDirect	Assignment of the system entitlement to a system entitlement is removed.	

You can configure automatic withdrawal of system entitlement assignments to hierarchical roles, if you use the following default attestation policies or procedures:

- Attestation of system entitlement assignments to department
- Attestation of system entitlement assignments to cost centers
- Attestation of system entitlement assignments to locations
- Attestation of system entitlement assignments to business roles

Enabled the following configuration parameters to do this.



Configuration parameter	Effect when set
QER Attestation AutoRe- movalScope Depart- mentHasUNSGroup RemoveDirect	The assignment of the system entitlement to a department is removed.
	Therefore the system entitlement is removed from all employees that inherit assignments from this department.
QER Attestation AutoRe- movalScope ProfitCen- terHasUNSGroup RemoveDirect	The assignment of the system entitlement to a cost center is removed.
	Therefore the system entitlement is removed from all employees that inherit assignments from this cost center.
QER Attestation AutoRe- movalScope LocalityHasUNSGroup RemoveDirect	The assignment of the system entitlement to a location is removed.
	Therefore the system entitlement is removed from all employees that inherit assignments from this location.
QER Attestation AutoRe- movalScope OrgHasUNSGroup RemoveDirect	The assignment of a system entitlement to a business role is removed.
	Therefore the system entitlement is removed from all employees that inherit assignments from this business role.

Table 44: Effect of configuration parameters when attestation denied

System role attestation

Installed modules: System Roles Module

If you use the **System role membership attestation** default attestation policy or have set up attestation policies with the **System entitlement memberships attestation** default attestation procedure, you can configure automatic removal of system roles through the **QER | Attestation | AutoRemovalScope | ESetAssignment** configuration parameter. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the system role.

Configuration parameter	Effect when set
QER Attestation	Direct membership in the system role is removed.
AutoRemovalScope	This removes all indirect assignments obtained by the



Configuration parameter	Effect when set
ESetAssignment RemoveDirect	employee through this system role.
QER Attestation AutoRemovalScope ESetAssignment RemovePrimaryRole	If the system role was inherited through a primary role, the role is withdrawn.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope	If the system role was inherited through a requested role, the role request is canceled or unsubscribed.
ESetAssignment RemoveRequestedRole	This removes all indirect assignments obtained by the employee through this role.
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.
QER Attestation AutoRemovalScope	If the system role was inherited through a delegated role, the delegation of this role is canceled or unsubscribed.
ESetAssignment RemoveDelegatedRole	This removes all indirect assignments obtained by the employee through this role.
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.
QER Attestation AutoRemovalScope ESetAssignment RemoveRequested	If the system role was requested through the IT Shop, the request is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this system role.
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.
QER Attestation AutoRemovalScope ESetAssignment RemoveDirectRole	The system role assignment to hierarchical roles is removed.
	This removes the system role assignment to all employees, which inherits assignments from these roles.
	IMPORTANT: Employees whose attestation has been approved can lose the system role through this.
	Check the side-effects of this configuration parameter in your situation before you set it.



If you use the **System role entitlement assignment attestation** default attestation policy or have set up attestation policies with the **System role entitlement assignment attestation** default attestation procedure, you can configure automatic removal of the assignments through the **QER | Attestation | AutoRemovalScope | ESetHasEntitlement** configuration parameter.

Table 46: Effect of configuration parameters when attestation denied

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope	Assignment of the company resource to
ESetHasEntitlement RemoveDirect	a system role is removed.

You can configure automatic withdrawal of system role assignments to hierarchical roles, if you use the following default attestation policies or procedures:

- Department system role assignment attestation
- Cost center system role assignment attestation
- · Location system role assignment attestation
- Business role system role assignment attestation

Enabled the following configuration parameters to do this.

Configuration parameter	Effect when set
QER Attestation AutoRe- movalScope DepartmentHasESet RemoveDirect	The assignment of the system role to a department is removed.
	Therefore the system role is removed from all employees that inherit assignments from this department.
QER Attestation AutoRe- movalScope ProfitCenterHasESet RemoveDirect	The assignment of the system role to a cost center is removed.
	Therefore the system role is removed from all employees that inherit assignments from this cost center.
QER Attestation AutoRe- movalScope LocalityHasESet RemoveDirect	The assignment of the system role to a location is removed.
	Therefore the system role is removed from all employees that inherit assignments from this location.
QER Attestation AutoRe- movalScope OrgHasESet RemoveDirect	The assignment of the system role to a business role is removed.
	Therefore the system role is removed from all employees that inherit assignments from this business role.

Table 47: Effect of configuration parameters when attestation denied



Application role attestation

When you use the **Application role membership attestation** default attestation policy or have set up attestation policies with the **Application role membership attestation** default attestation procedure, you can configure automatic removal of application roles through the **QER | Attestation | AutoRemovalScope | AERoleMembership** configuration parameter. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the application role.

Configuration parameter	Effect when set
QER Attestation AutoRemovalScope	The employee's secondary membership is removed from the application role.
AERoleMembership RemoveDirectRole	This removes all indirect assignments obtained by the employee through this application role. Membership in dynamic roles is not removed in this process.
QER Attestation AutoRemovalScope AERoleMembership RemoveRequestedRole	If the employee requested the application role through the IT Shop, the request is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this application role.
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.
QER Attestation AutoRemovalScope AERoleMembership RemoveDelegatedRole	If the application role was delegated to the employee, deleg- ation is canceled or unsubscribed.
	This removes all indirect assignments obtained by the employee through this application role.
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.

Table 48: Effect of configuration parameters when attestation denied

Business role attestation

Installed modules: Business Roles Module



When you use the **Business role membership attestation** default attestation policy and have set up attestation policies with the **Business role membership attestation** default attestation procedure, you can configure automatic removal of business roles through the **QER | Attestation | AutoRemovalScope | RoleMembership** configuration parameter. After attestation approval has been denied, One Identity Manager checks which type of assignment was used for the user account to become a member in the business role.

Configuration parameter	Effect when set		
QER Attestation AutoRemovalScope	The employee's secondary membership in the business role is removed.		
RoleMembership RemoveDirectRole	This removes all indirect assignments obtained by the employee through this business role. Membership in dynamic roles is not removed by this.		
QER Attestation AutoRemovalScope	If the employee requested the business role through the IT Shop, the request is canceled or unsubscribed.		
RoleMembership RemoveRequestedRole	This removes all indirect assignments obtained by the employee through this business role.		
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.		
QER Attestation AutoRemovalScope RoleMembership RemoveDelegatedRole	If the business role was delegated to the employee, delegation is canceled or unsubscribed.		
	This removes all indirect assignments obtained by the employee through this business role.		
	Set the desired behavior in the QER Attestation AutoRe- movalScope PWOMethodName configuration parameter. For more information, see Default attestation and withdrawal of entitlements on page 112.		

Table 49: Effect of configuration parameters when attestation denied



User attestation and recertification

Use the One Identity Manager attestation functionality to regularly check and authorize employees' master data and target system entitlements and assignments. In addition, One Identity Manager provides default procedures for managers to quickly attest and certify the master data of newly added One Identity Manager users in the One Identity Manager database. This functionality can be used, for example, if external employees, such as contract workers, are provided with temporary access to the One Identity Manager. The sequence is different for internal and external employees.

Regular recertification can be run through scheduled tasks.

In the context of an attestation, a manager can check and update the master data for the user to be certified, if necessary. Use the Web Portal for attestation.

Detailed information about this topic

- Configuring user attestation and recertification on page 122
- Attesting new users on page 123
- Recertifying existing users on page 131

One Identity Manager users for attesting and recertifying users

The following user are involved in attestation and recertification of employees.

Table 50: Users

User	Tasks
Employee administrators	Employee administrators must be assigned to the Identity Management Employees Administrators application role.
Users with this application role:	
	Can edit master data for all employees



User	Tasks
	Can assign a manager.
	 Can assign company resources to employees.
	 Check and authorize employee master data.
	Create and edit risk index functions.
	 Edit password policies for employee passwords
	 Delete employee's security keys (WebAuthn)
Manager	Check employee master data of the user to be certified.
	 Update employee master data as required.
	 Assign another manager if required.
	Attests the master data.
Attestors for external users	Attestors for external users must be assigned to the Identity & Access Governance Attestation Attestors for external users application role.
	Users with this application role:
	Attests new, external employees.
Administrators for attestation	Administrators must be assigned to the Identity & Access Governance Attestation Administrators application role.
cases	Users with this application role:
	 Modify the attestation policies if necessary.
	Create more schedules if required.
Web Portal users	Log on to the Web Portal and enter their master data,

Configuring user attestation and recertification

To use the attestation and recertification function for new internal users

- 1. In the Designer, set the **QER | Attestation | UserApproval** configuration parameter.
- 2. Assign at least one employee to the **Identity Management | Employees |** Administrators application role.

All employees with this application role can assign a manager to the employee being attested during the attestation process.



To use the attestation and recertification function for new external users

- 1. In the Designer, set the following configuration parameters:
 - **QER | Attestation | ApproveNewExternalUsers**: Select the value **1**.
 - **QER | WebPortal | PasswordResetURL**: Enter the URL for the Password Reset Portal.
 - QER | Attestation | MailTemplateIdents | NewExternalUserVerification: Mail template sending verification links.
 - **QER | Attestation | NewExternalUserTimeoutInHours**: For new external users, specify the duration of the verification link in hours.

The default is 4 hours. If logging in to the Password Reset Portal fails because the timeout has expired, the user can ask for a new verification link to be sent. To change the duration of the verification link, change the value in the configuration parameter.

• **QER | Attestation | NewExternalUserFinalTimeoutInHours**: Specify the duration in hours, within which self-registration must be successfully completed.

If the user does not complete registration with 24 hours, the attestation case quits. To register anyway, the user must log in again to the Web Portal from the beginning. To change the checkout duration of registration, change the value of the configuration parameter.

Assign at least one employee to the Identity & Access Governance | Attestation
 | Attestor for external users application role.

Detailed information about this topic

- Self-registration of new users in the Web Portal on page 124
- Adding new employees using a manager or employee administrator on page 126
- Importing new employee master data on page 128
- The recertification sequence on page 133
- Link for verifying new external users on page 107

Attesting new users

Attestation of new users is divided into three use cases by One Identity Manager:

- 1. Registration of new external users logging in to the Web Portal.
- 2. Adding new employees in the Manager or using a manager in the Web Portal.
- 3. Adding a new employee by importing employee master data.

The result of attestation is the same in all three cases.





• Certified, activated employees who can access all entitlements assigned to them in One Identity Manager and the connected target systems.

Company resources are inherited. Account definitions are assigned to internal employees.

- OR -

• Denied and permanently deactivated employees.

Disable employees cannot log in to One Identity Manager tools. Company resources are not inherited. Account definitions are not automatically assigned. User accounts associated with the employee are also locked or deleted. You can customize the behavior to meet your requirements.

Self-registration of new users in the Web Portal

Users who are not yet registered have the option to register themselves to use the Web Portal. These users can log in to the Web Portal once a manager has attested the user's master data and the set the user's password. This adds an external employee to the One Identity Manager database.

Attestation sequence:

1. The user logs in to the Web Portal for the first time and enters the required properties.

A new employee object is added to the One Identity Manager database with properties:

Table 51: Properties of a newly added employee

Property	Value
Certification status	New
External	Set
Contact email address	Email address to send the verification link to.
Permanently disabled	Set
No inheritance	Set

2. Attestation is started automatically.

Attestation policy used: **New user certification**

NOTE: The attestation only starts automatically if the **QER | Attestation | UserApproval** configuration parameter is set. Otherwise the new user remains disabled permanently until a manager changes the employee master data manually.



3. Attestors are found.

Effective approval policy: Certification of users

- If the QER | Attestation | ApproveNewExternalUsers configuration parameter is set and the value is 1, attestation of members of the Identity & Access Governance | Attestation | Attestors for external users is submitted.
 - a. If an attestor for external users denies the attestation, the attestation case is closed. The employee object's properties are updated in the database.

Table 52: Properties of an external employee with deniedattestation

Property	Value	Explanation
Certification status	Denied	
External	Set	
Permanently disabled	Set	The user cannot log in to the Web Portal.
No inheritance	Set	Company resources are not inherited.

b. If an attestor for external users approves attestation, an email with a verification link is sent to the new user.

NOTE: If the **QER | Attestation | ApproveNewExternalUsers** configuration parameter is not set or the value is **0**, an email with a verification link is sent immediately to the new user.

5. Once the user has followed the link and a password and a password question have been set, the attestation case is approved. The employee object's properties are updated in the database.

Table 53: Properties of an external employee with approvedattestation

Property	Value	Explanation
Certification status	Certified	
External	Set	
Permanently disabled	Not set	The user can log in to the Web Portal.
No inheritance	Not set	Company resources are inherited.

The default is 4 hours. If logging in to the Password Reset Portal fails because the timeout has expired, the user can ask for a new verification link to be sent.

If the user does not complete registration with 24 hours, the attestation case quits. To register anyway, the user must log in again to the Web Portal from the beginning.



Related topics

• Configuring user attestation and recertification on page 122

Adding new employees using a manager or employee administrator

You can also attest new users if new employees are added in the Manager or if a manager in the Web Portal adds a new employees. Specify the required behavior with the configuration parameter **QER | Attestation | UserApproval | InitialApprovalState**. This configuration parameter has the default value **0**. This gives each new employee the certification status **Certified**. Automatic attestation is not carried out.

To automatically attest new users

• In the Designer, enable the **QER | Attestation | UserApproval |** InitialApprovalState configuration parameter and set the value to 1.

All employees added to the database from this point on are given the certification status **New**. This means automatic attestation of these employees is carried out.

The sequence is different for internal and external employees.

Attestation sequence:

1. Enter the new user's master data and assign a manager to them.

For detailed information about adding employees, see the *One Identity Manager Identity Management Base Module Administration Guide* and the *One Identity Manager Web Portal User Guide*.

The certification status corresponds to the value of the **QER** | **Attestation** | **UserApproval** | **InitialApprovalState** configuration parameter. If the configuration parameter has the value **1**, certification status is set to **New**.

By default, the employee is active and can log in immediately to One Identity Manager.

- If new users are not allowed to log in to One Identity Manager until their master data has been attested, run the task **Disable employee permanently**.
- 2. Once the employee master data has been saved, attestation starts.

Attestation policy used: **New user certification**

3. Attestors are found.

Effective approval policy: Certification of users

4. If the **External** option is set for the employee:

Attestation takes place as described in the Self-registration of new users in the Web Portal section, steps 4 to 5.



- 5. If the **External** option is set for the employee:
 - a. One Identity Manager checks whether you have assigned a manager to the employee.
 - If you have assigned a manager to the employee, the case is immediately passed on to them for approval.
 - If you have not assigned a manager to the employee, the case is assigned to the employee administrators for approval.
 - b. An employee administrator checks your master data and also assigns a manager to you.
 - The employee administrator assigns a manager and approves attestation. The attestation case is assigned to the manager for approval.
 - If the employee administrator does not assign a manager and approves attestation, the attestation case is closed. The employee object's properties are updated in the database.

Property	Value	Explanation
Certification status	Certified	
External	Not set	
Disabled permanently	Not set	
No inheritance	Not set	Company resources are inherited.

Table 54: Properties of an employee with approvedattestation

• If an employee administrator denies attestation approval, the attestation case is closed. Your employee properties are updated in the database.

Table 55: Properties of an employee with rejected attestation

Property	Value	Explanation
Ceritifcation status	Rejected	
External	Not set	
Permanently disabled	Set	
No inheritance	Set	Company resources are not inherited.
		User accounts are not created automatically.

c. The manager can deny attestation approval if he is not the manager in charge of the employee.



- The manager can assign another person as manager. The attestation case is immediately assigned to this manager.
- If the manager does not know who your manager is, approval is returned to the employee administrators. These can
 - Assign another manager
 - Not assign another manager and grant attestation approval
 - Deny attestation approval
- d. If the manager approves attestation, the attestation case is closed. Your employee properties are updated in the database.

Table 56: Properties of an employee with approvedattestation

Property	Value	Explanation
Certification status	Certified	
External	Not set	
Disabled permanently	Not set	
No inheritance	Not set	Company resources are inherited.

NOTE: Only employee administrators can ultimately deny attestation approval. If a manager denies attestation, the case is returned to the employee administrators for approval in any case.

Related topics

• Configuring user attestation and recertification on page 122

Importing new employee master data

You can request attestation of new employees if the master data is imported from other systems into the One Identity Manager database. To ensure that new employees are automatically attested, you must set the employee's certification status to **New** (Person.ApprovalState = '1'). There are two possible ways to do this:

1. The **QER** | **Attestation** | **UserApproval** | **InitialApprovalState** configuration parameter is evaluated for certification status. If the configuration parameter has the value **1**, certification status is set to **New**.

Prerequisite: The import does not alter the Person.ApprovalState property.

NOTE: The **QER | Attestation | UserApproval | InitialApprovalState** configuration parameter has the value **0** by default. This gives each new employee the certification status **Certified**. Automatic attestation is not carried out.



If you want to attest new employees immediately, change the value of the configuration parameter to **1**.

- 2. The import sets the Person.ApprovalState property explicitly.
 - The import sets ApprovalState='1' (**New**).

Employees are automatically attested by their manager.

• The import sets ApprovalState='0' (**Certified**).

Imported employee master data has already been authorized. It should not be attested again.

• The import sets ApprovalState='3' (**Denied**).

The employee is disabled permanently and is not attested.

Attestation of new users is triggered when:

- The QER | Attestation | UserApproval configuration parameter is set
- New employee master data was imported into the One Identity Manager database
- The certification status for new employees is set to **New**
- No **Import data source** is stored with the employee.

If the **External** option is not set for an employee, attestation takes place as described in the Adding new employees using a manager or employee administrator section, step 5.

If the **External** option is set for the employee, attestation takes place as described in the Self-registration of new users in the Web Portal section, steps 4 to 5.

The **New user certification** attestation policy is run.

Related topics

• Configuring user attestation and recertification on page 122

Scheduled attestation

Users are also attested when the certification status for an employee is set to **New** at a later date (manually or through import). The **Daily** schedule is assigned to the **New user certification** attestation policy for this purpose. Attestation of new users is started when the time set in the schedule is reached. This process determines all employees with the certification status **New** and for whom no attestation cases are pending.

You can assign a custom schedule to the attestation policy if required.

Detailed information about this topic

• Schedules on page 17



Limiting attestation objects for certification

IMPORTANT: In order to customize the default **New user certification** attestation policy, you must make changes to One Identity Manager objects. Always use a custom copy of the respective object to make changes.

It may be necessary to limit attestation of new users to a certain group of employees, for example, if only employees in a specific departments should be attested. To do this, you can extend the condition attached to the attestation policy. Create a custom attestation policy for this.

The following objects must be changed so that attestation of new users can be carried out with this attestation policy. Always create a copy of the respective object to do this.

- New user certification attestation policy
- VI_Attestation_Person_new_AttestationCase_for_Certification process
- VI_Attestation_AttestationCase_Person_Approval_Granted process
- VI_Attestation_AttestationCase_Person_Approval_Dismissed process

IMPORTANT: In order for attestation to run correctly in the Web Portal, the default **Certification of users** attestation procedure and the default **Certification of users** approval policy must be assigned to the attestation policy.

The default attestation procedure, the default approval policy, and the default **Certification of users** approval workflow must not be changed.

To customize default attestation of new users

1. Copy the **Certification of users** attestation policy and customize it.

Table 57: Attestation policy properties

Property	Value
Attestation procedure	Certification of users.
Approval policies	Certification of users.
Editing conditions	Copy the default condition without modification so that the correct attestation object is selected.
	To limit the number of attestation objects, you can add additional partial conditions to the database query.

2. In the Designer, create a copy of the VI_Attestation_Person_new_AttestationCase_ for_Certification process from the Person base object and customize the copy.

Table 58: Process properties with changes

Process step	Parameter	Change
Create attestation instance	WhereClause	Replace the UID of the New user certification attestation policy with the UID of the new attestation policy.

3. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Granted process of the AttestationCase base object and customize the copy.

Table 59: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the New user certification attestation policy
Generating condition	with the UID of the new attestation policy.

4. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Dismissed process of the AttestationCase base object and customize the copy.

Table 60: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the New user certification attestation policy
Generating condition	with the UID of the new attestation policy.

For detailed information about editing processes, see the One Identity Manager Configuration Guide.

Detailed information about this topic

- General master data for attestation policies on page 25
- Creating a copy on page 32

Recertifying existing users

IMPORTANT: Access to connected target systems may possibly be denied to One Identity Manager users as a result of recertification. You can configure this behavior to meet your



company's requirements. Read the following section thoroughly before you use the recertification function.

One Identity Manager provides an attestation policy for performing cyclical attestation of existing users allowing companies to regularly test and authorize employee master data stored in the One Identity Manager database. Cyclical attestation is triggered through a scheduled task. This resets the certification status for all employees stored in the database. One Identity Manager uses the same procedure for this as for attesting new users. The case is referred to as recertification.

Result of recertification

• Certified, activated employees who can access all entitlements assigned to them in One Identity Manager and the connected target systems.

Company resources are inherited. Account definitions are assigned to internal employees.

- OR -

• Denied and permanently deactivated employees.

Disable employees cannot log in to One Identity Manager tools. Company resources are not inherited. Account definitions are not automatically assigned. User accounts associated with the employee are also locked or deleted. You can customize the behavior to meet your requirements.

Preparing for recertification

To set up regular user attestation

- 1. In the Designer, set the required configuration parameters.
- 2. Create a schedule and assign it to the **User recertification** attestation policy. By doing this, you replace the schedule assigned by default.
 - Enable the schedule.

Detailed information about this topic

Configuring user attestation and recertification on page 122

Related topics

- General master data for attestation policies on page 25
- Schedules on page 17



The recertification sequence

One Identity Manager uses the same method for recertification as for certification of new users. User recertification is triggered when all the following are true:

- The **QER | Attestation | UserApproval** configuration parameter is set.
- No Import data source is stored with the employee or the Import data source is not E-Business Suite.
- The execution time in the schedule stored for the **User recertification** attestation policy has been reached.

Internal employees are attested by their manager. If an employee is not assigned a manager, the employee administrator assigns an initial manager for them. Only employee administrators can ultimately deny recertification. If a manager denies recertification, the case is always returned to the employee administrators to decide approval.

External employees are attested by members of the **Identity & Access Governance |** Attestation | Attestors for external users application role.

If the **External** option is not set for an employee, attestation takes place as described in the Adding new employees using a manager or employee administrator section, step 5.

If the **External** option is set for the employee, attestation takes place as described in the Self-registration of new users in the Web Portal section, steps 4 to 5.

The attestors are determined using the **Certification of users** approval policy.

Limiting attestation objects for recertification

IMPORTANT: In order to customize the **User recertification** default attestation policy, you must make changes to One Identity Manager objects. Always use a custom copy of the relevant object to make these changes.

All employees saved in the database are recertified using the **User recertification** attestation policy supplied in One Identity Manager. It may be necessary to limit recertification of new users to a certain group of employees, for example, if only employees in a specific departments should be attested. To do this, you can extend the condition attached to the attestation policy. Create a custom attestation policy for this.

The following objects must be changed so that recertification of users can be carried out with this attestation policy. Always create a copy of the respective object to do this.

- User recertification attestation policy
- VI_Attestation_AttestationCase_Person_Approval_Granted process
- VI_Attestation_AttestationCase_Person_Approval_Dismissed process

IMPORTANT: In order for recertification to run correctly in the Web Portal, the default



Certification of users attestation procedure and the default **Certification of users** approval policy must be assigned to the attestation policy.

The default attestation procedure, the default approval policy, and the default **Certification of users** approval workflow must not be changed.

To customize default recertification of users

1. Copy the **User recertification** attestation policy and customize it.

Table 61: Attestation policy properties

Property	Value
Attestation procedure	Certification of users.
Approval policies	Certification of users.
Editing conditions	Copy the default condition without modification so that the correct attestation object is selected.
	To limit the number of attestation objects, you can add additional partial conditions to the database query.

2. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Granted process of the AttestationCase base object and customize the copy.

Table 62: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the User recertification attestation policy
Generating condition	with the UID of the new attestation policy.

3. In the Designer, copy the VI_Attestation_AttestationCase_Person_Approval_Dismissed process of the AttestationCase base object and customize the copy.

Table 63: Process properties with changes

Process property	Change
Pre-script for generating	Replace the UID of the User recertification attestation policy
Generating condition	with the UID of the new attestation policy.



For detailed information about editing processes, see the One Identity Manager Configuration Guide.

Detailed information about this topic

- General master data for attestation policies on page 25
- Creating a copy on page 32



Mitigating controls

6

Violation of regulatory requirements can harbor different risks for companies. To evaluate these risks, you can apply risk indexes to attestation policies. These risk indexes provide information about the risk involved for the company if this particular policy is violated. Once the risks have been identified and evaluated, mitigating controls can be implemented.

Mitigating controls are independent on One Identity Manager's functionality. They are not monitored through One Identity Manager.

Mitigating controls describe controls that are implemented if an attestation rule was violated. The attestation can be approved after the next attestation run, once controls have been applied.

To edit mitigating controls

• In the Designer, set the **QER | CalculateRiskIndex** configuration parameter and compile the database.

For more detailed information about risk assessment, see the One Identity Manager Risk Assessment Administration Guide.

General master data for mitigating controls

To edit mitigating controls

- 1. In the Manager, select the **Risk index functions | Mitigating controls** category.
- Select a mitigating control in the result list and run the Change master data task.
 OR -

Click 🖶 in the result list.

- 3. Edit the mitigating control master data.
- 4. Save the changes.

Enter the following master data for mitigating controls.



Property	Description
Measure	Unique identifier for the mitigating control.
Significance reduction	When the mitigating control is implemented, this value is used to reduce the risk of denied attestation cases. Enter a number between 0 and 1.
Description	Detailed description of the mitigating control.
Functional area	Functional area in which the mitigating control may be applied.
Department	Department in which the mitigating control may be applied.

Table 64: General master data for a mitigating control

Additional tasks for mitigating controls

After you have entered the master data, you can run the following tasks.

Mitigating controls overview

You can see the most important information about a mitigating control on the overview form.

To obtain an overview of a mitigating control

- 1. In the Manager, select the **Risk index functions | Mitigating controls** category.
- 2. Select the mitigating control in the result list.
- 3. Select the Mitigating control overview task.

Assigning attestation policies

Use this task to specify for which attestation policies the mitigating control is valid.

To assign attestation policies to mitigating controls

- 1. In the Manager, select the **Risk index functions | Mitigating control** category.
- 2. Select the mitigating control in the result list.
- 3. Select the **Assign attestation polices** task.

Assign the attestation policies in **Add assignments**.

TIP: In **Remove assignments**, you can remove the assignment of attestation



policies.

To remove an assignment

- 4. Save the changes.

Calculating mitigation

The reduction in significance of a mitigating control supplies the value by which the risk index of an attestation policy is reduced when the control is implemented. One Identity Manager calculates a reduced risk index based on the risk index and the significance reduction. One Identity Manager supplies default functions for calculating reduced risk indexes. These functions cannot be edited with One Identity Manager tools.

The reduced risk index is calculated from the company policy and the significance reduced sum of all assigned mitigating controls.

Risk index (reduced) = Risk index - sum significance reductions

If the significance reduction sum is greater than the risk index, the reduced risk index is set to $\mathbf{0}$.



Appendix: Configuration parameters for attestation

The following configuration parameters are additionally available in One Identity Manager after the module has been installed. Some general configuration parameters are relevant for attestation. The following table contains a summary of all applicable configuration parameters for attestation.

Configuration parameter	Description
QER Attestation	Preprocessor relevant configuration parameter for controlling the model parts for attestation. Changes to the parameter require recompiling the database.
	If the parameter is enabled you can use the attestation function.
QER Attestation AllowAllReportTypes	This configuration parameter specifies whether all report formats are permitted for attestation policies. By default, only PDF is allowed because it is the only audit secure format.
QER Attestation ApproveNewEx- ternalUsers	This configuration parameter specifies whether new external users must be attested before the are enabled.
QER Attestation AutoCloseInactivePerson	If this configuration parameter is set, pending attestation cases for an employee are closed, when this employees is permanently deactivated.
QER Attestation AutoRemovalScope	General configuration parameter for defining automatic withdrawal of member- ships/assignments if attestation approval is not granted.
QER Attestation	Determines default behavior for automatic

Table 65: Overview of configuration parameters



Configuration parameter	Description	
AutoRemovalScope AERoleMembership	removal of application role memberships if attest- ation approval is not granted.	
QER Attestation AutoRemovalScope AERoleMembership RemoveDelegatedRole	If this configuration parameter is set, it ends the application role delegation if attestation approval is not granted.	
QER Attestation AutoRemovalScope AERoleMembership RemoveDirectRole	If this configuration parameter is set, the employee's membership of the application role is removed when attestation approval is not granted.	
QER Attestation AutoRemovalScope AERoleMembership RemoveRequestedRole	If this configuration parameter is set, the request for membership of the application role is aborted if attestation approval is not granted.	
QER Attestation AutoRe- movalScope DepartmentHasESet	Determines default behavior for automatic removal of system role assignments to depart- ments if attestation approval has been denied.	
QER Attestation AutoRe- movalScope DepartmentHasESet RemoveDirect	If this configuration parameter is set, system role to department assignments are removed if attestation approval is not granted.	
QER Attestation AutoRe- movalScope Depart- mentHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to departments if attestation approval has been denied.	
QER Attestation AutoRe- movalScope Depart- mentHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to department assignments are removed if attestation approval is not granted.	
QER Attestation AutoRemovalScope ESetAssignment	Determines default behavior for automatic removal of system role memberships if attest- ation approval is not granted.	
QER Attestation AutoRemovalScope ESetAssignment RemoveDelegatedRole	If this configuration parameter is set, it ends the role delegation through which the employee obtained the system role if attestation approval is not granted.	
	This removes all indirect assignments obtained by the employee through this role.	
QER Attestation AutoRemovalScope ESetAssignment RemoveDirect	If this configuration parameter is set, the direct user account membership in the system role will be removed if attestation approval is not	

Configuration parameter	Description
	granted.
	This removes all indirect assignments obtained by the employee through the system role.
QER Attestation AutoRemovalScope ESetAssignment RemoveDirectRole	If this configuration parameter is set, the system role assignment to roles (organizations and business roles) is removed if attestation approval is not granted. This removes the system entitlement assignment to all user accounts whose associated employees are members of these roles.
	IMPORTANT: Employees whose attestation has been approved can lose the system role through this.
QER Attestation AutoRemovalScope ESetAssignment RemovePrimaryRole	If this configuration parameter is set, the primary role assignment through which the employee obtained the system role is removed from the employee when attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope ESetAssignment RemoveRequested	If this configuration parameter is set, the requested system role is canceled if attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through the system role.
QER Attestation AutoRemovalScope ESetAssignment RemoveRequestedRole	If this configuration parameter is set, the request for the role through which the employee obtained the system role is canceled if attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRe- movalScope ESetHasEntitlement	Determines default behavior for automatic removal of system role assignments after attest- ation approval has been denied.
QER Attestation AutoRe- movalScope ESetHasEntitlement RemoveDirect	If this configuration parameter is set, company resource assignments to system roles are removed when attestation approval is denied.
QER Attestation AutoRemovalScope GroupMembership	Determines default behavior for automatic removal of united namespace system entitle- ments if attestation approval is not granted.



Configuration parameter	Description
QER Attestation AutoRemovalScope GroupMembership RemoveDelegatedRole	If this configuration parameter is set, it ends the role delegation through which the employee obtained the system entitlement if attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope GroupMembership RemoveDirect	If this configuration parameter is set, the direct user account membership in the system entitle- ment will be removed if attestation approval is not granted.
QER Attestation AutoRemovalScope GroupMembership RemoveDirectRole	If this configuration parameter is set, the system entitlement assignment to roles (organizations and business roles) is removed if attestation approval is not granted. This removes the system entitlement assignment to all user accounts whose associated employees are members of these roles.
	IMPORTANT: Employees whose attestation has been approved can lose the system entitlement through this.
QER Attestation AutoRemovalScope GroupMembership RemovePrimaryRole	If this configuration parameter is set, the primary role assignment through which the employee obtained the system entitlement is removed from the employee when attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope GroupMembership RemoveRequested	If this configuration parameter is set, the requested system entitlement is canceled if attestation approval is not granted.
QER Attestation AutoRemovalScope GroupMembership RemoveRequestedRole	If this configuration parameter is set, the request for the role through which the employee obtained the system entitlement is canceled when attest- ation approval is not granted.
	This removes all indirect assignments obtained by the employee through this role.
QER Attestation AutoRemovalScope GroupMembership RemoveSystemRole	If this configuration parameter is set, the system role assignment through which the employee obtained the system entitlement is removed



Configuration parameter	Description
	from the employee when attestation approval is not granted.
	This removes all indirect assignments obtained by the employee through this system role.
	NOTE: This configuration parameter is only available if the System Roles Module is installed.
QER Attestation AutoRe- movalScope LocalityHasESet	Determines default behavior for automatic removal of system role assignments to locations if attestation approval has been denied.
QER Attestation AutoRe- movalScope LocalityHasESet RemoveDirect	If this configuration parameter is set, system role to location assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope LocalityHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to locations if attestation approval has been denied.
QER Attestation AutoRe- movalScope LocalityHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to location assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope OrgHasESet	Determines default behavior for automatic removal of system role assignments to business roles if attestation approval has been denied.
QER Attestation AutoRe- movalScope OrgHasESet RemoveDirect	If this configuration parameter is set, system role to business role assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope OrgHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to business roles if attestation approval has been denied.
QER Attestation AutoRe- movalScope OrgHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to business role assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope ProfitCenterHasESet	Determines default behavior for automatic removal of system role assignments to system roles if attestation approval has been denied.
QER Attestation AutoRe- movalScope ProfitCenterHasESet RemoveDirect	If this configuration parameter is set, system role to cost center assignments are removed if attestation approval is not granted.

Configuration parameter	Description
QER Attestation AutoRe- movalScope ProfitCen- terHasUNSGroup	Determines default behavior for automatic removal of system entitlement assignments to system roles if attestation approval has been denied.
QER Attestation AutoRe- movalScope ProfitCen- terHasUNSGroup RemoveDirect	If this configuration parameter is set, system entitlement to cost center assignments are removed if attestation approval is not granted.
QER Attestation AutoRe- movalScope PWOMethodName	Method to be executed on requests if the requested assignment is to be deleted when attestation approval is not granted.
	The requests can be unsubscribed (Unsubscribe) or aborted (Abort). If the configuration parameter is not set, the requests are aborted by default.
QER Attestation AutoRemovalScope RoleMembership	Determines default behavior for automatic removal of business role memberships if attest- ation approval is not granted.
QER Attestation AutoRemovalScope RoleMembership	If this configuration parameter is set, it ends the business role delegation if attestation approval is not granted.
RemoveDelegatedRole	This removes all indirect assignments the employee obtained through this business role.
QER Attestation AutoRemovalScope RoleMembership RemoveDirectRole	If this configuration parameter is set, the employee secondary membership in the business role will be removed if attestation approval is not granted.
	This removes all indirect assignments the employee obtained through this business role.
QER Attestation AutoRemovalScope RoleMembership	If this configuration parameter is set, the request for membership of the business role is canceled if attestation approval is not granted.
RemoveRequestedRole	This removes all indirect assignments the employee obtained through this business role.
QER Attestation AutoRemovalScope UNSGroupInUNSGroup	Specifies the default behavior for removing assignments from system entitlements to system entitlement is attestation approval is not granted.
QER Attestation AutoRemovalScope	If this configuration parameter is set, the system entitlement assignment to a system entitlement



Configuration parameter	Description
UNSGroupInUNSGroup RemoveDirect	is removed when attestation approval is not granted.
QER Attestation DefaultSenderAddress	This configuration parameter contains the sender email address for messages automatically generated for attestation.
QER Attestation MailApproval Account	Name of the user account for authenticating the mailbox used for attestation by mail.
QER Attestation MailApproval DeleteMode	Specifies the way emails are deleted from the inbox.
QER Attestation MailApproval Domain	Domain of the user account for authenticating the mailbox used for attestation by mail.
QER Attestation MailApproval ExchangeURI	Specifies the Microsoft Exchange Web Service URL. AutoDiscover mode is used to find the URL if it is not given.
QER Attestation MailApproval Inbox	Microsoft Exchange mailbox. Approval mails for attestation by mail are sent to this mailbox.
QER Attestation MailApproval Password	User account password for authenticating the mailbox used for attestation by mail.
QER Attestation MailTemplateIdents AnswerToApprover	This mail template is used to send a notification with an answer to a question from an approver.
QER Attestation MailTemplateIdents AttestationApproval	Mail template used for attestation by mail.
QER Attestation MailTemplateIdents InformAddingPerson	This mail template is used to notify approvers that an approval decision has been made for the step they added.
QER Attestation MailTemplateIdents InformDelegatingPerson	This mail template is used to notify approvers that an approval decision has been made for the step they delegated.
QER Attestation MailTemplateIdents NewEx- ternalUserVerification	Mail template for sending a message with a verification link to a new external user.
QER Attestation MailTemplateIdents QueryFromApprover	This mail template is used to send a notification with a question from an approver to an employee.
QER Attestation	This mail template is used for generating an



Configuration parameter	Description
MailTemplateIdents RequestApproverByCollection	email when there are pending attestation for an approver. If this configuration parameter is not set, a Mail template request or Mail template reminder can be entered for single approval steps. This template is then sent for each individual attestation case. If this config- uration parameter is set, single mails are not sent.
QER Attestation NewEx- ternalUserFinalTimeoutInHours	Number of hours given for new external users to register (default: 24 hrs).
QER Attestation NewEx- ternalUserTimeoutInHours	Number of hours that the access code and verific- ation link for new external users are valid (default: 4 hrs).
QER Attestation OnWorkflowAssign	This configuration parameter specifies how pending attestation cases are handled when a new approval workflow is assigned to the approval policy.
QER Attestation OnWorkflowUpdate	This configuration parameter specifies how pending attestations are handled when the approval workflow is changed.
QER Attestation PersonToAttestNoDecide	This configuration parameter specifies whether employees to be attested are allowed to approve this attestation case. If the parameter is set, an attestation case cannot be approved by employees, which are contained in the attest- ation object (AttestationCase.ObjectKeyBase) or in the objects identifiers 1-3 (AttestationCase.UID_ObjectKey1, ObjectKey2 or ObjectKey3). If the parameter is not set, these employee are allowed to make approval decisions for this attestation case.
QER Attestation ReducedApproverCalculation	This configuration parameter specifies, which approval steps are recalculated if modifications require attestors to be redetermined.
QER Attestation UserApproval	Supports attestation procedures for regularly checking and confirming One Identity Manager users through their Manager.
QER Attestation UserApproval InitialApprovalState	Certification status for new employees. If an employee is added with the certification status 1 = new, data attestation by the employee's manager is started.

Configuration parameter	Description
QER CalculateRiskIndex	Preprocessor relevant configuration parameter controlling system components for calculating an employee's risk index. Changes to the parameter require recompiling the database.
	If the parameter is enabled, values for the risk index can be entered and calculated.
QER Employee Defender	This configuration parameter specifies whether Starling Two-Factor Authentication is supported.
QER Employee Defender ApiEndpoint	This configuration parameter contains the URL of the Starling 2FA API end point used to register new users.
QER Employee Defender ApiKey	This configuration parameter contains your company's subscription key for accessing the Starling Two-Factor Authentication interface.
QER Person Defender DisableForceParameter	This configuration parameter specifies whether Starling 2FA is forced to send the OTP by SMS or phone call if one of these options is selected for multi-factor authentication. If the configuration parameter is set, Starling 2FA can disallow the request and the user must request the OPT through Starling 2FA.
QER WebPortal BaseURL	Web Portal URL This address is used in mail templates to add hyperlinks to the Web Portal.
QER WebPortal PasswordResetURL	URL for the Password Reset Portal. This address is used to navigate.
Common MailNotification DefaultCulture	This configuration parameter contains the default language for email notifications if no language can be determined for the recipient.
Common MailNotification Signature	Data for the signature in email automatically generated from mail templates.
Common MailNotification Signature Caption	Signature under the salutation.
Common MailNotification Signature Company	Company name.
Common MailNotification Signature Link	Link to company website.
Common MailNotification SMTPAccount	User account name for authentication on an SMTP server.



Configuration parameter	Description
Common MailNotification SMTPDomain	User account domain for authentication on the SMTP server.
Common MailNotification SMTPPassword	User account password for authentication on the SMTP server.
Common MailNotification SMTPPort	Port for SMTP services on the SMTP server (default: 25).
Common MailNotification SMTPRelay	SMTP server for sending notifications.
Common MailNotification SMTPUseDefaultCredentials	If this configuration parameter is set, the One Identity Manager Service credentials are used for authentication on the SMTP server. If this configuration parameter is not set, the login data stored in the configuration parameters Common MailNotification SMTPDomain and Common MailNotification SMTPAccount or Common MailNotification SMTPPass- word is used.
Common ProcessState PropertyLog	When this configuration parameter is set, changes to individual values are logged and shown in the process view.

()NE IDENTITY^{**}

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit https://www.oneidentity.com/company/contact-us.aspx.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at https://support.oneidentity.com/.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product



149

Index

A

application role chief approval team 23, 78 approval 54 approval by mail 108 approval level 49 connect 54 approval policies 25, 42 default 43 user certification 124, 126 verify 44 approval procedure 57 add 72 approvals made externally 70 approver for attestation policy 62 attestation compliance rule attestor 62 attestation organization attestor 62 attestor for attestation company policy 62 calculated approval 69 condition 73 copy 77 custom 72 delete 77 department manager 65 department manager of account's person 65 employee manager 65 escalation 83 manager of account's person 65 manager of system roles to be attested 64

members of a certain role 67 overview form 76 owner of a privileged object 68 permitted for tables 76 product owners 65 proposed owner 68 query 73 recipient's location attestor 62 recipient's manager 64 recipient's cost center attestor 62 recipient's department attestor 62 recipient's primary role attestor 62 role manager 64 specific role Manager 67 target system manager of the permission for attestation 65 target system managers 65 waiting for further approval 71 approval process 42 approval reason 23 approval step 49-50 edit 50 approval workflow 45, 93 change 95 copy 55 default 56 delete 55 edit 48 overview form 55 user certification 124, 126



Index

approver notification 105 select 57 attestation 8 employee 121 new employee 123 new user 123 approver 124, 126 customize 130 imported employee master data 128 prepare 126 prepare import 128 sequence 124, 126 start schedule 129 remove application role automatically 119 remove business role automatically 119 remove entitlement automatically 112 remove system entitlement automatically 114 remove system role automatically 116 start 31, 91 for selected objects 91 user 121 user certification attestation policy 28 attestation procedure 15 attestation case 91 abort 88 additional attestors 82 approval sequence 93 approve automatically 86 attestation history 94

close attestations 91 closed 97 create 31, 91 delegate approval 82 delete 25, 97 escalate 83 notification 98 overview form 93 pending attestation 91 processing time 93 query 82 record 97 reject approval 82 reroute approval 82 timeout 83, 86, 88 attestation object 25, 31, 33 also attestor 81 attestation policy assign approver 29 assign compliance framework 29 assign mitigating control 30 calculation schedule assign 25 copy 32 create 25 create in Web Portal 112 default 28, 112 delete 33 disable 25, 33 edit 25 mitigating control 30 new user certification 124, 126, 128 customize 130 obsolete attestation cases 97 overview form 29



owner 25 processing time 25 report 25 risk index 25, 27 show condition 32 attestation procedure assign approval policy 16 default 15, 112 group 10 overview form 16 set up 12 attestation type 12 assign attestation procedure 12 default 11 overview form 11 attestors 93 approval by email 108 approve own attestation case 81 notification 100-101, 105-106 recalculate 78 restrict 81 select 57

В

base object 12 mail template 35 basic data 10

С

calculation schedule 17 assign attestation policy 20 default schedule 19 default schedule attestation check 17 new user certification 129 overview form 20 recertification 132 start immediately 21 certification see attestation 121 certification status employee 123 chief approval team 23, 78 compliance framework 21 assign attestation policy 22 manager 21 overview form 22

D

default attestation policy 112 default attestation procedure 112 default mail template 107 delegation approval notification 103 deny 54

Ε

email notification set up 98 employee attestation 121 certification status 124 initial 126, 128 certified 123, 131 no inheritance 123, 131 not set 123, 131 set 123, 131 escalation 54 notification 105



F

fallback approver 85

L

login verification link 107

Μ

mail template base object 35, 37 hyperlink 37 mitigating control 136 assign attestation policy 31, 137 create 31 log 136 overview form 137 significance reduction 136 multi-factor authentication 80

Ν

notification abort 104 additional attestors 106 approval 102 attestors 101 default mail template 107 demand 99, 105 deny 102 deny approval 105 escalation 105 external user 107 mail template 34, 98 on delegation 103 query 106 recipient 98 refuse approval 105 reject approval 105 reminder 100-101 sender 98 verification link 107

R

reason 23 recertification 8, 121 attestation policy customize 133 calculation schedule 132 customize 133 employee 131 prepare 132 sequence 133 user 131 report 12 create 15 default 15 reroute 54 risk assessment attestation policy 27 risk index calculate 138 reduced calculate 138

S

scheduled 91 security code 80



153

significance reduction 136 standard reason 23 Starling 2FA 80 Starling Two-Factor Authentication 80

Т

timeout 54

U

user certification approval policies 43 approval workflow 56 calculation schedule 19

W

Workflow Editor open 45

