# Wireshark User's Guide

# for Wireshark 1.9

Ulf Lamping, Richard Sharpe, NS Computer Software and Services P/L Ed Warnicke,



## Wireshark User's Guide: for Wireshark 1.9

by Ulf Lamping, Richard Sharpe, and Ed Warnicke Copyright © 2004-2012 Ulf Lamping , Richard Sharpe , Ed Warnicke

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU General Public License, Version 2 or any later version published by the Free Software Foundation.

All logos and trademarks in this document are property of their respective owner.

Preface	ix
1. Foreword	
2. Who should read this document?	. ix
3. Acknowledgements	
4. About this document	x
5. Where to get the latest copy of this document?	x
6. Providing feedback about this document	x
1. Introduction	1
1.1. What is Wireshark?	
1.1.1. Some intended purposes	
1.1.2. Features	
1.1.3. Live capture from many different network media	
1.1.4. Import files from many other capture programs	
1.1.5. Export files for many other capture programs	
1.1.6. Many protocol decoders	
1.1.7. Open Source Software	
1.1.8. What Wireshark is not	
1.2. System Requirements	
1.2.1. General Remarks	
1.2.2. Microsoft Windows	
1.2.3. Unix / Linux	
1.3. Where to get Wireshark?	
1.4. A brief history of Wireshark	
1.5. Development and maintenance of Wireshark	
1.6. Reporting problems and getting help	
1.6.1. Website	
1.6.2. Wiki	
1.6.3. Q&A Forum	
1.6.4. FAQ	
1.6.5. Mailing Lists	
1.6.6. Reporting Problems	
1.6.7. Reporting Crashes on UNIX/Linux platforms	
1.6.8. Reporting Crashes on Windows platforms	
2. Building and Installing Wireshark	
2.1. Introduction	
2.2. Obtaining the source and binary distributions	
2.3. Before you build Wireshark under UNIX	
2.4. Building Wireshark from source under UNIX	
2.5. Installing the binaries under UNIX	
2.5.1. Installing from rpm's under Red Hat and alike	
2.5.2. Installing from deb's under Debian, Ubuntu and other Debian derivatives	
2.5.3. Installing from portage under Gentoo Linux	
2.5.4. Installing from packages under FreeBSD	
2.6. Troubleshooting during the install on Unix	
2.7. Building from source under Windows	
2.8. Installing Wireshark under Windows	
2.8.1. Install Wireshark	
2.8.2. Manual WinPcap Installation	
2.8.3. Update Wireshark	
2.8.4. Update WinPcap	
2.8.5. Uninstall Wireshark	
2.8.6. Uninstall WinPcap	
3. User Interface	
3.1. Introduction	19

3.2. Start Wireshark	19
3.3. The Main window	19
3.3.1. Main Window Navigation	21
3.4. The Menu	21
3.5. The "File" menu	22
3.6. The "Edit" menu	25
3.7. The "View" menu	27
3.8. The "Go" menu	31
3.9. The "Capture" menu	32
3.10. The "Analyze" menu	
3.11. The "Statistics" menu	
3.12. The "Telephony" menu	
3.13. The "Tools" menu	
3.14. The "Internals" menu	
3.15. The "Help" menu	
3.16. The "Main" toolbar	
3.17. The "Filter" toolbar	
3.18. The "Packet List" pane	
3.19. The "Packet Details" pane	
3.20. The "Packet Bytes" pane	
3.21. The Statusbar	
4. Capturing Live Network Data	
4.1. Introduction	
4.2. Prerequisites	
4.3. Start Capturing	
4.4. The "Capture Interfaces" dialog box	
4.4. The Capture Interfaces dialog box	
4.5.1. Capture frame	
4.5.1. Capture File(s) frame	
4.5.2. Capture File(s) frame	
4.5.4. Display Options frame	
4.5.5. Name Resolution frame	
4.5.6. Buttons	
4.6. The "Edit Interface Settings" dialog box	
4.7. The "Add New Interfaces" dialog box	
4.7.1. Add or remove pipes	
4.7.2. Add or hide local interfaces	
4.7.3. Add or hide remote interfaces	
4.8. The "Remote Capture Interfaces" dialog box	
4.8.1. Remote Capture Interfaces	
4.8.2. Remote Capture Settings	
4.9. The "Interface Details" dialog box	
4.10. Capture files and file modes	
4.11. Link-layer header type	
4.12. Filtering while capturing	
4.12.1. Automatic Remote Traffic Filtering	
4.13. While a Capture is running	
4.13.1. Stop the running capture	
4.13.2. Restart a running capture	
5. File Input / Output and Printing	
5.1. Introduction	
5.2. Open capture files	
5.2.1. The "Open Capture File" dialog box	
5.2.2. Input File Formats	73

5.3. Saving captured packets	74
5.3.1. The "Save Capture File As" dialog box	
5.3.2. Output File Formats	
5.4. Merging capture files	
5.4.1. The "Merge with Capture File" dialog box	
5.5. Import text file	
5.5.1. The "File import" dialog box	
5.6. File Sets	81
5.6.1. The "List Files" dialog box	82
5.7. Exporting data	82
5.7.1. The "Export as Plain Text File" dialog box	83
5.7.2. The "Export as PostScript File" dialog box	
5.7.3. The "Export as CSV (Comma Separated Values) File" dialog box	
5.7.4. The "Export as C Arrays (packet bytes) file" dialog box	
5.7.5. The "Export as PSML File" dialog box	
5.7.6. The "Export as PDML File" dialog box	
5.7.7. The "Export selected packet bytes" dialog box	
5.7.8. The "Export Objects" dialog box	
5.8. Printing packets	
5.8.1. The "Print" dialog box	
5.9. The Packet Range frame	
5.10. The Packet Format frame	
6. Working with captured packets	
6.1. Viewing packets you have captured	
6.2. Pop-up menus	
6.2.1. Pop-up menu of the "Packet List" column header	
6.2.2. Pop-up menu of the "Packet List" pane	
6.2.3. Pop-up menu of the "Packet Details" pane	
6.3. Filtering packets while viewing	
6.4. Building display filter expressions	
6.4.1. Display filter fields	
6.4.2. Comparing values	
6.4.3. Combining expressions	
6.4.4. A common mistake	
6.5. The "Filter Expression" dialog box	
6.6. Defining and saving filters	
6.7. Defining and saving filter macros	
6.8. Finding packets	
6.8.1. The "Find Packet" dialog box	
6.8.2. The "Find Next" command	
6.8.3. The "Find Previous" command	113
6.9. Go to a specific packet	113
6.9.1. The "Go Back" command	113
6.9.2. The "Go Forward" command	113
6.9.3. The "Go to Packet" dialog box	
6.9.4. The "Go to Corresponding Packet" command	113
6.9.5. The "Go to First Packet" command	114
6.9.6. The "Go to Last Packet" command	
6.10. Marking packets	
6.11. Ignoring packets	
6.12. Time display formats and time references	
6.12.1. Packet time referencing	
7. Advanced Topics	
7.1. Introduction	117

7.2. Following TCP streams	
7.2.1. The "Follow TCP Stream" dialog box	117
7.3. Expert Infos	
7.3.1. Expert Info Entries	
7.3.2. "Expert Info" dialog	
7.3.3. "Colorized" Protocol Details Tree	
7.3.4. "Expert" Packet List Column (optional)	
7.4. Time Stamps	
7.4.1. Wireshark internals	
7.4.2. Capture file formats	
7.4.3. Accuracy	
7.5. Time Zones	
7.5.1. Set your computer's time correctly!	
7.5.2. Wireshark and Time Zones	
7.6. Packet Reassembling	
7.6.1. What is it?	
7.6.2. How Wireshark handles it	
7.7. Name Resolution	
7.7.1. Name Resolution drawbacks	
7.7.2. Ethernet name resolution (MAC layer)	
7.7.3. IP name resolution (network layer)	
7.7.4. IPX name resolution (network layer)	
7.7.5. TCP/UDP port name resolution (transport layer)	
7.8. Checksums	
7.8.1. Wireshark checksum validation	
7.8.2. Checksum offloading	
8.1. Introduction	
<ul><li>8.2. The "Summary" window</li><li>8.3. The "Protocol Hierarchy" window</li></ul>	
8.4. Conversations	
8.4.1. What is a Conversation?	
8.4.2. The "Conversations" window	
8.4.3. The protocol specific "Conversation List" windows	
8.5. Endpoints	
8.5.1. What is an Endpoint?	
8.5.2. The "Endpoints" window	
8.5.2. The Endpoints window	
8.6. The "IO Graphs" window	
8.7. Service Response Time	
8.7.1. The "Service Response Time DCE-RPC" window	
8.8. Compare two capture files	
8.9. WLAN Traffic Statistics	
8.10. The protocol specific statistics windows	
9. Telephony	
9.1. Introduction	
9.2. RTP Analysis	
9.3. VoIP Calls	
9.4. LTE MAC Traffic Statistics	
9.5. LTE RLC Traffic Statistics	
9.6. The protocol specific statistics windows	
10. Customizing Wireshark	
10.1. Introduction	
10.2. Start Wireshark from the command line	

10.3. Packet colorization	150
10.4. Control Protocol dissection	153
10.4.1. The "Enabled Protocols" dialog box	153
10.4.2. User Specified Decodes	154
10.4.3. Show User Specified Decodes	
10.5. Preferences	
10.5.1. Interface Options	157
10.6. Configuration Profiles	158
10.7. User Table	160
10.8. Display Filter Macros	
10.9. ESS Category Attributes	
10.10. GeoIP Database Paths	
10.11. IKEv2 decryption table	
10.12. Object Identifiers	
10.13. PRES Users Context List	
10.14. SCCP users Table	
10.15. SMI (MIB and PIB) Modules	
10.16. SMI (MIB and PIB) Paths	
10.17. SNMP Enterprise Specific Trap Types	
10.18. SNMP users Table	163
10.19. Tektronix K12xx/15 RF5 protocols Table	
10.20. User DLTs protocol table	
11. Lua Support in Wireshark	
11.1. Introduction	
11.2. Example of Dissector written in Lua	
11.2. Example of Dissector written in Lua	
11.5. Example of Listener written in Lua	
11.5. Saving capture files	
11.5.1. Dumper	
11.5.2. PseudoHeader	
11.6. Obtaining dissection data	
11.6.1. Field	
11.6.2. FieldInfo	
11.6.3. Non Method Functions	
11.7. GUI support	
11.7.1. ProgDlg	
11.7.2. TextWindow	
11.7.3. Non Method Functions	
11.8. Post-dissection packet analysis	
11.8.1. Listener	
11.9. Obtaining packet information	
11.9.1. Address	
11.9.2. Column	
11.9.3. Columns	
11.9.4. NSTime	
11.9.5. Pinfo	
11.9.6. PrivateTable	
11.10. Functions for writing dissectors	
11.10.1. Dissector	
11.10.2. DissectorTable	
11.10.3. Pref	186
11.10.4. Prefs	
11.10.5. Proto	
11.10.6. ProtoField	189

11.10.7. Non Method Functions	198
11.11. Adding information to the dissection tree	198
11.11.1. TreeItem	
11.12. Functions for handling packet data	
11.12.1. ByteArray	
11.12.3. Tvb	
11.12.4. TvbRange	203
11.12.5. UInt	
11.13. Utility Functions	
11.13.1. Dir	
11.13.2. Non Method Functions	
A. Files and Folders	
A.1. Capture Files	
A.1.1. Libpcap File Contents	
A.1.2. Not Saved in the Capture File	
A.2. Configuration Files and Folders	
A.2.1. Protocol help configuration	
A.3. Windows folders	
A.3.1. Windows profiles	
A.3.2. Windows 7, Vista, XP, 2000, and NT roaming profiles	
A.3.2. Windows 7, Vista, XI, 2000, and WI roanning promos	
B. Protocols and Protocol Fields	
C. Wireshark Messages	
C.1. Packet List Messages	
C.1.1. [Malformed Packet]	
C.1.2. [Packet size limited during capture]	
C.2. Packet Details Messages	
C.2.1. [Response in frame: 123]	
C.2.2. [Request in frame: 123]	
C.2.3. [Time from request: 0.123 seconds]	
C.2.4. [Stream setup by PROTOCOL (frame 123)]	
D. Related command line tools	
D.1. Introduction	
D.2. tshark: Terminal-based Wireshark	
D.3. tcpdump: Capturing with tcpdump for viewing with Wireshark	
D.4. <b>dumpcap</b> : Capturing with dumpcap for viewing with Wireshark	
D.5. capinfos: Print information about capture files	227
D.6. rawshark: Dump and analyze network traffic.	
D.7. editcap: Edit capture files	
D.8. mergecap: Merging multiple capture files into one	
D.9. text2pcap: Converting ASCII hexdumps to network captures	
D.10. idl2wrs: Creating dissectors from CORBA IDL files	
D.10.1. What is it?	
D.10.2. Why do this?	237
	237
D.10.4. TODO	239
D.10.5. Limitations	
	239
E. This Document's License (GPL)	240

# Preface

# 1. Foreword

Wireshark is one of those programs that many network managers would love to be able to use, but they are often prevented from getting what they would like from Wireshark because of the lack of documentation.

This document is part of an effort by the Wireshark team to improve the usability of Wireshark.

We hope that you find it useful, and look forward to your comments.

# 2. Who should read this document?

The intended audience of this book is anyone using Wireshark.

This book will explain all the basics and also some of the advanced features that Wireshark provides. As Wireshark has become a very complex program since the early days, not every feature of Wireshark may be explained in this book.

This book is not intended to explain network sniffing in general and it will not provide details about specific network protocols. A lot of useful information regarding these topics can be found at the Wireshark Wiki at <a href="http://wiki.wireshark.org">http://wiki.wireshark.org</a>

By reading this book, you will learn how to install Wireshark, how to use the basic elements of the graphical user interface (such as the menu) and what's behind some of the advanced features that are not always obvious at first sight. It will hopefully guide you around some common problems that frequently appear for new (and sometimes even advanced) users of Wireshark.

# 3. Acknowledgements

The authors would like to thank the whole Wireshark team for their assistance. In particular, the authors would like to thank:

- Gerald Combs, for initiating the Wireshark project and funding to do this documentation.
- Guy Harris, for many helpful hints and a great deal of patience in reviewing this document.
- Gilbert Ramirez, for general encouragement and helpful hints along the way.

The authors would also like to thank the following people for their helpful feedback on this document:

- Pat Eyler, for his suggestions on improving the example on generating a backtrace.
- Martin Regner, for his various suggestions and corrections.
- Graeme Hewson, for a lot of grammatical corrections.

The authors would like to acknowledge those man page and README authors for the Wireshark project from who sections of this document borrow heavily:

• Scott Renfro from whose **mergecap** man page <u>Section D.8</u>, "<u>mergecap</u>: <u>Merging multiple capture files</u> <u>into one</u>" is derived.

- Ashok Narayanan from whose **text2pcap** man page <u>Section D.9</u>, "<u>text2pcap</u>: <u>Converting ASCII</u> <u>hexdumps to network captures</u>" is derived.
- Frank Singleton from whose README.idl2wrs <u>Section D.10</u>, "idl2wrs: <u>Creating dissectors from</u> <u>CORBA IDL files</u>" is derived.

# 4. About this document

This book was originally developed by <u>Richard Sharpe</u> with funds provided from the Wireshark Fund. It was updated by <u>Ed Warnicke</u> and more recently redesigned and updated by <u>Ulf Lamping</u>.

It is written in DocBook/XML.

You will find some specially marked parts in this book:



This is a warning!

You should pay attention to a warning, as otherwise data loss might occur.



This is a note!

A note will point you to common mistakes and things that might not be obvious.



This is a tip!

Tips will be helpful for your everyday work using Wireshark.

# 5. Where to get the latest copy of this document?

The latest copy of this documentation can always be found at: <u>http://www.wireshark.org/docs/</u>.

# 6. Providing feedback about this document

Should you have any feedback about this document, please send it to the authors through <u>wireshark-dev[AT]wireshark.org</u>.

# **Chapter 1. Introduction**

# 1.1. What is Wireshark?

Wireshark is a network packet analyzer. A network packet analyzer will try to capture network packets and tries to display that packet data as detailed as possible.

You could think of a network packet analyzer as a measuring device used to examine what's going on inside a network cable, just like a voltmeter is used by an electrician to examine what's going on inside an electric cable (but at a higher level, of course).

In the past, such tools were either very expensive, proprietary, or both. However, with the advent of Wireshark, all that has changed.

Wireshark is perhaps one of the best open source packet analyzers available today.

## 1.1.1. Some intended purposes

Here are some examples people use Wireshark for:

- network administrators use it to troubleshoot network problems
- network security engineers use it to **examine security problems**
- developers use it to debug protocol implementations
- people use it to **learn network protocol** internals

Beside these examples, Wireshark can be helpful in many other situations too.

## 1.1.2. Features

The following are some of the many features Wireshark provides:

- Available for **UNIX** and **Windows**.
- **Capture** live packet data from a network interface.
- Display packets with very detailed protocol information.
- Open and Save packet data captured.
- **Import and Export** packet data from and to a lot of other capture programs.
- Filter packets on many criteria.
- Search for packets on many criteria.
- Colorize packet display based on filters.
- Create various statistics.
- ... and a lot more!

However, to really appreciate its power, you have to start using it.

Figure 1.1, "Wireshark captures packets and allows you to examine their content." shows Wireshark having captured some packets and waiting for you to examine them.

🗖 te																				
_		· ·																		
Eile	Edit	⊻iew	Go	Capture	e <u>A</u> nalya	ze <u>S</u> ta	itistics	Telepho	n <u>y</u> <u>⊺</u> oc	ols <u>I</u> n	iternals	Help								
8	ë.	94 6	M 🕅		<b>3</b> ×	2	8	् 🔶	•	2 7	- ⊉		⊕ (	a Q	m   è	¥ 🖹	8	×   🕽	<b>İ</b>	
Filter	•										🖌 E	Expression	Clear	Apply						
No.		Time		Sour				Destina				Protocol								^
		0.00			.168.0				dcast			ARP			itous					
		0.29			.168.0				168.0			NBNS			query					
		0.29			.168.0				168.0			ICMP			nation					
		1.02			.168.0				0.0.2	-		IGMP			mbersh					
		1.04			.168.0				168.0			DNS			ard qu			Idap	_tcp.nl	bç
		1.04			.168.0				255.2		50	SSDP			RCH *					
		1.05			.168.0				168.0			DNS			ard qu		A ni	510061	La.wwo	04
		1.05			.168.0				168.0			SSDP			1.1 20		-1.04		· • ·	
		1.08			.168.0				168.0			NBNS			tratio					
		1.11			.168.0				168.0			DNS			ard qu					
		1.22			.168.0				168.0 168.0			TCP			> htt > ncu-					
	12	1.22	1202	192	.100.0	/. ±		192	100.0	• 4		TCP	00	neep	z neu-	Z LOTN	, A	-V] 26		
																				>
												red (496								~
												t: Netge					d:75	5:9a)		
												t: 192.1						_		_
∣⊡⊤							, sro	Port	: ncu	-2 (	3196),	, Dst Po	rt: hi	tp (8	0), se	q: 0,	Len:	: 0		
					-2 (31															≡
					: http	(80)														
				ex: 5]		(	+ 4			. un la m	- `									
				mber:	u 3 byte:		cive	seque	nce n	umpe	r)									
				(SYN		5			_											- 11
l *					) ⊇: 6424	10														V
																				¥
0000					9a 00			cd 02				[-u								
0010					00 80 50 3c			CO a8				.0.Н@								
0020					00 02			01 01			/ 02		(6	p.						
1	•	•				- · ·		••												
	المر الح	Uhaah -		KB 00:00	1.02		D-	-koka, 10	0 Disel-	undi 40	O Made	d. O Lond See	. 0.00 0	00	Dec fil	e: Default				
	ile: "C	:/cest.c	ap 14	KB UU:UU	1:02		Ра	EKets: 12	U Displa;	yea: 12	:u marke	d: O Load tim	e: 0:00.0	00	Profile	e: Derauit				

Figure 1.1. Wireshark captures packets and allows you to examine their content.

## 1.1.3. Live capture from many different network media

Wireshark can capture traffic from many different network media types - and despite its name - including wireless LAN as well. Which media types are supported, depends on many things like the operating system you are using. An overview of the supported media types can be found at: <u>http://wiki.wireshark.org/</u> <u>CaptureSetup/NetworkMedia</u>.

## 1.1.4. Import files from many other capture programs

Wireshark can open packets captured from a large number of other capture programs. For a list of input formats see <u>Section 5.2.2</u>, "Input File Formats".

## 1.1.5. Export files for many other capture programs

Wireshark can save packets captured in a large number of formats of other capture programs. For a list of output formats see <u>Section 5.3.2</u>, "Output File Formats".

## 1.1.6. Many protocol decoders

There are protocol decoders (or dissectors, as they are known in Wireshark) for a great many protocols: see <u>Appendix B</u>, <u>*Protocols and Protocol Fields*</u>.

## 1.1.7. Open Source Software

Wireshark is an open source software project, and is released under the <u>GNU General Public License</u> (GPL). You can freely use Wireshark on any number of computers you like, without worrying about license keys or fees or such. In addition, all source code is freely available under the GPL. Because of that, it is very easy for people to add new protocols to Wireshark, either as plugins, or built into the source, and they often do!

## 1.1.8. What Wireshark is not

Here are some things Wireshark does not provide:

- Wireshark isn't an intrusion detection system. It will not warn you when someone does strange things on your network that he/she isn't allowed to do. However, if strange things happen, Wireshark might help you figure out what is really going on.
- Wireshark will not manipulate things on the network, it will only "measure" things from it. Wireshark doesn't send packets on the network or do other active things (except for name resolutions, but even that can be disabled).

# **1.2. System Requirements**

What you'll need to get Wireshark up and running ...

## 1.2.1. General Remarks

- The values below are the minimum requirements and only "rules of thumb" for use on a moderately used network
- Working with a busy network can easily produce huge memory and disk space usage! For example: Capturing on a fully saturated 100MBit/s Ethernet will produce ~ 750MBytes/min! Having a fast processor, lots of memory and disk space is a good idea in that case.
- If Wireshark is running out of memory it crashes, see: <u>http://wiki.wireshark.org/KnownBugs/</u> <u>OutOfMemory</u> for details and workarounds
- Wireshark won't benefit much from Multiprocessor/Hyperthread systems as time consuming tasks like filtering packets are single threaded. No rule is without exception: during an "Update list of packets in real time" capture, capturing traffic runs in one process and dissecting and displaying packets runs in another process which should benefit from two processors.

## **1.2.2. Microsoft Windows**

- Windows XP Home, XP Pro, XP Tablet PC, XP Media Center, Server 2003, Vista, 2008, 7, or 2008 R2
- Any modern 32-bit x86 or 64-bit AMD64/x86-64 processor.
- 128MB available RAM. Larger capture files require more RAM.
- 75MB available disk space. Capture files require additional disk space.
- 800\*600 (1280\*1024 or higher recommended) resolution with at least 65536 (16bit) colors (256 colors should work if Wireshark is installed with the "legacy GTK1" selection of the Wireshark 1.0.x releases)

- A supported network card for capturing:
  - Ethernet: Any card supported by Windows should work. See the wiki pages on <u>Ethernet capture</u> and <u>offloading</u> for issues that may affect your environment.
  - 802.11: See the <u>Wireshark wiki page</u>. Capturing raw 802.11 information may be difficult without special equipment.
  - Other media: See http://wiki.wireshark.org/CaptureSetup/NetworkMedia

#### Remarks:

- Many older Windows versions are no longer supported for three reasons: None of the developers use those systems which makes support difficult. The libraries Wireshark depends on (GTK, WinPcap, ...) have dropped support for older releases. Microsoft has also dropped support for these systems.
- Windows 95, 98 and ME are no longer supported. The "old technology" releases of Windows lack memory protection (specifically <u>VirtualProtect</u>) which we use to improve program safety and security. The last known version to work was Ethereal 0.10.14 (which includes WinPcap 3.1). You can get it from <u>http://ethereal.com/download.html</u>. According to <u>this bug report</u>, you may need to install Ethereal 0.10.0 on some systems.

Microsoft retired support for Windows 98 and ME in 2006.

• Windows NT 4.0 no longer works with Wireshark. The last known version to work was Wireshark 0.99.4 (which includes WinPcap 3.1). You still can get it from <a href="http://www.wireshark.org/download/win32/all-versions/wireshark-setup-0.994">http://www.wireshark.org/download/win32/all-versions/wireshark-setup-0.994</a>.

Microsoft retired support for Windows NT 4.0 in 2004.

• Windows 2000 no longer works with Wireshark. The last known version to work was Wireshark 1.2.x (which includes WinPcap 4.1.2). You still can get it from <a href="http://www.wireshark.org/download/win32/all-versions/">http://www.wireshark.org/download/win32/all-versions/</a>.

Microsoft retired support for Windows 2000 in 2010.

- Windows CE and the embedded versions of Windows are not currently supported.
- Multiple monitor setups are supported but may behave a bit strangely.

### 1.2.3. Unix / Linux

Wireshark currently runs on most UNIX platforms. The system requirements should be comparable to the Windows values listed above.

Binary packages are available for at least the following platforms:

- Apple Mac OS X
- Debian GNU/Linux
- FreeBSD
- Gentoo Linux
- HP-UX
- Mandriva Linux

- NetBSD
- OpenPKG
- Red Hat Enterprise/Fedora Linux
- rPath Linux
- Sun Solaris/i386
- Sun Solaris/Sparc
- Canonical Ubuntu

If a binary package is not available for your platform, you should download the source and try to build it. Please report your experiences to <u>wireshark-dev[AT]wireshark.org</u>.

# **1.3. Where to get Wireshark?**

You can get the latest copy of the program from the Wireshark website: <u>http://www.wireshark.org/</u><u>download.html</u>. The website allows you to choose from among several mirrors for downloading.

A new Wireshark version will typically become available every 4-8 months.

If you want to be notified about new Wireshark releases, you should subscribe to the wireshark-announce mailing list. You will find more details in <u>Section 1.6.5</u>, "<u>Mailing Lists</u>".

# **1.4. A brief history of Wireshark**

In late 1997, Gerald Combs needed a tool for tracking down networking problems and wanted to learn more about networking, so he started writing Ethereal (the former name of the Wireshark project) as a way to solve both problems.

Ethereal was initially released, after several pauses in development, in July 1998 as version 0.2.0. Within days, patches, bug reports, and words of encouragement started arriving, so Ethereal was on its way to success.

Not long after that, Gilbert Ramirez saw its potential and contributed a low-level dissector to it.

In October, 1998, Guy Harris of Network Appliance was looking for something better than tcpview, so he started applying patches and contributing dissectors to Ethereal.

In late 1998, Richard Sharpe, who was giving TCP/IP courses, saw its potential on such courses, and started looking at it to see if it supported the protocols he needed. While it didn't at that point, new protocols could be easily added. So he started contributing dissectors and contributing patches.

The list of people who have contributed to the project has become very long since then, and almost all of them started with a protocol that they needed that Wireshark or Ethereal did not already handle. So they copied an existing dissector and contributed the code back to the team.

In 2006 the project moved house and re-emerged under a new name: Wireshark.

In 2008, after ten years of development, Wireshark finally arrived at version 1.0. This release was the first deemed complete, with the minimum features implemented. Its release coincided with the first Wireshark Developer and User Conference, called SharkFest.

# **1.5. Development and maintenance of Wireshark**

Wireshark was initially developed by Gerald Combs. Ongoing development and maintenance of Wireshark is handled by the Wireshark team, a loose group of individuals who fix bugs and provide new functionality.

There have also been a large number of people who have contributed protocol dissectors to Wireshark, and it is expected that this will continue. You can find a list of the people who have contributed code to Wireshark by checking the about dialog box of Wireshark, or at the <u>authors</u> page on the Wireshark web site.

Wireshark is an open source software project, and is released under the <u>GNU General Public License</u> (GPL). All source code is freely available under the GPL. You are welcome to modify Wireshark to suit your own needs, and it would be appreciated if you contribute your improvements back to the Wireshark team.

You gain three benefits by contributing your improvements back to the community:

- Other people who find your contributions useful will appreciate them, and you will know that you have helped people in the same way that the developers of Wireshark have helped people.
- The developers of Wireshark might improve your changes even more, as there's always room for improvement. Or they may implement some advanced things on top of your code, which can be useful for yourself too.
- The maintainers and developers of Wireshark will maintain your code as well, fixing it when API changes or other changes are made, and generally keeping it in tune with what is happening with Wireshark. So if Wireshark is updated (which is done often), you can get a new Wireshark version from the website and your changes will already be included without any effort for you.

The Wireshark source code and binary kits for some platforms are all available on the download page of the Wireshark website: <u>http://www.wireshark.org/download.html</u>.

# 1.6. Reporting problems and getting help

If you have problems, or need help with Wireshark, there are several places that may be of interest to you (well, besides this guide of course).

## 1.6.1. Website

You will find lots of useful information on the Wireshark homepage at http://www.wireshark.org.

## 1.6.2. Wiki

The Wireshark Wiki at <u>http://wiki.wireshark.org</u> provides a wide range of information related to Wireshark and packet capturing in general. You will find a lot of information not part of this user's guide. For example, there is an explanation how to capture on a switched network, an ongoing effort to build a protocol reference and a lot more.

And best of all, if you would like to contribute your knowledge on a specific topic (maybe a network protocol you know well), you can edit the wiki pages by simply using your web browser.

## 1.6.3. Q&A Forum

The Wireshark Q and A forum at <u>http://ask.wireshark.org</u> offers a resource where questions and answers come together. You have the option to search what questions were asked before and what answers were given by people who knew about the issue. Answers are graded, so you can pick out the best ones easily. If your issue isn't discussed before you can post one yourself.

## 1.6.4. FAQ

The "Frequently Asked Questions" will list often asked questions and the corresponding answers.



#### **Read the FAQ!**

Before sending any mail to the mailing lists below, be sure to read the FAQ, as it will often answer the question(s) you might have. This will save yourself and others a lot of time (keep in mind that a lot of people are subscribed to the mailing lists).

You will find the FAQ inside Wireshark by clicking the menu item Help/Contents and selecting the FAQ page in the dialog shown.

An online version is available at the Wireshark website: <u>http://www.wireshark.org/faq.html</u>. You might prefer this online version, as it's typically more up to date and the HTML format is easier to use.

## 1.6.5. Mailing Lists

There are several mailing lists of specific Wireshark topics available:

wireshark-announce	This mailing list will inform you about new program releases, which usually appear about every 4-8 weeks.
wireshark-users	This list is for users of Wireshark. People post questions about building and using Wireshark, others (hopefully) provide answers.
wireshark-dev	This list is for Wireshark developers. If you want to start developing a protocol dissector, join this list.

You can subscribe to each of these lists from the Wireshark web site: <u>http://www.wireshark.org</u>. Simply select the **mailing lists** link on the left hand side of the site. The lists are archived at the Wireshark web site as well.



#### Tip!

You can search in the list archives to see if someone asked the same question some time before and maybe already got an answer. That way you don't have to wait until someone answers your question.

## **1.6.6. Reporting Problems**



#### Note!

Before reporting any problems, please make sure you have installed the latest version of Wireshark.

When reporting problems with Wireshark, it is helpful if you supply the following information:

- 1. The version number of Wireshark and the dependent libraries linked with it, e.g. GTK+, etc. You can obtain this from the about dialog box of Wireshark, or with the command **wireshark -v**.
- 2. Information about the platform you run Wireshark on.
- 3. A detailed description of your problem.
- 4. If you get an error/warning message, copy the text of that message (and also a few lines before and after it, if there are some), so others may find the place where things go wrong. Please don't give something like: "I get a warning while doing x" as this won't give a good idea where to look at.



#### Don't send large files!

Do not send large files (>100KB) to the mailing lists, just place a note that further data is available on request. Large files will only annoy a lot of people on the list who are not interested in your specific problem. If required, you will be asked for further data by the persons who really can help you.



#### Don't send confidential information!

If you send captured data to the mailing lists, be sure they don't contain any sensitive or confidential information like passwords or such.

## 1.6.7. Reporting Crashes on UNIX/Linux platforms

When reporting crashes with Wireshark, it is helpful if you supply the traceback information (besides the information mentioned in "Reporting Problems").

You can obtain this traceback information with the following commands:

```
$ gdb `whereis wireshark | cut -f2 -d: | cut -d' ' -f2` core >& bt.txt
backtrace
^D
```





#### Note

Type the characters in the first line verbatim! Those are back-tics there!

1.1	
100	
100	

#### Note

backtrace is a **gdb** command. You should enter it verbatim after the first line shown above, but it will not be echoed. The ^D (Control-D, that is, press the Control key and the D key together) will cause **gdb** to exit. This will leave you with a file called bt.txt in the current directory. Include the file with your bug report.



#### Note

If you do not have **gdb** available, you will have to check out your operating system's debugger.

You should mail the traceback to the wireshark-dev[AT]wireshark.org mailing list.

## **1.6.8. Reporting Crashes on Windows platforms**

The Windows distributions don't contain the symbol files (.pdb), because they are very large. For this reason it's not possible to create a meaningful backtrace file from it. You should report your crash just like other problems, using the mechanism described above.

# Chapter 2. Building and Installing Wireshark

# 2.1. Introduction

As with all things, there must be a beginning, and so it is with Wireshark. To use Wireshark, you must:

- Obtain a binary package for your operating system, or
- Obtain the source and build Wireshark for your operating system.

Currently, several Linux distributions ship Wireshark, but they are commonly shipping an out-of-date version. No other versions of UNIX ship Wireshark so far, and Microsoft does not ship it with any version of Windows. For that reason, you will need to know where to get the latest version of Wireshark and how to install it.

This chapter shows you how to obtain source and binary packages, and how to build Wireshark from source, should you choose to do so.

The following are the general steps you would use:

- 1. Download the relevant package for your needs, e.g. source or binary distribution.
- 2. Build the source into a binary, if you have downloaded the source.

This may involve building and/or installing other necessary packages.

3. Install the binaries into their final destinations.

# **2.2.** Obtaining the source and binary distributions

You can obtain both source and binary distributions from the Wireshark web site: <u>http://</u><u>www.wireshark.org</u>. Simply select the download link, and then select either the source package or binary package of your choice from the mirror site closest to you.



#### Download all required files!

In general, unless you have already downloaded Wireshark before, you will most likely need to download several source packages if you are building Wireshark from source. This is covered in more detail below.

Once you have downloaded the relevant files, you can go on to the next step.



#### Note!

While you will find a number of binary packages available on the Wireshark web site, you might not find one for your platform, and they often tend to be several versions behind the

current released version, as they are contributed by people who have the platforms they are built for.

For this reason, you might want to pull down the source distribution and build it, as the process is relatively simple.

# 2.3. Before you build Wireshark under UNIX

Before you build Wireshark from sources, or install a binary package, you must ensure that you have the following other packages installed:

• GTK+, The GIMP Tool Kit.

You will also need Glib. Both can be obtained from www.gtk.org

• libpcap, the packet capture software that Wireshark uses.

You can obtain libpcap from <u>www.tcpdump.org</u>

Depending on your system, you may be able to install these from binaries, e.g. RPMs, or you may need to obtain them in source code form and build them.

If you have downloaded the source for GTK+, the instructions shown in Example 2.1, "Building GTK+ from source" may provide some help in building it:

#### **Example 2.1. Building GTK+ from source**

```
gzip -dc gtk+-2.21.1.tar.gz | tar xvf -
<much output removed>
cd gtk+-2.21.1
./configure
<much output removed>
make
<much output removed>
make install
<much output removed>
```



#### Note!

You may need to change the version number of GTK+ in Example 2.1, "Building GTK+ from source" to match the version of GTK+ you have downloaded. The directory you change to will change if the version of GTK+ changes, and in all cases, **tar xvf** - will show you the name of the directory you should change to.



#### Note!

If you use Linux, or have GNU **tar** installed, you can use **tar zxvf gtk+-2.21.1.tar.gz**. It is also possible to use **gunzip -c** or **gzcat** rather than **gzip -dc** on many UNIX systems.



#### Note!

If you downloaded GTK+ or any other tar file using Windows, you may find your file called gtk+-2\_21\_1\_tar.gz.

You should consult the GTK+ web site if any errors occur in carrying out the instructions in Example 2.1, "Building GTK+ from source".

If you have downloaded the source to libpcap, the general instructions shown in <u>Example 2.2</u>, "<u>Building</u> and installing libpcap" will assist in building it. Also, if your operating system does not support **tcpdump**, you might also want to download it from the <u>tcpdump</u> web site and install it.

#### Example 2.2. Building and installing libpcap

```
gzip -dc libpcap-1.0.0.tar.Z | tar xvf -
<much output removed>
cd libpcap-1.0.0
./configure
<much output removed>
make
<much output removed>
make install
<much output removed>
```



#### Note!

The directory you should change to will depend on the version of libpcap you have downloaded. In all cases, **tar xvf** - will show you the name of the directory that has been unpacked.

Under Red Hat 6.x and beyond (and distributions based on it, like Mandrake) you can simply install each of the packages you need from RPMs. Most Linux systems will install GTK+ and GLib in any case, however you will probably need to install the devel versions of each of these packages. The commands shown in Example 2.3, "Installing required RPMs under Red Hat Linux 6.2 and beyond" will install all the needed RPMs if they are not already installed.

#### Example 2.3. Installing required RPMs under Red Hat Linux 6.2 and beyond

```
cd /mnt/cdrom/RedHat/RPMS
rpm -ivh glib-1.2.6-3.i386.rpm
rpm -ivh glib-devel-1.2.6-3.i386.rpm
rpm -ivh gtk+-1.2.6-7.i386.rpm
rpm -ivh gtk+-devel-1.2.6-7.i386.rpm
rpm -ivh libpcap-0.4-19.i386.rpm
```



#### Note

If you are using a version of Red Hat later than 6.2, the required RPMs have most likely changed. Simply use the correct RPMs from your distribution.

Under Debian you can install Wireshark using aptitude. aptitude will handle any dependency issues for you. <u>Example 2.4</u>, "Installing debs under Debian, Ubuntu and other Debian derivatives" shows how to do this.

#### Example 2.4. Installing debs under Debian, Ubuntu and other Debian derivatives

aptitude install wireshark-dev

# 2.4. Building Wireshark from source under UNIX

Use the following general steps if you are building Wireshark from source under a UNIX operating system:

1. Unpack the source from its **gzip**'d **tar** file. If you are using Linux, or your version of UNIX uses GNU **tar**, you can use the following command:

```
tar zxvf wireshark-1.9-tar.gz
```

For other versions of UNIX, you will want to use the following commands:

```
gzip -d wireshark-1.9-tar.gz
tar xvf wireshark-1.9-tar
```



#### Note!

The pipeline gzip -dc wireshark-1.9-tar.gz | tar xvf - will work here as well.



#### Note!

If you have downloaded the Wireshark tarball under Windows, you may find that your browser has created a file with underscores rather than periods in its file name.

- 2. Change directory to the Wireshark source directory.
- 3. Configure your source so it will build correctly for your version of UNIX. You can do this with the following command:

./configure

If this step fails, you will have to rectify the problems and rerun **configure**. Troubleshooting hints are provided in <u>Section 2.6</u>, "Troubleshooting during the install on Unix".

4. Build the sources into a binary, with the **make** command. For example:

make

5. Install the software in its final destination, using the command:

make install

Once you have installed Wireshark with **make install** above, you should be able to run it by entering **wireshark**.

# **2.5. Installing the binaries under UNIX**

In general, installing the binary under your version of UNIX will be specific to the installation methods used with your version of UNIX. For example, under AIX, you would use **smit** to install the Wireshark binary package, while under Tru64 UNIX (formerly Digital UNIX) you would use **setId**.

## 2.5.1. Installing from rpm's under Red Hat and alike

Use the following command to install the Wireshark RPM that you have downloaded from the Wireshark web site:

```
rpm -ivh wireshark-1.9.i386.rpm
```

If the above step fails because of missing dependencies, install the dependencies first, and then retry the step above. See <u>Example 2.3, "Installing required RPMs under Red Hat Linux 6.2 and beyond</u>" for information on what RPMs you will need to have installed.

# 2.5.2. Installing from deb's under Debian, Ubuntu and other Debian derivatives

If you can just install from the repository then use:

```
aptitude install wireshark
```

aptitude should take care of all of the dependency issues for you.

Use the following command to install downloaded Wireshark deb's under Debian:

dpkg -i wireshark-common\_1.9.0-1\_i386.deb wireshark\_1.9.0-1\_i386.deb

dpkg doesn't take care of all dependencies, but reports what's missing.



#### Note!

By installing Wireshark packages non-root users won't gain rights automatically to capture packets. To allow non-root users to capture packets follow the procedure described in <u>/usr/share/doc/wireshark-common/README.Debian</u>

## 2.5.3. Installing from portage under Gentoo Linux

Use the following command to install Wireshark under Gentoo Linux with all of the extra features:

USE="adns gtk ipv6 portaudio snmp ssl kerberos threads selinux" emerge wireshark

## 2.5.4. Installing from packages under FreeBSD

Use the following command to install Wireshark under FreeBSD:

pkg\_add -r wireshark

pkg\_add should take care of all of the dependency issues for you.

# 2.6. Troubleshooting during the install on Unix

A number of errors can occur during the installation process. Some hints on solving these are provided here.

If the **configure** stage fails, you will need to find out why. You can check the file config.log in the source directory to find out what failed. The last few lines of this file should help in determining the problem.

The standard problems are that you do not have GTK+ on your system, or you do not have a recent enough version of GTK+. The **configure** will also fail if you do not have libpcap (at least the required include files) on your system.

Another common problem is for the final compile and link stage to terminate with a complaint of: Output too long. This is likely to be caused by an antiquated **sed** (such as the one shipped with Solaris). Since **sed** is used by the **libtool** script to construct the final link command, this leads to mysterious problems. This can be resolved by downloading a recent version of sed from <u>http://directory.fsf.org/project/sed/</u>.

If you cannot determine what the problems are, send an email to the **wireshark-dev** mailing list explaining your problem, and including the output from config.log and anything else you think is relevant, like a trace of the **make** stage.

# 2.7. Building from source under Windows

It is recommended to use the binary installer for Windows, until you want to start developing Wireshark on the Windows platform.

For further information how to build Wireshark for Windows from the sources, have a look at the Developer's Guide on the <u>Documentation Page</u>.

You may also want to have a look at the Development Wiki: <u>http://wiki.wireshark.org/Development</u> for the latest available development documentation.

# 2.8. Installing Wireshark under Windows

In this section we explore installing Wireshark under Windows from the binary packages.

## 2.8.1. Install Wireshark

You may acquire a binary installer of Wireshark named something like: wireshark-winxx-1.9.x.exe. The Wireshark installer includes WinPcap, so you don't need to download and install two separate packages.

Simply download the Wireshark installer from: <u>http://www.wireshark.org/download.html</u> and execute it. Beside the usual installer options like where to install the program, there are several optional components.



#### Tip: Just keep the defaults!

If you are unsure which settings to select, just keep the defaults.

#### 2.8.1.1. "Choose Components" page

#### Wireshark

• Wireshark GTK - Wireshark is a GUI network protocol analyzer.

TShark - TShark is a command-line based network protocol analyzer.

**Plugins / Extensions** (for the Wireshark and TShark dissection engines):

- Dissector Plugins Plugins with some extended dissections.
- Tree Statistics Plugins Plugins with some extended statistics.
- Mate Meta Analysis and Tracing Engine (experimental) user configurable extension(s) of the display filter engine, see <a href="http://wiki.wireshark.org/Mate">http://wiki.wireshark.org/Mate</a> for details.
- **SNMP MIBs** SNMP MIBs for a more detailed SNMP dissection.

**Tools** (additional command line tools to work with capture files):

- Editcap Editcap is a program that reads a capture file and writes some or all of the packets into another capture file.
- **Text2Pcap** Text2pcap is a program that reads in an ASCII hex dump and writes the data into a libpcapstyle capture file.
- Mergecap Mergecap is a program that combines multiple saved capture files into a single output file.
- Capinfos Capinfos is a program that provides information on capture files.
- Rawshark Rawshark is a raw packet filter.

**User's Guide** - Local installation of the User's Guide. The Help buttons on most dialogs will require an internet connection to show help pages if the User's Guide is not installed locally.

#### 2.8.1.2. "Additional Tasks" page

- Start Menu Shortcuts add some start menu shortcuts.
- **Desktop Icon** add a Wireshark icon to the desktop.
- Quick Launch Icon add a Wireshark icon to the Explorer quick launch toolbar.
- Associate file extensions to Wireshark Associate standard network trace files to Wireshark.

#### 2.8.1.3. "Install WinPcap?" page

The Wireshark installer contains the latest released WinPcap installer.

If you don't have WinPcap installed, you won't be able to capture live network traffic, but you will still be able to open saved capture files.

- Currently installed WinPcap version the Wireshark installer detects the currently installed WinPcap version.
- **Install WinPcap x.x** if the currently installed version is older than the one which comes with the Wireshark installer (or WinPcap is not installed at all), this will be selected by default.

• Start WinPcap service "NPF" at startup - so users without administrative privileges can capture.

More WinPcap info:

- Wireshark related: http://wiki.wireshark.org/WinPcap
- General WinPcap info: <u>http://www.winpcap.org</u>

#### 2.8.1.4. Command line options

You can simply start the Wireshark installer without any command line parameters, it will show you the usual interactive installer.

For special cases, there are some command line parameters available:

- /NCRC disables the CRC check
- /S runs the installer or uninstaller silently with default values. Please note: The silent installer won't install WinPCap!
- /desktopicon installation of the desktop icon, =yes force installation, =no don't install, otherwise use defaults / user settings. This option can be useful for a silent installer.
- /quicklaunchicon installation of the quick launch icon, =yes force installation, =no don't install, otherwise use defaults / user settings.
- /D sets the default installation directory (\$INSTDIR), overriding InstallDir and InstallDirRegKey. It must be the last parameter used in the command line and must not contain any quotes, even if the path contains spaces.

Example:

```
wireshark-win32-1.9.0.exe /NCRC /S /desktopicon=yes
/quicklaunchicon=no /D=C:\Program Files\Foo
```

## 2.8.2. Manual WinPcap Installation



#### Note!

As mentioned above, the Wireshark installer takes care of the installation of WinPcap, so usually you don't have to worry about WinPcap at all!

The following is only necessary if you want to try a different version than the one included in the Wireshark installer, e.g. because a new WinPcap (beta) version was released.

Additional WinPcap versions (including newer alpha or beta releases) can be downloaded from the following locations:

- The main WinPcap site: <a href="http://www.winpcap.org">http://www.winpcap.org</a>
- The Wiretapped.net mirror: <u>http://www.mirrors.wiretapped.net/security/packet-capture/winpcap</u>

At the download page you will find a single installer exe called something like "auto-installer", which can be installed under various Windows systems, including NT4.0/2000/XP/2003/Vista/7/2008.

## 2.8.3. Update Wireshark

From time to time you may want to update your installed Wireshark to a more recent version. If you join Wireshark's announce mailing list, you will be informed about new Wireshark versions, see <u>Section 1.6.5</u>, <u>"Mailing Lists"</u> for details how to subscribe to this list.

New versions of Wireshark usually become available every 4 to 8 months. Updating Wireshark is done the same way as installing it, you simply download and start the installer exe. A reboot is usually not required and all your personal settings remain unchanged.

## 2.8.4. Update WinPcap

New versions of WinPcap are less frequently available, maybe only once in a year. You will find WinPcap update instructions where you can download new WinPcap versions. Usually you have to reboot the machine after installing a new WinPcap version.



### Warning!

If you have an older version of WinPcap installed, you must uninstall it before installing the current version. Recent versions of the WinPcap installer will take care of this.

## 2.8.5. Uninstall Wireshark

You can uninstall Wireshark the usual way, using the "Add or Remove Programs" option inside the Control Panel. Select the "Wireshark" entry to start the uninstallation procedure.

The Wireshark uninstaller will provide several options as to which things are to be uninstalled; the default is to remove the core components but keep the personal settings, WinPcap and alike.

WinPcap won't be uninstalled by default, as other programs than Wireshark may use it as well.

## 2.8.6. Uninstall WinPcap

You can uninstall WinPcap independently of Wireshark, using the "WinPcap" entry in the "Add or Remove Programs" of the Control Panel.



#### Note!

After uninstallation of WinPcap you can't capture anything with Wireshark.

It might be a good idea to reboot Windows afterwards.

# **Chapter 3. User Interface**

# 3.1. Introduction

By now you have installed Wireshark and are most likely keen to get started capturing your first packets. In the next chapters we will explore:

- How the Wireshark user interface works
- How to capture packets in Wireshark
- How to view packets in Wireshark
- How to filter packets in Wireshark
- ... and many other things!

# 3.2. Start Wireshark

You can start Wireshark from your shell or window manager.



### Tip!

When starting Wireshark it's possible to specify optional settings using the command line. See <u>Section 10.2</u>, "Start Wireshark from the command line" for details.



#### Note!

In the following chapters, a lot of screenshots from Wireshark will be shown. As Wireshark runs on many different platforms with many different window managers, different styles applied and there are different versions of the underlying GUI toolkit used, your screen might look different from the provided screenshots. But as there are no real differences in functionality, these screenshots should still be well understandable.

# 3.3. The Main window

Let's look at Wireshark's user interface. Figure 3.1, "The Main window" shows Wireshark as you would usually see it after some packets are captured or loaded (how to do this will be described later).

	test.c	ap															_ [	
Eile	Edit	⊻iew	<u>G</u> o	<u>C</u> apture	Analyze	e <u>S</u> tatist	tics Tele	ephon <u>y T</u>	ools <u>I</u> n	iternals	Help							
	<b>i</b>	<u>e</u> (0	1		<b>X</b>	22		🔶 🔿	4)	₽		€€		T   6	🏽 🗹 🛒	5 %		
Filte	er:									🕶 E	Expression	Clear /	Apply					
No.		Time		Sourc				stination			Protocol Le							~
		0.00			.168.0.			oadcas	-		ARP				ARP for			
		0.29		192	.168.0.	.1	19	92.168.	0.2		NBNS				NBSTAT			
		0.29			.168.0.			92.168.			ICMP				i unread			
		1.02			.168.0.			24.0.0.			IGMP				nip Repo			
		1.04			.168.0.			92.168.			DNS				ieny SRV		otcp.	nbç
		1.04			.168.0.			39.255.		50	SSDP				НТТР∕1.			
		1.05			.168.0.			92.168.			DNS				ieny soA	(nb100	)61d.ww	/004
		1.05			.168.0.			92.168.			SSDP			1.1 20				
		1.08			.168.0.			92.168.			NBNS				n NB NE			
		1.11			.168.0.			92.168.			DNS				ieny A p			
		1.22			.168.0.			92.168.			TCP				p [SYN]			
	12	1,22	7282	192	.168.0.	.1	19	92.168.	0.2		TCP	60	http	> ncu-	2 [SYN,	ACK]	Seq=0	Ack 🗠
$\leq$						111	1											>
ΞF	- rame	11:	62 k	ovtes	on wir	e (496	; bits	). 62 b	vtes	captur	ed (496	bits)						~
•	Ether	net :	II, S	5rc: 1	92.168	.0.2 (	(00:0b	:5d:20:	cd:02)	), Ds1	: Netgea	r_2d::	75:9a	(00:0	9:5b:2c	l:75:9a	i)	
• :	Inter	net I	Prote	col,	src: 1	92.168	3.0.2	(192.16	8.0.2	), Ds1	:: 192.16	8.0.1	(192	.168.0	.1)			
	Trans	miss	ion (	Iontro	l Prot	ocol,	She P	ort: no	u-2 ()	3196),	, Dst Por	t: ht	tp (8	0), se	q: 0, L	en: 0		
1 7	SOL	unce j	port	: ncu-	2 (319	6)												=
	Des	stinat	tion	port:	http	(80)												
				ex: 5]														
	Sec	quence	e nur	nber:	0 (	relati	ive se	quence	numbei	r)								
	Hea	ider i	lengt	:h: 28	bytes													
6	Ð Fla	igs: (	0x02	(SYN)	-													
	Wir	ndow :	size	value	: 6424	0												~
000					9a 00 0			02 08			[-u							
001					00 80 0			a8 00			.0.Н@							
002					50 3c 3 00 02 0			00 00		) 02	.P<0	o	p.					
003		aiv	27 E		00 02 1	- UJ	04 UI	. 01 04	92				••					
	File: "C	:/test.c/	an" 14	KB 00:00	:02		Packet	s: 120 Disol	aved: 12	20 Marke	d: O Load time:	: 0:00.00	n	Profi	le: Default			
							T dendet.	. reconspi			2. 0 2000 cmbs	. 5155100	-	Tron	or portadic			

Figure 3.1. The Main window

Wireshark's main window consists of parts that are commonly known from many other GUI programs.

- 1. The menu (see Section 3.4, "The Menu") is used to start actions.
- 2. The *main toolbar* (see Section 3.16, "The "Main" toolbar") provides quick access to frequently used items from the menu.
- 3. The *filter toolbar* (see Section 3.17, "The "Filter" toolbar") provides a way to directly manipulate the currently used display filter (see Section 6.3, "Filtering packets while viewing").
- 4. The *packet list pane* (see Section 3.18, "The "Packet List" pane") displays a summary of each packet captured. By clicking on packets in this pane you control what is displayed in the other two panes.
- 5. The *packet details pane* (see Section 3.19, "The "Packet Details" pane") displays the packet selected in the packet list pane in more detail.
- 6. The *packet bytes pane* (see Section 3.20, "The "Packet Bytes" pane") displays the data from the packet selected in the packet list pane, and highlights the field selected in the packet details pane.
- 7. The *statusbar* (see <u>Section 3.21, "The Statusbar</u>") shows some detailed information about the current program state and the captured data.



#### Tip!

The layout of the main window can be customized by changing preference settings. See <u>Section 10.5, "Preferences"</u> for details!

## **3.3.1. Main Window Navigation**

Packet list and detail navigation can be done entirely from the keyboard. <u>Table 3.1, "Keyboard Navigation</u>" shows a list of keystrokes that will let you quickly move around a capture file. See <u>Table 3.5, "Go menu</u> <u>items</u>" for additional navigation keystrokes.

Accelerator	Description
Tab, Shift+Tab	Move between screen elements, e.g. from the toolbars to the packet list to the packet detail.
Down	Move to the next packet or detail item.
Up	Move to the previous packet or detail item.
Ctrl+Down, F8	Move to the next packet, even if the packet list isn't focused.
Ctrl+Up, F7	Move to the previous packet, even if the packet list isn't focused.
Ctrl+.	Move to the next packet of the conversation (TCP, UDP or IP)
Ctrl+,	Move to the previous packet of the conversation (TCP, UDP or IP)
Left	In the packet detail, closes the selected tree item. If it's already closed, jumps to the parent node.
Right	In the packet detail, opens the selected tree item.
Shift+Right	In the packet detail, opens the selected tree item and all of its subtrees.
Ctrl+Right	In the packet detail, opens all tree items.
Ctrl+Left	In the packet detail, closes all tree items.
Backspace	In the packet detail, jumps to the parent node.
Return, Enter	In the packet detail, toggles the selected tree item.

Additionally, typing anywhere in the main window will start filling in a display filter.

# 3.4. The Menu

The Wireshark menu sits on top of the Wireshark window. An example is shown in Figure 3.2, "The Menu".



#### Note!

Menu items will be greyed out if the corresponding feature isn't available. For example, you cannot save a capture file if you didn't capture or load any data before.

#### Figure 3.2. The Menu

<u>File Edit View Go Capture Analyze Statistics Telephony</u> Tools Internals <u>H</u>elp

It contains the following items:

**File** This menu contains items to open and merge capture files, save / print / export capture files in whole or in part, and to quit from Wireshark. See <u>Section 3.5, "The "File" menu"</u>.

Edit	This menu contains items to find a packet, time reference or mark one or more packets, handle configuration profiles, and set your preferences; (cut, copy, and paste are not presently implemented). See <u>Section 3.6</u> , "The "Edit" menu".
View	This menu controls the display of the captured data, including colorization of packets, zooming the font, showing a packet in a separate window, expanding and collapsing trees in packet details, See <u>Section 3.7</u> , "The "View" menu".
Go	This menu contains items to go to a specific packet. See <u>Section 3.8</u> , "The "Go" menu".
Capture	This menu allows you to start and stop captures and to edit capture filters. See <u>Section 3.9</u> , <u>"The "Capture" menu"</u> .
Analyze	This menu contains items to manipulate display filters, enable or disable the dissection of protocols, configure user specified decodes and follow a TCP stream. See <u>Section 3.10</u> , <u>"The "Analyze" menu"</u> .
Statistics	This menu contains items to display various statistic windows, including a summary of the packets that have been captured, display protocol hierarchy statistics and much more. See <u>Section 3.11, "The "Statistics" menu</u> ".
Telephony	This menu contains items to display various telephony related statistic windows, including a media analysis, flow diagrams, display protocol hierarchy statistics and much more. See <u>Section 3.12, "The "Telephony" menu"</u> .
Tools	This menu contains various tools available in Wireshark, such as creating Firewall ACL Rules. See <u>Section 3.13, "The "Tools" menu"</u> .
Internals	This menu contains items that show information about the internals of Wireshark. See <u>Section 3.14, "The "Internals" menu"</u> .
Help	This menu contains items to help the user, e.g. access to some basic help, manual pages of the various command line tools, online access to some of the webpages, and the usual about dialog. See <u>Section 3.15</u> , "The "Help" menu".

Each of these menu items is described in more detail in the sections that follow.



#### Tip!

You can access menu items directly or by pressing the corresponding accelerator keys which are shown at the right side of the menu. For example, you can press the Control (or Strg in German) and the K keys together to open the capture dialog.

# 3.5. The "File" menu

The Wireshark file menu contains the fields shown in Table 3.2, "File menu items".

_												
1	test.ca	р										
Eile	Edit	⊻iew <u>G</u> o	<u>C</u> apture	<u>A</u> nalyz	e <u>S</u> tatist	ics Telephon <u>y</u>	Tools Internal	s <u>H</u> elp				
	Open		C	trl+0	24	0 🦕 🥧	🔹 주 🕹			- 🖬 🖬 🌆	* 183	
	Open <u>R</u> e	ecent		•					-, -, -, _		06.1620	
	Merge						~	Expression	Clear Apply			
	Import.					Destination		Protocol	Length Info			~
×	⊆lose		Ct	rl+W	.2	Broadca		ARP		ous ARP for		
	Save			itrl+5	.1	192.168		NBNS		iery NBSTAT '		
	_				. 2	192.168		ICMP		ation unreach		
đ	Save <u>A</u> s		Shift+C		.2 .2	224.0.0 192.168		IGMP		pership Repor		
	File Set				.2 .2		.0.1	DNS		rd query SRV H * HTTP∕1.1		. nbc
							.233.230	DNS		d query SOA		v004
_	<u>E</u> xport			•	File	ed Packet Bytes	. Ctrl+H	SSDP	337 HTTP/1.		TIDE VOID. W	
	Print		C	trl+P	Object		Cm+H	HTTP		ation NB NB1	L0061D<00>	
_				[		102.100		DICOM	87 Standar	'd queny A pr	oxyconf.ww	004.
	Quit			trl+Q		192.168		SMB		≻ http [SYN]		
	12 1	L.227282	2 192.1	168.0	.1	192.168	.0.2	200	60 http >	ncu-2 [SYN,	ACK] Seq=0	Ack 🗸
$\leq$												>
						bits), 62						~
									ar_2d:75:9a (		:75:9a)	
									68.0.1 (192.1			
						src Port: n	CU-2 (3196	), DST PO	rt: http (80)	I, Seq: V, Le	en: U	
			: ncu–2 ) port:									=
		eam inc		neep	(00)							
	-		umber: 0		relati	ve sequence	number)					
			th: 28									
6		js: 0x02										
	Wind	low size	e value:	6424	10							~
000	00 00	09 5b	2d 75 9a	a 00	0b 5d	20 cd 02 08	3 00 45 00	[-u	. ]E.			
001			48 40 00			2c c0 a8 00			. a,			
002			7c 00 50 e0 00 00			f8 00 00 00 b4 01 01 04		•••¦••	<6p.			
203	a	/			., .,	2. 01 01 0-						
	File: "C+A	test can" 14	KB 00:00:0	2		Packets: 120 Dis	played: 120 Marl	ked: 0 Load time	e: 0:00.000	Profile: Default		

#### Figure 3.3. The "File" Menu

#### Table 3.2. File menu items

Menu Item	Accelerator	Description
Open	Ctrl+O	This menu item brings up the file open dialog box that allows you to load a capture file for viewing. It is discussed in more detail in Section 5.2.1, "The "Open Capture File" dialog box".
Open Recent		This menu item shows a submenu containing the recently opened capture files. Clicking on one of the submenu items will open the corresponding capture file directly.
Merge		This menu item brings up the merge file dialog box that allows you to merge a capture file into the currently loaded one. It is discussed in more detail in <u>Section 5.4</u> , "Merging capture files".
Import		This menu item brings up the import file dialog box that allows you to import a text file into a new temporary capture. It is discussed in more detail in <u>Section 5.5</u> , "Import text file".
Close	Ctrl+W	This menu item closes the current capture. If you haven't saved the capture, you will be asked to do so first (this can be disabled by a preference setting).
Save	Ctrl+S	This menu item saves the current capture. If you have not set a default capture file name (perhaps with the -w <capfile> option), Wireshark pops up the Save Capture File As dialog box (which</capfile>

Menu Item	Accelerator	Description					
		is discussed further in <u>Section 5.3.1</u> , "The "Save Capture File As" <u>dialog box</u> ").					
		Note! If you have already saved the current capture, this					
		menu item will be greyed out.					
		You cannot save a live capture while the capture is in progress. You must stop the capture in order to save.					
Save As	Shift+Ctrl+S	This menu item allows you to save the current capture file to whatever file you would like. It pops up the Save Capture File As dialog box (which is discussed further in <u>Section 5.3.1, "The "Save Capture File As" dialog box</u> ").					
File Set > List Files		This menu item allows you to show a list of files in a file set. It pops up the Wireshark List File Set dialog box (which is discussed further in Section 5.6, "File Sets").					
File Set > Next File		If the currently loaded file is part of a file set, jump to the next file in the set. If it isn't part of a file set or just the last file in that set, this item is greyed out.					
FileSet>Previous File		If the currently loaded file is part of a file set, jump to the previous file in the set. If it isn't part of a file set or just the first file in that set, this item is greyed out.					
Export > File		This menu item allows you to export all (or some) of the packets in the capture file to file. It pops up the Wireshark Export dialog box (which is discussed further in <u>Section 5.7, "Exporting data"</u> ).					
Export > Selected Packet Bytes	Ctrl+H	This menu item allows you to export the currently selected bytes in the packet bytes pane to a binary file. It pops up the Wireshark Export dialog box (which is discussed further in <u>Section 5.7.7,</u> "The "Export selected packet bytes" dialog box")					
Export > Objects > HTTP		This menu item allows you to export all or some of the captured HTTP objects into local files. It pops up the Wireshark HTTP object list (which is discussed further in <u>Section 5.7.8</u> , "The "Export Objects" dialog box")					
Export > Objects > DICOM		This menu item allows you to export all or some of the captured DICOM objects into local files. It pops up the Wireshark DICOM object list (which is discussed further in <u>Section 5.7.8, "The</u> "Export Objects" dialog box")					
Export > Objects > SMB		This menu item allows you to export all or some of the captured SMB objects into local files. It pops up the Wireshark SMB object list (which is discussed further in <u>Section 5.7.8</u> , "The "Export Objects" dialog box")					

Menu Item	Accelerator	Description
Print	Ctrl+P	This menu item allows you to print all (or some) of the packets in the capture file. It pops up the Wireshark Print dialog box (which is discussed further in <u>Section 5.8</u> , "Printing packets").
Quit	Ctrl+Q	This menu item allows you to quit from Wireshark. Wireshark will ask to save your capture file if you haven't previously saved it (this can be disabled by a preference setting).

# 3.6. The "Edit" menu

The Wireshark Edit menu contains the fields shown in Table 3.3, "Edit menu items".

🔼 te	🔽 test.cap															
Eile	Edit	⊻iew <u>G</u> o	⊆apture	<u>A</u> nalyze	Statistic	s Telephor	n <u>y T</u> oo	ols <u>I</u> nternal	s <u>H</u> elp							
₿(		Сору					•	o ₮ 🕹		⊕€	0	<b>¥</b>	¥ 🖪	%   0		
Filter		Eind Packet. Find Ne <u>x</u> t					Itrl+F Itrl+N	~	Expression	Clear 4	pply					
No.		Find Pre <u>v</u> iou	s			0	Etrl+B		Protocol ARP	Length I	nfo Gratuito			100 160		
		<u>M</u> ark Packet					trl+M	. 2	NBNS	92 (	Name que	eny NBS	STAT *	<00><00	0><00><	< <mark>(</mark>
		Toggle Mark	-		kets	Shift+Ctrl+		.1	ICMP		Destinat					
		Mark All Disp	•			Shift+C		2	IGMP		/3 Membe					
		Unmark All D		:kets				.1	DNS		Standard				_tcp.nb	DÇ
		Find Next M						55.250	SSDP		1-SEARCH					
		Find Previou	s Mark			Shift+(	Itrl+B	.1	DNS		Standard			nb1006	Ld.ww00	24
		Ignore Pack					trl+D	.2 .255	SSDP NBNS	110	HTTP/1.1 Registra	tion M	VB NB1			
		Ignore All Di Un-Ignore A	9	Shift+Ctrl+D Ctrl+Alt+D	.1	DNS		Standard								
		Un-Ignore A				.1	TCP		ncu-2 >							
	0	🕓 Set Time Reference (toggle)				0	Etrl+T	.2	TCP	60	nttp > r	ncu-2	LSYN,	ACKJ SO		
		Un-Time Ref	erence All Pa	ackets		Ctrl+	Alt+T									>
⊕ FI		Find Next Ti	me Referenc	e		Ctrl+Alt+N			ured (496							~
⊕ E' ⊕ II		Find Previou		Ctrl+	Alt+B		st: Netge st: 192.1					75:9a)				
Π		<u>C</u> onfiguratio		Shift+(	ft+Ctrl+A _2 (3196), Dst Port: http (80), Seq: 0, Len: 0											
	*	Preferences				Shift+(	Itrl+P									=
Destination port: http (80) [stream index: 5] Sequence number: 0 (relative sequence number) Header length: 28 bytes																
I <sup>⊕</sup>		ngs: 0x0 ndow siz		64240												
										-						¥
0000 0010 0020 0030	0	0 09 5b 0 30 18 0 01 0c a f0 27	48 40 C 7c 00 5	0 80 06 0 3c 36	5 61 5 95	20 cd 02 2c c0 a8 f8 00 00 b4 01 01	3 00 ( ) 00 (	02 CO a8	.O.H@.	] a, <6						
🔴 Fi	e: "C	:/test.cap" 1	4 KB 00:00:	02		Packets: 12	0 Displa	ved: 120 Mar	ked: O Load tim	ne: 0:00.00	)	Profile: D	efault			

#### Figure 3.4. The "Edit" Menu

#### Table 3.3. Edit menu items

Menu Item	Accelerator	Description
Copy > Description	Shift+Ctrl+D	This menu item will copy the description of the selected item in the detail view to the clipboard.
Copy > Fieldname	Shift+Ctrl+F	This menu item will copy the fieldname of the selected item in the detail view to the clipboard.
Copy > Value	Shift+Ctrl+V	This menu item will copy the value of the selected item in the detail view to the clipboard.

Menu Item	Accelerator	Description
Copy > As Filter	Shift+Ctrl+C	This menu item will use the selected item in the detail view to create a display filter. This display filter is then copied to the clipboard.
Find Packet	Ctrl+F	This menu item brings up a dialog box that allows you to find a packet by many criteria. There is further information on finding packets in <u>Section 6.8</u> , "Finding packets".
Find Next	Ctrl+N	This menu item tries to find the next packet matching the settings from "Find Packet".
Find Previous	Ctrl+B	This menu item tries to find the previous packet matching the settings from "Find Packet".
Mark Packet (toggle)	Ctrl+M	This menu item "marks" the currently selected packet. See <u>Section 6.10, "Marking packets"</u> for details.
Toggle Marking Of All Displayed Packets	Shift+Ctrl+Alt+M	This menu item toggles the mark on all displayed packets.
Mark All Displayed Packets	Shift+Ctrl+M	This menu item "marks" all displayed packets.
Unmark All Displayed Packets	Ctrl+Alt+M	This menu item "unmarks" all displayed packets.
Find Next Mark	Shift+Ctrl+N	Find the next marked packet.
Find Previous Mark	Shift+Ctrl+B	Find the previous marked packet.
Ignore Packet (toggle)	Ctrl+D	This menu item marks the currently selected packet as ignored. See <u>Section 6.11, "Ignoring packets"</u> for details.
Ignore All Displayed Packets (toggle)	Shift+Ctrl+D	This menu item marks all displayed packets as ignored.
Un-Ignore All Packets	Ctrl+Alt+D	This menu item unmarks all ignored packets.
Set Time Reference (toggle)	Ctrl+T	This menu item set a time reference on the currently selected packet. See <u>Section 6.12.1</u> , "Packet time referencing" for more information about the time referenced packets.
Un-Time Reference All Packets	Ctrl+Alt+T	This menu item removes all time references on the packets.
Find Next Time Reference	Ctrl+Alt+N	This menu item tries to find the next time referenced packet.

Menu Item	Accelerator	Description					
Find Previous Time Reference	Ctrl+Alt+B	This menu item tries to find the previous time referenced packet.					
Configuration Profiles	Shift+Ctrl+A	This menu item brings up a dialog box for handling configuration profiles. More detail is provided in <u>Section 10.6</u> , "Configuration <u>Profiles</u> ".					
Preferences	Shift+Ctrl+P	This menu item brings up a dialog box that allows you to see preferences for many parameters that control Wireshark. You ca also save your preferences so Wireshark will use them the next tim you start it. More detail is provided in <u>Section 10.5</u> , "Preferences"					

### 3.7. The "View" menu

The Wireshark View menu contains the fields shown in Table 3.4, "View menu items".

Figure 3.5. The "View" Menu

🗖 test.ca	р			_ 🗆 🔀
<u>Eile E</u> dit	<u>View Go Capture Analyze St</u>	atistics Teleph	on <u>y T</u> ools Internals <u>H</u> elp	
	✓ <u>M</u> ain Toolbar		🔷 🥥 🚡 👱   🗐 🕞   O. Q. Q. 🖻	🎬 🗹 畅 💥 🗒
Filter:	<ul> <li>Filter Toolbar</li> <li>Wireless Toolbar</li> </ul>		Expression Clear Apply	
No. 1	✓ <u>S</u> tatusbar		ation Protocol Length Info dcast ARP 42 Gratuito	us ARP for 192.168.0.2 (F
2	✓ Packet List			<mark>ry NBSTAT *&lt;00&gt;&lt;00&gt;&lt;00&gt;<c< mark=""> ion unreachable (Port unr</c<></mark>
3	<ul> <li>Packet Details</li> <li>Packet Bytes</li> </ul>		0.0.22 IGMP 54 V3 Member	rship Report / Join group
5:	Time Display Format	•	168.0.1 DNS 110 Standard Date and Time of Day: 1970-01-01 01:02:03.123456	query SRV _ldaptcp.nbc
7: 8: 9:	Name Resolution Colorize Packet List	•	Time of Day: 01:02:03.123456 Seconds Since Epoch (1970-01-01): 1234567890.1234	Ctrl+Alt+2
10 : 11 :	<ul> <li>✓ Auto Scroll in Live Capture</li> </ul>		56 Ctrl+Alt+3 51D<00> Ctrl+Alt+4 yconf.ww004. a=0 win=6424	
12 :	⊕ <u>Z</u> oom In	Ctrl++	Seconds Since Previous Captured Packet: 1.123456	Ctrl+Alt+5 <] Seq=0 Ack
	C Zoom Out	Ctrl+- Ctrl+=	Seconds Since Previous Displayed Packet: 1.123456	Ctrl+Alt+6
<ul> <li>              Frame          </li> <li>             Etheri              Interi      </li> <li>             Transi      </li> </ul>	<ul> <li>Resize All Columns</li> <li>Displayed Columns</li> </ul>	CtrI+= Shift+CtrI+R ▶	Automatic (File Format Precision) Seconds: 0 Deciseconds: 0.1	:9a)
Soui Des [Sti	Expand Subtrees Expand All Collapse All	Shift+Right Ctrl+Right Ctrl+Left	Centiseconds: 0.12 Milliseconds: 0.123	=
Seqi Heai ⊕ Flai	Colorize Conversation Reset Coloring 1-10	► Ctrl+Space	Microseconds: 0.123456 Nanoseconds: 0.123456789	
Win	🥵 Coloring Rules		Display Seconds with hours and minutes	Ctrl+Alt+0
0000 00 0010 00 0020 00 0030 fa		Ctrl+R 05 64 01 0	2 08 00 45 00[-u]E. 8 00 02 c0 a8 .0.H@ a, 0 00 00 70 02 .P<6p. 1 04 02	
🔴 File: "C:/	'test.cap" 14 KB 00:00:02	Packets: 1	20 Displayed: 120 Marked: 0 Load time: 0:00.000	Profile: Default .:

Table 3.4. View menu items

Menu Item	Accelerator	Description
Main Toolbar		This menu item hides or shows the main toolbar, see <u>Section 3.16</u> , <u>"The "Main" toolbar"</u> .
Filter Toolbar		This menu item hides or shows the filter toolbar, see <u>Section 3.17</u> , <u>"The "Filter" toolbar"</u> .

Menu Item	Accelerator	Description
Wireless Toolbar (Windows only)		This menu item hides or shows the wireless toolbar. See the AirPcap documentation for more information.
Statusbar		This menu item hides or shows the statusbar, see <u>Section 3.21, "The</u> <u>Statusbar"</u> .
Packet List		This menu item hides or shows the packet list pane, see Section 3.18, "The "Packet List" pane".
Packet Details		This menu item hides or shows the packet details pane, see Section 3.19, "The "Packet Details" pane".
Packet Bytes		This menu item hides or shows the packet bytes pane, see Section 3.20, "The "Packet Bytes" pane".
Time Display Format > Date and Time of Day: 1970-01-01 01:02:03.123456		Selecting this tells Wireshark to display the time stamps in date and time of day format, see Section 6.12, "Time display formats and time references". Note! The fields "Time of Day", "Date and Time of Day", "Seconds Since Beginning of Capture", "Seconds
		Since Previous Captured Packet" and "Seconds Since Previous Displayed Packet" are mutually exclusive.
TimeDisplayFormat > TimeofDay:01:02:03.123456		Selecting this tells Wireshark to display time stamps in time of day format, see Section 6.12, "Time display formats and time references".
TimeDisplayFormat>SecondsSinceEpoch(1970-01-01):1234567890.123	456	Selecting this tells Wireshark to display time stamps in seconds since 1970-01-01 00:00:00, see Section 6.12, "Time display formats and time references".
TimeDisplayFormat>SecondsSinceBeginningofCapture:123.123456		Selecting this tells Wireshark to display time stamps in seconds since beginning of capture format, see Section 6.12, "Time display formats and time references".
TimeDisplayFormat>SecondsSincePreviousCapturedPacket:1.123456		Selecting this tells Wireshark to display time stamps in seconds since previous captured packet format, see <u>Section 6.12</u> , "Time display formats and time references".

Menu Item	Accelerator	Description
Time Display Format > Seconds Since Previous Displayed Packet: 1.123456		Selecting this tells Wireshark to display time stamps in seconds since previous displayed packet format, see <u>Section 6.12</u> , " <u>Time display formats and time references</u> ".
Time Display Format >		
Time Display Format > Automatic (File Format Precision)		Selecting this tells Wireshark to display time stamps with the precision given by the capture file format used, see Section 6.12, "Time display formats and time references".         Image: Note!         The fields "Automatic", "Seconds" and "seconds" are mutually exclusive.
Time Display Format > Seconds: 0		Selecting this tells Wireshark to display time stamps with a precision of one second, see <u>Section 6.12</u> , "Time display formats and time references".
Time Display Format >seconds: 0		Selecting this tells Wireshark to display time stamps with a precision of one second, decisecond, centisecond, millisecond, microsecond or nanosecond, see <u>Section 6.12</u> , "Time display formats and time references".
TimeDisplayFormat>DisplaySecondswithhoursandminutes		Selecting this tells Wireshark to display time stamps in seconds, with hours and minutes.
Name Resolution > Resolve Name		This item allows you to trigger a name resolve of the current packet only, see <u>Section 7.7, "Name Resolution"</u> .
Name Resolution > Enable for MAC Layer		This item allows you to control whether or not Wireshark translates MAC addresses into names, see Section 7.7, "Name Resolution".
Name Resolution > Enable for Network Layer		This item allows you to control whether or not Wireshark translates network addresses into names, see Section 7.7, "Name Resolution".
Name Resolution > Enable for Transport Layer		This item allows you to control whether or not Wireshark translates transport addresses into names, see <u>Section 7.7, "Name Resolution"</u> .
Colorize Packet List		This item allows you to control whether or not Wireshark should colorize the packet list.

Menu Item	Accelerator	Description
		Note!           Enabling colorization will slow down the display of new packets while capturing / loading capture files.
Auto Scroll in Live Capture		This item allows you to specify that Wireshark should scroll the packet list pane as new packets come in, so you are always looking at the last packet. If you do not specify this, Wireshark simply adds new packets onto the end of the list, but does not scroll the packet list pane.
Zoom In	Ctrl++	Zoom into the packet data (increase the font size).
Zoom Out	Ctrl+-	
Normal Size		Zoom out of the packet data (decrease the font size).
	Ctrl+=	Set zoom level back to 100% (set font size back to normal).
Resize All Columns	Shift+Ctrl+R	Resize all column widths so the content will fit into it.          Note!         Resizing may take a significant amount of time, especially if a large capture file is loaded.
Displayed Columns		This menu items folds out with a list of all configured columns. These columns can now be shown or hidden in the packet list.
Expand Subtrees	Shift+Right	This menu item expands the currently selected subtree in the packet details tree.
Expand All	Ctrl+Right	Wireshark keeps a list of all the protocol subtrees that are expanded, and uses it to ensure that the correct subtrees are expanded when you display a packet. This menu item expands all subtrees in all packets in the capture.
Collapse All	Ctrl+Left	This menu item collapses the tree view of all packets in the capture list.
Colorize Conversation		This menu item brings up a submenu that allows you to color packets in the packet list pane based on the addresses of the currently selected packet. This makes it easy to distinguish packets belonging to different conversations. Section 10.3, "Packet colorization".
Colorize Conversation > Color 1-10		These menu items enable one of the ten temporary color filters based on the currently selected conversation.
Colorize Conversation > Reset coloring		This menu item clears all temporary coloring rules.
Colorize Conversation > New Coloring Rule		This menu item opens a dialog window in which a new permanent coloring rule can be created based on the currently selected conversation.

Menu Item	Accelerator	Description
Coloring Rules		This menu item brings up a dialog box that allows you to color packets in the packet list pane according to filter expressions you choose. It can be very useful for spotting certain types of packets, see <u>Section 10.3</u> , "Packet colorization".
Show Packet in New Window		This menu item brings up the selected packet in a separate window. The separate window shows only the tree view and byte view panes.
Reload	Ctrl+R	This menu item allows you to reload the current capture file.

### 3.8. The "Go" menu

The Wireshark Go menu contains the fields shown in Table 3.5, "Go menu items".

#### Figure 3.6. The "Go" Menu

📶 test.cap	
File Edit View Go Capture Analyze Statisti	s Telephony Iools Internals Help
🖳 🕍 🎯 🛞 🔶 <u>B</u> ack	Alt+Left 🍃 7 生   🗐 🕞   🗨 🔍 🔍 📅   🌌 🖾 🎭   💢
Eorward	Alt+Right
Filter:	Ctrl+G
No. Time 1 0,000 Go to Corresponding Packet	Protocol Length Info ARP 42 Gratuitous ARP for 192.168.0.2 (F
2 0.299 1 Previous Packet	ARP         42 Gratuitous ARP for 192.168.0.2 (F)           Ctrl+Up         .2         NBNS         92 Name guery NBSTAT *<00><00><00
3 0.299 4 Next Packet	Ctrl+Down 1 ICMP 70 Destination unreachable (Port unr
4 1.025 🛖 First Basket	Childenne 2 IGMP 54 V3 Membership Report / Join group
5 1.044 Trist Packet 6 1.048 Last Packet	,1 DNS 110 Standard query SRV _Idaptcp.nbc
7 1.050 Previous Packet In Conversati	
8 1.055 Next Packet In Conversation	Ctrl+, 2 SSDP 337 HTTP/1.1 200 OK
9 1.082038 192.168.0.2	192.168.0.255 NBNS 110 Registration NB NB10061D<00>
10 1.111945 192.168.0.2	192.168.0.1 DNS 87 Standard query A proxyconf.ww004.
11 1.226156 192.168.0.2	192.168.0.1 TCP 62 ncu-2 > http [SYN] seq=0 Win=6424
12 1.227282 192.168.0.1	192.168.0.2 TCP 60 http > ncu-2 [SYN, ACK] Seq=0 Ack ♥
	bits), 62 bytes captured (496 bits)
	0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1)
	Src Port: ncu-2 (3196), Dst Port: http (80), Seq: 0, Len: 0
Source port: ncu-2 (3196)	
Destination port: http (80) [Stream index: 5]	
	ve sequence number)
Header length: 28 bytes	
⊞ Flags: 0x02 (SYN)	
Window size value: 64240	×
	20 cd 02 08 00 45 00[-u]E.
	2c c0 a8 00 02 c0 a8   .0.H@ a, f8 00 00 00 00 70 02   .P<6p.
	b4 01 01 04 02
File: "C:/test.cap" 14 KB 00:00:02	Packets: 120 Displayed: 120 Marked: 0 Load time: 0:00.000 Profile: Default


#### Table 3.5. Go menu items

Menu Item	Accelerator	Description					
Back	Alt+Left	Jump to the recently visited packet in the packet history, much like the page history in a web browser.					
Forward	Alt+Right	Jump to the next visited packet in the packet history, much like the page history in a web browser.					

Menu Item	Accelerator	Description
Go to Packet	Ctrl+G	Bring up a dialog box that allows you to specify a packet number, and then goes to that packet. See <u>Section 6.9</u> , "Go to a specific <u>packet</u> " for details.
Go to Corresponding Packet		Go to the corresponding packet of the currently selected protocol field. If the selected field doesn't correspond to a packet, this item is greyed out.
Previous Packet	Ctrl+Up	Move to the previous packet in the list. This can be used to move to the previous packet even if the packet list doesn't have keyboard focus.
Next Packet	Ctrl+Down	Move to the next packet in the list. This can be used to move to the previous packet even if the packet list doesn't have keyboard focus.
First Packet	Ctrl+Home	Jump to the first packet of the capture file.
Last Packet	Ctrl+End	Jump to the last packet of the capture file.
Previous Packet In Conversation	Ctrl+,	Move to the previous packet in the current conversation. This can be used to move to the previous packet even if the packet list doesn't have keyboard focus.
Next Packet In Conversation	Ctrl+.	Move to the next packet in the current conversation. This can be used to move to the previous packet even if the packet list doesn't have keyboard focus.

### 3.9. The "Capture" menu

The Wireshark Capture menu contains the fields shown in Table 3.6, "Capture menu items".



1+	est.ca	20																								_ [	
_									<b>Ch - M</b>	N	Teles			1-	Tele		1.1l-										
Eile	Edit	Viev	v <u>G</u> o						<u>p</u> uaus	acs	reieț	briony	<u> </u>	oois	Tuce	rnais	Help	_									
	Ë.			2275	_		ices	•		Ctrl+		\$	\$		Ŧ	⊉			Ð, (		1		2	} %		Ĵ	
Filter	r:				l St	ption art	s			Ctrl+ Ctrl+						~	Expression.	d	ear	Apply							
No.		Time			l St					Chrl+		tinatio	n				Protocol	Lend	ath	Info							~
	1	0.0	0000	0							r	oad	as	t			ARP	-	42	Gratui	tous ,	ARP	for	192	.168	3.0.2	(F
	2	0.2	9913	9	Re	estar	t			Ctrl+	R 9	2.10	i8.	0.2			NBNS		92	Name q	uery M	VBST	TAT 1	*<00	><00	)><00	><0
	3	0.2	9921	4 📓	l Ca	aptur	e <u>F</u> ilte	ers			9	2.10	58.)	0.1			ICMP		-70	Destin	ation	unr	reac	habl	e (F	Port	unr
	4	1.0	2565	9	19	2.1	68.	0.2			22.	4.0.	0.3	22			IGMP			V3 Mem							
	5	1.0	4436	6	19	2.1	68.)	0.2				2.10					DNS			Standa					lap	tcp.	nbç
	6	1.0	4865				68.)				23	9.2	55.0	255	.250	0	SSDP			M-SEAR							
			5078		_		68.)					2.10					DNS			Standa				nb1	.0061	.d.ww	004
			5505				68.)					2.10					SSDP			НТТР/1							
			8203				68.)					2.10			55		NBNS			Regist							
			1194				68.					2.10					DNS			Standa							
			2615				68.					2.10					TCP			ncu-2							
	12	1.2	2728	2	19	2.1	68.	0.1			19	2.10	58.	0.2			TCP		60	http >	ncu-2	2 [9	5ΥN,	ACK	(] Se	eq=0	Ack 🗸
<									1	11																	>
ΞF	rame	11	: 62	byt	tes	or	ı wi	re	(496	5 bi	ts)	, 6	2 b	yte	s c	aptu	red (49	6 b*	its	)							~
ΞE	ther	net	II,	Sre	c:	192	.16	8.0	.2	(00:	Ob:	5d::	20:	cd:	02)	, Ds	t: Netg	ear_	_2 d	:75:9a	(00:09	9:5b	:2d	:75:	9a)		
÷Ι	nter	net	Pro	toc	ο٦,	Sr	·c:	192	.168	3.0.	2 (	192	16	8.0	.2)	, Ds	t: 192.	168.	0.1	L (192.)	168.0.	1)					
ΘΤ	rans	mis:	sion	Cot	ntr	ol	Pro	itoci	οΊ,	Sho	PO	rt:	nc	u-2	(3:	196)	, Dst P	ort:	: h1	tp (80	), Sec	q: C	), Le	en:	0		
			por																								=
			atio				ittp	i (8i	0)																		
			n in																								
			ce n					(re	lat	ive	seq	uen	e	num	berj	)											
			len				byte	:5																			
÷	Fla																										_
	Win	idow	siz	e va	alu	le:	642	40																			~
000	0 0	0 09	) 5b	2d	75	9a	00	0h	5.0	20	cd	02	08	00	45	00	[-u.		1	F							
001	ō ōi	0 30	18	48	40	00	80	06	61	. 2c	C0	a8	00	02	C0	a8	.0.Н@										
002			. QC							f8					70	02		°<6		p.							
003	0 f	a f(	) 27	e0	00	00	02	04	05	b4	01	01	04	02				• • •	•••	• • •							
🔴 F	ile: "C:	/test.	cap" 1	4 KB (	00:0	0:02				Pa	ckets	: 120	Displ	ayed	: 120	Marke	ed: O Load ti	me: 0	:00.0	00	Profile	: Def	ault				
				_	_	_	_	_	_	_	_	_			_				_			_					

Table 3.6. Capture menu items

Menu Item	Accelerator	Description					
Interfaces	Ctrl+I	This menu item brings up a dialog box that shows what's going on at the network interfaces Wireshark knows of, see <u>Section 4.4</u> , <u>"The "Capture Interfaces" dialog box"</u> ).					
Options	Ctrl+K	This menu item brings up the Capture Options dialog be (discussed further in <u>Section 4.5, "The "Capture Options" dialog</u> <u>box</u> ") and allows you to start capturing packets.					
Start	Ctrl+E	Immediately start capturing packets with the same settings than the last time.					
Stop	Ctrl+E	This menu item stops the currently running capture, see <u>Section 4.13.1, "Stop the running capture"</u> ).					
Restart	Ctrl+R	This menu item stops the currently running capture and starts again with the same options, this is just for convenience.					
Capture Filters		This menu item brings up a dialog box that allows you to create and edit capture filters. You can name filters, and you can save them for future use. More detail on this subject is provided in <u>Section 6.6</u> , <u>"Defining and saving filters"</u>					

### 3.10. The "Analyze" menu

The Wireshark Analyze menu contains the fields shown in Table 3.7, "Analyze menu items".

Figure 3.8. The "Analyze" Menu

📶 test.cap				
Eile Edit View Go Capture Analyze Statistics Telephony Tools Intern	nals <u>H</u> elp			
Filter:     Display Filter Macros	:   📃 🕞   🗨 🔍 🔍 🗹   🕁 🗹 🍢   💢			
Apply as Column No. Time Source Apply as Filter	Selected			
1 0.000000 192.: Prepare a Filter	Not Selected uitous ARP for 192.168.0.2 (F			
2         0.299139         192.           3         0.299214         192.         ☑ Enabled Protocols         Shift+Ctrl+E           4         1.025659         192.         ☑ Decode As				
5 1.044366 192. 6 1.048652 192.	dard query SRV _ldaptcp.nbc			
7       1.050784       192.       Eollow TCP Stream         8       1.055053       192.       Eollow UDP Stream         9       1.082038       192.       Eollow SSL Stream         10       1.111945       192.       Expert Info         11       1.226156       192.       Expert Info	DNS     86 Standard query SOA nbl0061d.ww004       SSDP     337 HTTP/1.1 200 OK       NBNS     110 Registration NB NB10061D<00>       DNS     87 Standard query A proxyconf.ww004.       TCP     62 ncu-2 > http [SYN] seq=0 win=6424       TCP     60 http > ncu-2 [SYN, ACK] seq=0 Ack			
Conversation Filter				
<pre>e Frame 11: 62 bytes on wire (496 bits), 62 bytes captured (496 bits)     Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a)     Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1)     Transmission Control Protocol, Src Port: ncu-2 (3196), Dst Port: http (80), Seq: 0, Len: 0     Source port: ncu-2 (3196)     Destination port: http (80)     [Stream index: 5]     Sequence number: 0 (relative sequence number)     Header length: 28 bytes     Elfags: 0x02 (SYN)</pre>				
Window size value: 64240	✓			
0000         00         09         5b         2d         75         9a         00         0b         5d         20         cd         02         08         00         45         0           0010         00         30         18         48         40         00         80         66         51         2c         c0         a8         00         2c         c0         a           0020         00         01         0c         7c         00         50         3c         36         95         f8         00         00         07         0           0030         fa         f0         27         e0         00         00         02         04         05         b4         01         04         02	8 .О.Н@ а,			
Transmission Control Protocol (tcp), 28 bytes Packets: 120 Displayed: 120 M	arked: 0 Load time: 0:00.000 Profile: Default .:			

Table 3.7. Analyze menu items

Menu Item	Accelerator	Description
Display Filters		This menu item brings up a dialog box that allows you to create and edit display filters. You can name filters, and you can save them for future use. More detail on this subject is provided in <u>Section 6.6</u> , <u>"Defining and saving filters"</u>
Display Filter Macros		This menu item brings up a dialog box that allows you to create and edit display filter macros. You can name filter macros, and you can save them for future use. More detail on this subject is provided in <u>Section 6.7, "Defining and saving filter macros"</u>
Apply as Column		This menu item adds the selected protocol item in the packet details pane as a column to the packet list.
Apply as Filter >		These menu items will change the current display filter and apply the changed filter immediately. Depending on the chosen menu item, the current display filter string will be replaced or appended to by the selected protocol field in the packet details pane.
Prepare a Filter >		These menu items will change the current display filter but won't apply the changed filter. Depending on the chosen menu item, the current display filter string will be replaced or appended to by the selected protocol field in the packet details pane.

Menu Item	Accelerator	Description
Enabled Protocols	Shift+Ctrl+E	This menu item allows the user to enable/disable protocol dissectors, see <u>Section 10.4.1</u> , "The "Enabled Protocols" dialog box"
Decode As		This menu item allows the user to force Wireshark to decode certain packets as a particular protocol, see <u>Section 10.4.2</u> , "User <u>Specified Decodes</u> "
User Specified Decodes		This menu item allows the user to force Wireshark to decode certain packets as a particular protocol, see <u>Section 10.4.3</u> , "Show <u>User Specified Decodes</u> "
Follow TCP Stream		This menu item brings up a separate window and displays all the TCP segments captured that are on the same TCP connection as a selected packet, see <u>Section 7.2</u> , "Following TCP streams"
Follow UDP Stream		Same functionality as "Follow TCP Stream" but for UDP streams.
Follow SSL Stream		Same functionality as "Follow TCP Stream" but for SSL streams. XXX - how to provide the SSL keys?
Expert Info		Open a dialog showing some expert information about the captured packets. The amount of information will depend on the protocol and varies from very detailed to non-existent. XXX - add a new section about this and link from here
Conversation Filter >		In this menu you will find conversation filter for various protocols.

### 3.11. The "Statistics" menu

The Wireshark Statistics menu contains the fields shown in Table 3.8, "Statistics menu items".

Figure 3.9. The "Statistics" Menu

📶 test.cap						
<u>File E</u> dit <u>V</u> iew <u>Go</u> <u>C</u> apture <u>A</u> nalyze	Statistics Telephony Iools Internals Help					
	🕅 Summary Protocol Hierarchy					
Filter:	Depression Conversations					
No. Time Source	Endpoints					
1 0.000000 192.168.0.2	Packet Lengths ARP 42 Gratuitous ARP for 192.168.0.2 (F					
2 0.299139 192.168.0.1	IO Graphs NBNS 92 Name query NBSTAT *<00><00><0					
3 0.299214 192.168.0.2 4 1.025659 192.168.0.2	Conversation List IGMP 54 V3 Membership Report / Join group					
5 1.044366 192.168.0.2						
6 1.048652 192.168.0.2	Service Decreases Time					
7 1.050784 192.168.0.2	Service Response Time PDDI ndard guery SOA nb10061d.ww004					
8 1.055053 192.168.0.1	ANCP P/1.1 200 OK					
91.082038 192.168.0.2	BOOTP-DHCP istration NB NB10061D<00>					
10 1.111945 192.168.0.2	Collectd Idard query A proxyconf.ww004.					
11 1.226156 192.168.0.2	Compare2 > http [SYN] Seq=0 W1n=6424					
12 1.227282 192.168.0.1	Flow Graph I IPv6 > ncu-2 [SYN, ACK] Seq=0 Ack					
<	HTTP I I I I I I I I I I I I I I I I I I					
⊕ Frame 11: 62 bytes on wire	IP Addresses 🗵 NCP					
⊕ Ethernet II, Src: 192.168.	IP Destinations 🔋 RSVP					
Internet Protocol, Src: 19	IP Protocol Types 92.168.0.1)					
Transmission Control Proto	ONC-RPC Programs					
Source port: ncu-2 (3196) Destination port: http (	Sancane					
[stream index: 5]	TCP Stream Graph 🕨 📓 Token Ring					
Sequence number: 0 (r	UDP Multicast Streams  UDP (IPv4 & IPv6) WLAN Traffic					
Header length: 28 bytes	WLAN Irarric   USB					
⊞ Flags: 0x02 (SYN)	🛛 WLAN					
window size value: 64240						
0000 00 09 5b 2d 75 9a 00 0b 0010 00 30 18 48 40 00 80 06 0020 00 01 0c 7c 00 50 3c 36 0030 fa f0 27 e0 00 00 02 04	61 2c c0 a8 00 02 c0 a8 .0.H@ a, 95 f8 00 00 00 00 70 02					
File: "C:/test.cap" 14 KB 00:00:02	Packets: 120 Displayed: 120 Marked: 0 Load time: 0:00.015 Profile: Default					

All menu items will bring up a new window showing specific statistical information.

Table 3.8. Statistics menu items

Menu Item	Accelerator	Description
Summary		Show information about the data captured, see <u>Section 8.2</u> , "The <u>"Summary" window"</u> .
Protocol Hierarchy		Display a hierarchical tree of protocol statistics, see <u>Section 8.3</u> , <u>"The "Protocol Hierarchy" window"</u> .
Conversations		Display a list of conversations (traffic between two endpoints), see Section 8.4.2, "The "Conversations" window".
Endpoints		Display a list of endpoints (traffic to/from an address), see Section 8.5.2, "The "Endpoints" window".
Packet Lengths		See Section 8.10, "The protocol specific statistics windows"
IO Graphs		Display user specified graphs (e.g. the number of packets in the course of time), see <u>Section 8.6</u> , "The "IO Graphs" window".
Conversation List		Display a list of conversations, obsoleted by the combined window of Conversations above, see <u>Section 8.4.3</u> , "The protocol specific "Conversation List" windows".

Menu Item	Accelerator	Description
Endpoint List		Display a list of endpoints, obsoleted by the combined window of Endpoints above, see Section 8.5.3, "The protocol specific "Endpoint List" windows".
Service Response Time		Display the time between a request and the corresponding response, see Section 8.7, "Service Response Time".
ANCP		See Section 8.10, "The protocol specific statistics windows"
BOOTP- DHCP		See Section 8.10, "The protocol specific statistics windows"
Colledtd		See Section 8.10, "The protocol specific statistics windows"
Compare		See Section 8.10, "The protocol specific statistics windows"
Flow Graph		See Section 8.10, "The protocol specific statistics windows"
НТТР		HTTP request/response statistics, see <u>Section 8.10</u> , "The protocol <u>specific statistics windows</u> "
IP Addresses		See Section 8.10, "The protocol specific statistics windows"
IP Destinations		See Section 8.10, "The protocol specific statistics windows"
IP Protocol Types		See Section 8.10, "The protocol specific statistics windows"
ONC-RPC Programs		See Section 8.10, "The protocol specific statistics windows"
Sametime		See Section 8.10, "The protocol specific statistics windows"
TCP Stream Graph		See Section 8.10, "The protocol specific statistics windows"
UDP Multicast Streams		See Section 8.10, "The protocol specific statistics windows"
WLAN Traffic		See Section 8.9, "WLAN Traffic Statistics"

### 3.12. The "Telephony" menu

The Wireshark Telephony menu contains the fields shown in Table 3.9, "Telephony menu items".

🛛 test.cap					
Eile Edit View Go Capture Analyze Statistics	Telephony <u>I</u> ools <u>I</u> nternals	Help			
	IAX2	🗐 📑 ( Q, Q, 🔍 📅   📓 🛛 🥵 %   🕱			
Filter:		xpression Clear Apply			
No. Time Source	ANSI F	Protocol Length Info			
1 0.000000 192.168.0.2	 	ARP 42 Gratuitous ARP for 192.168.0.2 (F			
2 0.299139 192.168.0.1	TCUD Manager	NBNS 92 Name query NBSTAT *<00><00><00> <c< td=""></c<>			
3 0.299214 192.168.0.2	ite i	ICMP 70 Destination unreachable (Port unr			
4 1.025659 192.168.0.2		IGMP 54 V3 Membership Report / Join group			
5 1.044366 192.168.0.2	RTP •	Show All Streams			
6 1.048652 192.168.0.2	SIP	Ch http://			
7 1.050784 192.168.0.2	I – L	Stream Analysis Ind query SOA nb10061d.ww004			
8 1.055053 192.168.0.1 9 1.082038 192.168.0.2		SSDP 337 HTTP/1.1 200 OK NBNS 110 Registration NB NB10061D<00>			
10 1.111945 192.168.0.2	a Ton carp	NBNS 110 Registration NB NB10061D<00> DNS 87 Standard query A proxyconf.ww004.			
11 1.226156 192.168.0.2		TCP 62 ncu-2 > http [SYN] Seq=0 Win=6424			
12 1.227282 192.168.0.1		TCP 60 http > ncu-2 [SYN, ACK] Seq=0 Ack			
2	192.100.0.2	TCP OUTTCCP > TCC-2 [STN, ACK] BEQ-0 ACK			
		: Netgear_2d:75:9a (00:09:5b:2d:75:9a)			
⊕ Internet Protocol, src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1)					
□ Transmission Control Protocol, Src Port: ncu-2 (3196), Dst Port: http (80), Seq: 0, Len: 0					
Source port: ncu-2 (3196) 🔤					
Istream index: 5]					
	sequence number)				
Header length: 28 bytes					
Flags: 0x02 (SYN)					
window size value: 64240					
	) cd 02 08 00 45 00 : c0 a8 00 02 c0 a8	[-u ]E. .0.H@ a			
	00 00 00 00 70 02	.P<6p.			
	01 01 04 02				
File: "C:/test.cap" 14 KB 00:00:02	ackets: 120 Displayed: 120 Marked	: 0 Load time: 0:00.015 Profile: Default .:			

Figure 3.10. The "Telephony" Menu

All menu items will bring up a new window showing specific telephony related statistical information.

Table 3.9. Telephony menu iten	ns
--------------------------------	----

Menu Item	Accelerator	Description
IAX2		See Section 9.6, "The protocol specific statistics windows"
SMPP Operations		See Section 9.6, "The protocol specific statistics windows"
SCTP		See Section 9.6, "The protocol specific statistics windows"
ANSI		See Section 9.6, "The protocol specific statistics windows"
GSM		See Section 9.6, "The protocol specific statistics windows"
Н.225		See Section 9.6, "The protocol specific statistics windows"
ISUP Messages		See Section 9.6, "The protocol specific statistics windows"
LTE		See Section 9.4, "LTE MAC Traffic Statistics"
MTP3		See Section 9.6, "The protocol specific statistics windows"
RTP		See Section 9.2, "RTP Analysis"
SIP		See Section 9.6, "The protocol specific statistics windows"
UCP Messages		See Section 9.6, "The protocol specific statistics windows"
VoIP Calls		See Section 9.3, "VoIP Calls"

Menu Item	Accelerator	Description	
WAP-WSP		See Section 9.6, "The protocol specific statistics windows"	

### 3.13. The "Tools" menu

The Wireshark Tools menu contains the fields shown in Table 3.10, "Tools menu items".

#### Figure 3.11. The "Tools" Menu

🗖 t	est.cap						_ 🗆 🗙
Eile	<u>E</u> dit <u>V</u> iew <u>G</u> o	<u>Capture</u> <u>A</u> nalyze	Statistics Telephony Tools Inter	nals <u>H</u> elp			
		🖻 🖬 🗙 🛱	🖞 📇   🔍 🦕 🧋 🛛 Firewall A	CL Rules	A A M 📼	M 🛛 🗖 💥	<b>1</b>
-			Lua	•	Console		629
Filte	r:			<ul> <li>Expression</li> </ul>	Evaluate		
No.	Time	Source	Destination	Protocol	Wiki		~
	1 0.000000		Broadcast	ARP		s ARP for 192.1	L68.0.2 (F
	2 0.299139	192.168.0.1	192.168.0.2	NBNS	92 Name quer	y NBSTAT *<00≻<	<00><00> <c< td=""></c<>
	3 0.299214	192.168.0.2	192.168.0.1	ICMP	70 Destinati	on unreachable	(Port unr
	4 1.025659	192.168.0.2	224.0.0.22	IGMP	54 V3 Member	ship Report / 3	oin group
	5 1.044366	192.168.0.2	192.168.0.1	DNS	110 Standard	query SRV _1dap	ot⊂p.nbç
	6 1.048652	192.168.0.2	239.255.255.250	SSDP	175 M-SEARCH	* HTTP/1.1	
	7 1.050784		192.168.0.1	DNS		query SOA nb100	061d.ww004
	8 1.055053		192.168.0.2		337 HTTP/1.1		
	9 1.082038		192.168.0.255	NBNS		ion NB NB100610	
	10 1.111945		192.168.0.1	DNS		query A proxyco	
	11 1.226156		192.168.0.1	TCP		ttp [SYN] Seq=(	
	12 1.227282	192.168.0.1	192.168.0.2	TCP	60 http > nc	u-2 [SYN, ACK]	Seq=0 Ack
<							>
ΞF	rame 11: 62	bytes on wire	(496 bits), 62 bytes ca	otured (496 b	its)		~
ΞE	thernet II,	src: 192.168.0	.2 (00:0b:5d:20:cd:02),	Dst: Netgear	_2d:75:9a (00	:09:5b:2d:75:9a	υ T
÷Ι	nternet Prot	ocol, src: 192	.168.0.2 (192.168.0.2),	Dst: 192.168	.0.1 (192.168	.0.1)	
	ransmission -	Control Protoc	ol, Src Port: ncu-2 (319	96), Dst Port	: http (80),	Seq: 0, Len: 0	
		: ncu-2 (3196)					≡
		port: http (8	0)				
	[Stream ind						
	Sequence nu		lative sequence number)				
		th: 28 bytes					
Ð	Flags: 0x02						
	window size	value: 64240					~
000	0 00 09 5b 2	d 75 9a 00 0b	5d 20 cd 02 08 00 45 0	0[-u	1E.		
001	0 00 30 18 4	8 40 00 80 06	61 2c c0 a8 00 02 c0 a	.8 .0.Н@			
002		C 00 50 3c 36	95 f8 00 00 00 00 70 0	)2 .P<6	p.		
003	о тато 27 е	20 00 00 02 04	05 b4 01 01 04 02				
🔴   F	File: "C:/test.cap" 14	KB 00:00:02	Packets: 120 Displayed: 120 M	larked: O Load time: O	0:00.015 Pr	rofile: Default	

Table 3.10. Tools menu items

Menu Item	Menu Item Accelerator		Description
Firewall Rules	ACL		This allows you to create command-line ACL rules for many different firewall products, including Cisco IOS, Linux Netfilter (iptables), OpenBSD pf and Windows Firewall (via netsh). Rules for MAC addresses, IPv4 addresses, TCP and UDP ports, and IPv4+port combinations are supported. It is assumed that the rules will be applied to an outside interface.
Lua			These options allow you to work with the Lua interpreter optionally build into Wireshark, see <u>Section 11.1, "Introduction"</u> .

### 3.14. The "Internals" menu

The Wireshark Internals menu contains the fields shown in Table 3.11, "Help menu items".

1.	est.ca																					
_											_	_									_	
Eile	Edit	⊻iew	<u>G</u> o	Capture	Analy	ze	<u>S</u> tatistics	Tele	ohony	Tools	Inter	nals <u>t</u>	<u>H</u> elp									
	2	<u>e</u>	( 🛋			2	日	O,	<b>(</b> = )	) 🖒	Ē	issecto	r tables			-		( 🖂		*	<b>10</b>	
-	-	<u> </u>	s					~			3	jupport	ed Protoco	ols (slow!)		_		· —	~~	Q.0. 1	66	
Filter	n -											❤ Ex	pression	. Clear	Apply	_						
No.		Time		Sourc	е			Des	tinatior	1		F	rotocol	Length	Info							~
	1	0.00	0000	192	.168.0	0.2		Br	oadca	ast		,	ARP	42	Grat	uit	ous A	RP f	or :	192.1	168.0.2	2 (F
	2	0.29	9139	192	.168.0	0.1		19	2.16	3.0.2	1	1	NBNS	92	Name	gu qu	ery N	IBSTA	т *	<00><	<00><00	0><0
	3	0.29	9214	192	.168.(	0.2		19	2.16	3.0.1	_		ECMP	70	Dest	ina	tion	unne	ach	able	(Port	unr
	4	1.02	5659	192	.168.0	0.2		22	4.0.0	).22			EGMP	54	∨3 №	Iemb	ershi	p Re	por:	t / :	Join gr	roup
	5	1.044	4366	192	.168.0	0.2		19	2.16	3.0.1	-	[	DNS								tcp.	. nbç
	6	1.04	8652	192	.168.0	D.2		23	9.25	5.255	.250	2	SSDP				н * н					
	- 7	1.05	0784	192	.168.0	0.2		19	2.16	3.0.1	-	[	DNS	86	Star	idani	d que	eny s	OA I	nb10(	)61d.w	N004
	8	1.05	5053	192	.168.0	0.1		19	2.16	3.0.2		2	SSDP	337	HTTF	/1.:	1 200	ок 🛛				
	9	1.08	2038	192	.168.0	0.2		19	2.16	3.0.2	55	1	VBNS								<00>	
	10	1.11	1945	192	.168.0	D.2		19	2.16	3.0.1	-	[	DNS								onf.ww	
	11	1.22	6156	192	.168.0	0.2		19	2.16	3.0.1	-	-	ГСР								) Win=0	
	12	1.22	7282	192	.168.(	0.1		19	2.16	3.0.2	2	-	ГСР	60	http	>	ncu-2	: [SY	Ν, β	ACK]	Seq=0	Ack 🗸
<																						>
θE	rame	11:	62 k	ovtes	on wi	re	(496 b	its)	. 62	byte	es car	oture	ed (496	5 bits)								~
														ear_2d:		a (i	00:09	:5b:	2d::	75:9a	D .	Ē
														L68.0.1								
														ort: ht					Ler	n: 0		
				ncu-																		=
	Des	tinai	tion	port:	http	(8)	0)															
	[st	ream	inde	ex: 5]	•	-	-															
	Seq	uence	e num	ıber:	0	(re	lative	e seq	uenc	e num	nber)											
	Неа	ider <sup>-</sup>	lengt	:h: 28	; byte	s					-											
Œ	Fla	igs: (	0x02	(SYN)	-																	
	Win	idow s	size	value	: 642	40																~
000	0 0	0 09	5h 2	d 75	92 00	ûЬ	5d 2	0 cd	02.0	8 00	45 C	0	Γ_11	1 .	E							
001				8 40							a			a								
002				C 00							70 0	)2	.P	<6	p							
	o fa	a f0	27 e	0 00	00 02	04	05 b	4 01	01 (	04 02			'									
003																						
003																						

Figure 3.12. The "Internals" Menu

Table 3.11. Help menu items

Menu Item	Accelerator	Description
Dissector tables		This menu item brings up a dialog box showing the tables with subdissector relationships.
Supported Protocols (slow!)		This menu item brings up a dialog box showing the supported protocols and protocol fields.

### 3.15. The "Help" menu

The Wireshark Help menu contains the fields shown in Table 3.12, "Help menu items".

Figure 3.13. The "Help" Menu

🗖 t	est.c	ap																													_	
Eile	Edit	⊻ie	w	<u>G</u> o	⊆aj	pture	÷ 6	<u>A</u> naly	/ze	Sta	atisti	ics	Tele	phor	אַר	<u>T</u> ools	; <u>I</u> nl	erna:	s H	elp						_						
	<b>2</b>	0	<b>N</b>	1			7	8	8 6	2	8		0	4	\$	4	•	₽	1	1	<u>C</u> ontents				F1		(	2	R %	2		
							_			-	_						_			P	Manual Pa	ages			►			hark				
Filte	r:																	~		> 1	Website					W	/ires	hark F	ilter			
No.		Time				Sourc								stina							FAQ's					T	Shar	k				1
		0.0				192									dca		_		-		•					R	awS	hark				2 (F
		0.2				192										.0.				۸ 🧕	Wiki					D	ump	cap				0><0
		0.2				192 192										.0.	L			_	Download					M	lerge	ecap				roup
		1.0				192 192										. 22	1			2	Sample C	aptu	res				ditca					. nbc
		1.0				192											5.25	0			About Wi	resha	ark			T	ext2	pcap	_			
	7	1.0	050	784		192	.10	58.	0.2	2			19	2.1	L68	. 0. :	1		_	N2				scar	iuar	d que	eny	SOA	k nbi	1006	51d.v	w004
		1.(				192							-19	2.1	L68	.0.	2		S	SD	P					1 200						
		1.0				192										.0.				BN						atior						
		1.1				192							_			.0.3				NS						d que						
		1.2				192 192										.0.: .0.				CP CP						http						6424 Ack
2	12	1.4	. 27.	202	-	192	• т.	JO.	0.1	L .			Т.2	2	100		2			CP		0	U I	ιυυμ		ncu-z	4 L	STN,	ACI	NJ 2	seq=u	
									,												(10.0.1		~									
																					(496 b etgear					00.00		h.70	1.75	.0		
																					92.168							0.20		. 5a,	,	
																					t Port							О, Ц	.en:	0		
	SOL	unde	e po	ort	: r	icu-	-2	(31	.96	)																						
		stir						ttp	0 (	80)	1																					
	-	rea				-				_																						
		quer								ela	it n	ve	seo	lnei	nce	nu	nber	9														L
a	Hea Fla	ader						yte	:5																							_
Ŀ		ndov						647	40																							
											<b>r</b> 1	2.0									<b>F</b>	7		-								
000		003															) 45 2 c0				[–и .н@											
002	ōō	0 0	1 0	ic 7	'c	00	50	Зc	36	5	95	f8	00	00	0	0 00	70				. .P<6											
003	0 f	a f	0 2	7ε	20	00	00	02	04	1	05	b4	01	01	. 04	1 02	2			• • '	•••••	• •	• •	••								
F 🔵	ile: "C	:/tes	t.cap	" 14	кв с	0:00	:02					Pa	ckets	: 12	0 Dis	playe	d: 12	0 Mar	ked: I	) Lo	bad time:	0:00	.015	5		Profile	: De	fault				

Table 3.12. Help menu items

Menu Item	Accelerator	Description
Contents	F1	This menu item brings up a basic help system.
Manual Pages >		This menu item starts a Web browser showing one of the locally installed html manual pages.
Website		This menu item starts a Web browser showing the webpage from: <u>http://www.wireshark.org</u> .
FAQ's		This menu item starts a Web browser showing various FAQ's.
Downloads		This menu item starts a Web browser showing the downloads from: http://www.wireshark.org.
Wiki		This menu item starts a Web browser showing the front page from: <u>http://wiki.wireshark.org</u> .
Sample Captures		This menu item starts a Web browser showing the sample captures from: <u>http://wiki.wireshark.org</u> .
About Wireshark		This menu item brings up an information window that provides various detailed information items on Wireshark, such as how it's build, the plugins loaded, the used folders,



#### Note!

Calling a Web browser might be unsupported in your version of Wireshark. If this is the case, the corresponding menu items will be hidden.



#### Note!

If calling a Web browser fails on your machine, maybe because just nothing happens or the browser is started but no page is shown, have a look at the web browser setting in the preferences dialog.

### 3.16. The "Main" toolbar

The main toolbar provides quick access to frequently used items from the menu. This toolbar cannot be customized by the user, but it can be hidden using the View menu, if the space on the screen is needed to show even more packet data.

As in the menu, only the items useful in the current program state will be available. The others will be greyed out (e.g. you cannot save a capture file if you haven't loaded one).

#### Figure 3.14. The "Main" toolbar



Toolbar Icon	Toolbar Item	Corresponding Menu Item	Description
	Interfaces	Capture/ Interfaces	This item brings up the Capture Interfaces List dialog box (discussed further in <u>Section 4.3, "Start</u> <u>Capturing"</u> ).
	Options	Capture/Options	This item brings up the Capture Options dialog box (discussed further in <u>Section 4.3</u> , " <u>Start Capturing</u> ") and allows you to start capturing packets.
	Start	Capture/Start	This item starts capturing packets with the options form the last time.
	Stop	Capture/Stop	This item stops the currently running live capture process <u>Section 4.3, "Start Capturing"</u> ).
<b>)</b>	Restart	Capture/Restart	This item stops the currently running live capture process and restarts it again, for convenience.
ß	Open	File/Open	This item brings up the file open dialog box that allows you to load a capture file for viewing. It is discussed in more detail in <u>Section 5.2.1</u> , "The "Open Capture File" dialog box".
	Save As	File/Save As	This item allows you to save the current capture file to whatever file you would like. It pops up the Save Capture File As dialog box (which is discussed further in <u>Section 5.3.1, "The "Save Capture File As" dialog</u> <u>box"</u> ).

#### Table 3.13. Main toolbar items

Toolbar Icon	Toolbar Item	Corresponding Menu Item	Description
			Note! If you currently have a temporary capture file, the Save icon low will be shown instead.
x	Close	File/Close	This item closes the current capture. If you have not saved the capture, you will be asked to save it first.
ŝ	Reload	View/Reload	This item allows you to reload the current capture file.
	Print	File/Print	This item allows you to print all (or some of) the packets in the capture file. It pops up the Wireshark Print dialog box (which is discussed further in Section 5.8, "Printing packets").
٩	Find Packet	Edit/Find Packet	This item brings up a dialog box that allows you to find a packet. There is further information on finding packets in <u>Section 6.8</u> , "Finding packets".
4	Go Back	Go/Go Back	This item jumps back in the packet history.
₽	Go Forward	Go/Go Forward	This item jumps forward in the packet history.
ŝ	Go to Packet	Go/Go to Packet	This item brings up a dialog box that allows you to specify a packet number to go to that packet.
7	Go To First Packet	Go/First Packet	This item jumps to the first packet of the capture file.
⊉	Go To Last Packet	Go/Last Packet	This item jumps to the last packet of the capture file.
	Colorize	View/Colorize	Colorize the packet list (or not).
4	Auto Scroll in Live Capture	View/Auto Scroll in Live Capture	Auto scroll packet list while doing a live capture (or not).
⊕ <b>`</b>	Zoom In	View/Zoom In	Zoom into the packet data (increase the font size).
Q	Zoom Out	View/Zoom Out	Zoom out of the packet data (decrease the font size).
(i) <b>(</b>	Normal Size	View/Normal Size	Set zoom level back to 100%.
<del>}</del> +	Resize Columns	View/Resize Columns	Resize columns, so the content fits into them.
	Capture Filters	Capture/Capture Filters	This item brings up a dialog box that allows you to create and edit capture filters. You can name filters, and you can save them for future use. More detail on this subject is provided in <u>Section 6.6</u> , "Defining and <u>saving filters"</u> .

Toolbar Icon	Toolbar Item	Corresponding Menu Item	Description
¥	Display Filters	Analyze/Display Filters	This item brings up a dialog box that allows you to create and edit display filters. You can name filters, and you can save them for future use. More detail on this subject is provided in <u>Section 6.6</u> , "Defining and saving filters".
<b>1</b> 5	Coloring Rules	View/Coloring Rules	This item brings up a dialog box that allows you color packets in the packet list pane according to filter expressions you choose. It can be very useful for spotting certain types of packets. More detail on this subject is provided in Section 10.3, "Packet colorization".
*	Preferences	Edit/Preferences	This item brings up a dialog box that allows you to set preferences for many parameters that control Wireshark. You can also save your preferences so Wireshark will use them the next time you start it. More detail is provided in <u>Section 10.5</u> , "Preferences"
Ø	Help	Help/Contents	This item brings up help dialog box.

### 3.17. The "Filter" toolbar

The filter toolbar lets you quickly edit and apply display filters. More information on display filters is available in <u>Section 6.3</u>, "Filtering packets while viewing".

#### Figure 3.15. The "Filter" toolbar

|--|

<b>Table 3.14</b>	. Filter too	lbar items
-------------------	--------------	------------

Toolbar Icon	Toolbar Item	Description
¥	Filter:	Brings up the filter construction dialog, described in Figure 6.8, "Th "Capture Filters" and "Display Filters" dialog boxes".
	Filter input	The area to enter or edit a display filter string, see <u>Section 6.4</u> , "Building display filter expressions" . A syntax check of your filter string is done while you are typing. The background will turn red if you enter at incomplete or invalid string, and will become green when you enter valid string. You can click on the pull down arrow to select a previously entered filter string from a list. The entries in the pull down list will remain available even after a program restart.
		Note!         After you've changed something in this field, don't forget to press the Apply button (or the Enter/Return key), to apply this filter string to the display.

Toolbar Icon	Toolbar Item	Description
		Note!         This field is also where the current filter in effect is displayed.
ት	Expression	The middle button labeled "Add Expression" opens a dialog box that lets you edit a display filter from a list of protocol fields, described in Section 6.5, "The "Filter Expression" dialog box"
8	Clear	Reset the current display filter and clears the edit area.
V	Apply	Apply the current value in the edit area as the new display filter.
		Note!           Applying a display filter on large capture files might take quite a long time!

### 3.18. The "Packet List" pane

The packet list pane displays all the packets in the current capture file.

#### Figure 3.16. The "Packet List" pane

No	Time	Source	Destination	Protocol	Info	^
	1 0.000000	192.168.0.2	Broadcast	ARP	Who has 192.168.0.27 Gratuitous	
	2 0.299139	192.168.0.1	192.168.0.2	NBNS	Name query NBSTAT *<00><00><1	
	3 0.000075	192.168.0.2	192.168.0.1	ICMP	Destination unreachable (Port uni	
	4 0.726445	192.168.0.2	224.0.0.22	IGMP	V3 Membership Report	
	5 0.018707	192.168.0.2	192.168.0.1	DNS	Standard query SRV _ldaptcp.nb	
	6 0.004286	192.168.0.2	239.255.255.250	SSDP	M-SEARCH * HTTP/1.1	
	7 0.002132	192.168.0.2	192.168.0.1	DNS	Standard query SOA nb10061d.ww00	
	8 0.004269	192.168.0.1	192.168.0.2	SSDP	НТТР/1.1 200 ОК	
	9 0.026985	192.168.0.2	192.168.0.255	NBNS	Registration NB NB10061D<00>	
	0 0.029907	192.168.0.2	192.168.0.1	DNS	Standard query A proxyconf.ww004	
	1 0.114211	192.168.0.2	192.168.0.1	TCP	3196 > http [SYN] Seq=0 Ack=0 Wil	
	2 0.001126	192.168.0.1	192.168.0.2	TCP	<pre>http &gt; 3196 [SYN, ACK] Seq=0 Ack:</pre>	
	3 0.000043	192.168.0.2	192.168.0.1	TCP	3196 > http [ACK] Seq=1 Ack=1 Wi	
	4 0.000126	192.168.0.2	192.168.0.1	HTTP	SUBSCRIBE /upnp/service/Layer3Fo	
	5 0.001858	192.168.0.1	192.168.0.2	TCP	http > 3196 [ACK] Seq=1 Ack=256 \	
	6 0.003112	192.168.0.1	192.168.0.2	TCP	[TCP Window Update] http > 3196	
	7 0.015934	192.168.0.1	192.168.0.2	TCP	1025 > 5000 [SYN] Seq=0 Ack=0 Wil	
	8 0.000036	192.168.0.2	192.168.0.1	TCP	5000 > 1025 [SYN, ACK] Seq=0 Ack:	
1	9 0 001790	107 169 0 1	100 160 0 0	UTTD	UTTO /1 0 200 OV	
<					>	

Each line in the packet list corresponds to one packet in the capture file. If you select a line in this pane, more details will be displayed in the "Packet Details" and "Packet Bytes" panes.

While dissecting a packet, Wireshark will place information from the protocol dissectors into the columns. As higher level protocols might overwrite information from lower levels, you will typically see the information from the highest possible level only.

For example, let's look at a packet containing TCP inside IP inside an Ethernet packet. The Ethernet dissector will write its data (such as the Ethernet addresses), the IP dissector will overwrite this by its own (such as the IP addresses), the TCP dissector will overwrite the IP information, and so on.

There are a lot of different columns available. Which columns are displayed can be selected by preference settings, see <u>Section 10.5</u>, "Preferences".

The default columns will show:

• No. The number of the packet in the capture file. This number won't change, even if a display filter is used.

- **Time** The timestamp of the packet. The presentation format of this timestamp can be changed, see <u>Section 6.12</u>, "Time display formats and time references".
- Source The address where this packet is coming from.
- **Destination** The address where this packet is going to.
- **Protocol** The protocol name in a short (perhaps abbreviated) version.
- Info Additional information about the packet content.

There is a context menu (right mouse click) available, see details in Figure 6.4, "Pop-up menu of the "Packet List" pane".

### 3.19. The "Packet Details" pane

The packet details pane shows the current packet (selected in the "Packet List" pane) in a more detailed form.

#### Figure 3.17. The "Packet Details" pane

```
    B Frame 1 (42 bytes on wire, 42 bytes captured)
    B Ethernet II, Src: 192.168.0.2 (00:00:5d:20:cd:02), Dst: Broadcast (ff:ff:ff:ff:ff:ff:
    Address Resolution Protocol (request/gratuitous ARP)
```

This pane shows the protocols and protocol fields of the packet selected in the "Packet List" pane. The protocols and fields of the packet are displayed using a tree, which can be expanded and collapsed.

There is a context menu (right mouse click) available, see details in Figure 6.5, "Pop-up menu of the "Packet Details" pane".

Some protocol fields are specially displayed.

- Generated fields Wireshark itself will generate additional protocol fields which are surrounded by brackets. The information in these fields is derived from the known context to other packets in the capture file. For example, Wireshark is doing a sequence/acknowledge analysis of each TCP stream, which is displayed in the [SEQ/ACK analysis] fields of the TCP protocol.
- **Links** If Wireshark detected a relationship to another packet in the capture file, it will generate a link to that packet. Links are underlined and displayed in blue. If double-clicked, Wireshark jumps to the corresponding packet.

### 3.20. The "Packet Bytes" pane

The packet bytes pane shows the data of the current packet (selected in the "Packet List" pane) in a hexdump style.

Figure 3.18. The "Packet Bytes" pane

0000 ff ff ff ff ff ff 00 0b 5d 20 cd 02 08 06 00 01 ......] ..... 0010 08 00 06 04 00 01 00 0b 5d 20 cd 02 c0 a8 00 02 .....] ..... 0020 00 00 00 00 00 c0 a8 00 02 ...... As usual for a hexdump, the left side shows the offset in the packet data, in the middle the packet data is shown in a hexadecimal representation and on the right the corresponding ASCII characters (or . if not appropriate) are displayed.

Depending on the packet data, sometimes more than one page is available, e.g. when Wireshark has reassembled some packets into a single chunk of data, see <u>Section 7.6</u>, "<u>Packet Reassembling</u>". In this case there are some additional tabs shown at the bottom of the pane to let you select the page you want to see.

#### Figure 3.19. The "Packet Bytes" pane with tabs

0000	08	00	06	ab	04	53	08	00	06	6b	7f	bd	08	00	45	00	SkE.	~
								11										
0020	09	32	41	af	07	04	01	34	00	b4	04	00	2e	00	10	00	.2A4	
0030	00	00	00	00	a0	de	97	6C	d1	11	82	71	00	57	80	fO	lq.w	×
Frame	(342	byte	s) [	Reas	ssem	bled	DCE	/RPC	(160	14 by	tes)	Τ						



#### Note!

The additional pages might contain data picked from multiple packets.

The context menu (right mouse click) of the tab labels will show a list of all available pages. This can be helpful if the size in the pane is too small for all the tab labels.

### 3.21. The Statusbar

The statusbar displays informational messages.

In general, the left side will show context related information, the middle part will show the current number of packets, and the right side will show the selected configuration profile. Drag the handles between the text areas to change the size.

#### Figure 3.20. The initial Statusbar

O Ready to load or capture	No Packets	Profile: Default	
----------------------------	------------	------------------	--

This statusbar is shown while no capture file is loaded, e.g. when Wireshark is started.

#### Figure 3.21. The Statusbar with a loaded capture file

🔘 File: "/home/stig/http.pcap" 1673 KB 00:00:32 🛛 Packets: 2239 Displayed: 2239 Marked: 0 🔹 Profile: Default

- **The colorized bullet** on the left shows the highest expert info level found in the currently loaded capture file. Hovering the mouse over this icon will show a textual description of the expert info level, and clicking the icon will bring up the Expert Infos dialog box. For a detailed description of expert info, see Section 7.3, "Expert Infos".
- The left side shows information about the capture file, its name, its size and the elapsed time while it was being captured.
- The middle part shows the current number of packets in the capture file. The following values are displayed:
  - Packets: the number of captured packets
  - *Displayed:* the number of packets currently being displayed

- *Marked:* the number of marked packets
- *Dropped:* the number of dropped packets (only displayed if Wireshark was unable to capture all packets)
- Ignored: the number of ignored packets (only displayed if packets are ignored)
- **The right side** shows the selected configuration profile. Clicking in this part of the statusbar will bring up a menu with all available configuration profiles, and selecting from this list will change the configuration profile.

#### Figure 3.22. The Statusbar with a configuration profile menu



For a detailed description of configuration profiles, see Section 10.6, "Configuration Profiles".

#### Figure 3.23. The Statusbar with a selected protocol field

Opcode (arp.opcode), 2 bytes	Packets: 2239 Displayed: 2239 Marked: 0	Profile: Default	

This is displayed if you have selected a protocol field from the "Packet Details" pane.



#### Tip!

The value between the brackets (in this example **arp.opcode**) can be used as a display filter string, representing the selected protocol field.

#### Figure 3.24. The Statusbar with a display filter message

🔘 "!=" may have unexpected results (see the User's Guide) Packets: 2239 Displayed: 2237 Marked: 0 Profile: Default

This is displayed if you are trying to use a display filter which may have unexpected results. For a detailed description, see <u>Section 6.4.4</u>, "A common mistake".

# Chapter 4. Capturing Live Network Data

### 4.1. Introduction

Capturing live network data is one of the major features of Wireshark.

The Wireshark capture engine provides the following features:

- Capture from different kinds of network hardware (Ethernet, Token Ring, ATM, ...).
- Stop the capture on different triggers like: amount of captured data, captured time, captured number of packets.
- Simultaneously show decoded packets while Wireshark keeps on capturing.
- Filter packets, reducing the amount of data to be captured, see <u>Section 4.12</u>, "Filtering while capturing".
- Capturing into multiple files while doing a long term capture, and in addition the option to form a ringbuffer of these files, keeping only the last x files, useful for a "very long term" capture, see <u>Section 4.10, "Capture files and file modes"</u>.
- Simultaneous capturing from multiple network interfaces.

The capture engine still lacks the following features:

• Stop capturing (or doing some other action), depending on the captured data.

### **4.2.** Prerequisites

Setting up Wireshark to capture packets for the first time can be tricky.



#### Tip!

A comprehensive guide "How To setup a Capture" is available at: <u>http://wiki.wireshark.org/</u> <u>CaptureSetup</u>.

Here are some common pitfalls:

- You need to have root / Administrator privileges to start a live capture.
- You need to choose the right network interface to capture packet data from.
- You need to capture at the right place in the network to see the traffic you want to see.
- ... and a lot more!.

If you have any problems setting up your capture environment, you should have a look at the guide mentioned above.

### 4.3. Start Capturing

One of the following methods can be used to start capturing packets with Wireshark:

- You can get an overview of the available local interfaces using the "A Capture Interfaces" dialog box, see Figure 4.1, "The "Capture Interfaces" dialog box on Microsoft Windows" or Figure 4.2, "The "Capture Interfaces" dialog box on Unix/Linux". You can start a capture from this dialog box, using (one of) the "Capture" button(s).
- You can start capturing using the " Capture Options" dialog box, see Figure 4.3, "The "Capture Options" dialog box".
- If you have selected the right capture options before, you can immediately start a capture using the " Capture Start" menu / toolbar item. The capture process will start immediately.
- If you already know the name of the capture interface, you can start Wireshark from the command line and use the following:

wireshark -i eth0 -k

This will start Wireshark capturing on interface eth0, more details can be found at: <u>Section 10.2</u>, <u>"Start Wireshark from the command line"</u>.

### 4.4. The "Capture Interfaces" dialog box

When you select "Interfaces..." from the Capture menu, Wireshark pops up the "Capture Interfaces" dialog box as shown in Figure 4.1, "The "Capture Interfaces" dialog box on Microsoft Windows" or Figure 4.2, "The "Capture Interfaces" dialog box on Unix/Linux".



#### This dialog consumes lots of system resources!

As the "Capture Interfaces" dialog is showing live captured data, it is consuming a lot of system resources. Close this dialog as soon as possible to prevent excessive system load.



#### Not all available interfaces may be displayed!

This dialog box will only show the local interfaces Wireshark knows of. It will not show interfaces marked as hidden in <u>Section 10.5.1</u>, "Interface Options". As Wireshark might not be able to detect all local interfaces, and it cannot detect the remote interfaces available, there could be more capture interfaces available than listed.

As it is possible to simultaneously capture packets from multiple interfaces, the toggle buttons can be used to select one or more interfaces.




Figure 4.1. The "Capture Interfaces" dialog box on Microsoft Windows

Figure 4.2. The "Capture Interfaces" dialog box on Unix/Linux

😣 🗖 🔳 🛛 Wire	shark: Capture Interfaces	
Device	Description	IP
🔲 🛃 eth0	19	2.168.42
🗌 🚆 usbmon	1 USB bus number 1	none
🗌 🚆 usbmon	2 USB bus number 2	none
🗌 🗊 any	Pseudo-device that captures on all interfaces	none
🗌 🛃 lo		127.0.0
Help	Start Sto	р

Device (Unix/Linux only)	The interface device name.
Description	The interface description provided by the operating system, or the user defined comment added in <u>Section 10.5.1, "Interface Options"</u> .
IP	The first IP address Wireshark could find for this interface. You can click on the address to cycle through other addresses assigned to it, if available. If no address could be found "none" will be displayed.
Packets	The number of packets captured from this interface, since this dialog was opened. Will be greyed out, if no packet was captured in the last second.

Packets/s	Number of packets captured in the last second. Will be greyed out, if no packet was captured in the last second.
Stop	Stop a currently running capture.
Start	Start a capture on all selected interfaces immediately, using the settings from the last capture or the default settings, if no options have been set.
Options	Open the Capture Options dialog with the marked interfaces selected, see Section 4.5, "The "Capture Options" dialog box".
Details (Microsoft Windows only)	Open a dialog with detailed information about the interface, see <u>Section 4.9, "The "Interface Details" dialog box"</u> .
Help	Show this help page.
Close	Close this dialog box.

### 4.5. The "Capture Options" dialog box

When you select Options... from the Capture menu (or use the corresponding item in the "Main" toolbar), Wireshark pops up the "Capture Options" dialog box as shown in <u>Figure 4.3</u>, "The "Capture Options" dialog box".

### 😢 亘 💿 Wireshark: Capture Options

Capture								
Capture	Interface		Link-layer	head	der			
<b></b>	<b>eth0</b> 192.168.42.133 fe80::20c:29ff:fe3a:3a40	)	Ethernet					
	USB bus number 1:	usbm	USB with padded	Lin	ux header			
	USB bus number 2:	usbm	USB with padded	Lin	ux header			
	Pseudo-device tha	t capt	Linux cooked					
~	<b>lo (loopback)</b> 127.0.0.1 ::1		Ethernet					
🗹 Captu	<ul> <li>Capture on all interfaces</li> <li>Capture all in promiscuous mode</li> <li>Capture File(s)</li> </ul>							
File:								
🗌 Use m	ultiple files				🗹 Use po			
🗹 Next f	file every	1		*	megabyt			
🗌 Next f	file every	1		*	minute(s			
🗌 Ring b	uffer with	2		-	files			
🔲 Stop o	apture after	1		*	file(s)			
Stop Capt	ure							
🗌 afte	er	1		*	packet(s)			
🗌 afte	er	1		*	megabyt			
🗌 afte	er	1		*	minute(s			
Help								



Tip!

If you are unsure which options to choose in this dialog box, just try keeping the defaults as this should work well in many cases.

### 4.5.1. Capture frame

The table shows the settings for all available interfaces:

• The name of the interface and its IP addresses. If no address could be resolved from the system, "none" will be shown.



#### Note

loopback interfaces are not available on Windows platforms.

- The link-layer header type.
- The information whether promicuous mode is enabled or disabled.
- The maximum amount of data that will be captured for each packet. The default value is set to the 65535 bytes.
- The size of the kernel buffer that is reserved to keep the captured packets.
- The information whether packets will be captured in monitor mode (Unix/Linux only).
- The chosen capture filter.

By marking the checkboxes in the first column the interfaces are selected to be captured from. By doubleclicking on an interface the "Edit Interface Settings" dialog box as shown in <u>Figure 4.4, "The "Edit Interface</u> <u>Settings" dialog box"</u> will be opened.

Capture on all interfaces	As Wireshark can capture on multiple interfaces, it is possible to choose to capture on all available interfaces.
Capture all packets in promiscuous mode	This checkbox allows you to specify that Wireshark should put all interfaces in promiscuous mode when capturing.
Manage Interfaces	The "Manage Interfaces" button leads you to Figure 4.5, "The "Add <u>New Interfaces" dialog box</u> " where pipes can be defined, local interfaces scanned or hidden, or remote interfaces added (Windows only).

### 4.5.2. Capture File(s) frame

An explanation about capture file usage can be found in Section 4.10, "Capture files and file modes".

File

This field allows you to specify the file name that will be used for the capture file. This field is left blank by default. If the field is left blank, the capture data will be stored in a temporary file, see Section 4.10, "Capture files and file modes" for details.

You can also click on the button to the right of this field to browse through the filesystem.

Use multiple files	Instead of using a single file, Wireshark will automatically switch to a new one, if a specific trigger condition is reached.
Use pcap-ng format	This checkbox allows you to specify that Wireshark saves the captured packets in pcap-ng format. This next generation capture file format is currently in development. If more than one interface is chosen for capturing, this checkbox is set by default. See <a href="http://wiki.wireshark.org/Development/PcapNg">http://wiki.wireshark.org/Development/PcapNg</a> for more details on pcap-ng.
Next file every n megabyte(s)	Multiple files only: Switch to the next file after the given number of byte(s)/kilobyte(s)/megabyte(s)/gigabyte(s) have been captured.
Next file every n minute(s)	Multiple files only: Switch to the next file after the given number of second(s)/minutes(s)/hours(s)/days(s) have elapsed.
Ring buffer with n files	Multiple files only: Form a ring buffer of the capture files, with the given number of files.
Stop capture after n file(s)	Multiple files only: Stop capturing after switching to the next file the given number of times.

### 4.5.3. Stop Capture... frame

after n packet(s)	Stop capturing after the given number of packets have been captured.
after n megabytes(s)	Stop capturing after the given number of byte(s)/kilobyte(s)/ megabyte(s)/gigabyte(s) have been captured. This option is greyed out, if "Use multiple files" is selected.
after n minute(s)	Stop capturing after the given number of second(s)/minutes(s)/ hours(s)/days(s) have elapsed.

### 4.5.4. Display Options frame

Update list of packets in real time	This option allows you to specify that Wireshark should update the packet list pane in real time. If you do not specify this, Wireshark does not display any packets until you stop the capture. When you check this, Wireshark captures in a separate process and feeds the captures to the display process.
Automatic scrolling in live capture	This option allows you to specify that Wireshark should scroll the packet list pane as new packets come in, so you are always looking at the last packet. If you do not specify this, Wireshark simply adds new packets onto the end of the list, but does not scroll the packet list pane. This option is greyed out if "Update list of packets in real time" is disabled.
Hide capture info dialog	If this option is checked, the capture info dialog described in <u>Section 4.13, "While a Capture is running</u> " will be hidden.

### 4.5.5. Name Resolution frame

Enable MAC name resolution	This option allows you to control whether or not Wireshark translates MAC addresses into names, see <u>Section 7.7, "Name Resolution"</u> .
Enable network name resolution	This option allows you to control whether or not Wireshark translates network addresses into names, see <u>Section 7.7, "Name Resolution"</u> .
Enable transport name resolution	This option allows you to control whether or not Wireshark translates transport addresses into protocols, see <u>Section 7.7</u> , <u>"Name Resolution"</u> .

### 4.5.6. Buttons

Once you have set the values you desire and have selected the options you need, simply click on **Start** to commence the capture, or **Cancel** to cancel the capture.

If you start a capture, Wireshark allows you to stop capturing when you have enough packets captured, for details see <u>Section 4.13</u>, "While a Capture is running ...".

### 4.6. The "Edit Interface Settings" dialog box

If you double-click on an interface in Figure 4.3, "The "Capture Options" dialog box" the following dialog box pops up.

#### Figure 4.4. The "Edit Interface Settings" dialog box

I	📶 Edit Interf	ace Settings		
	Capture			
	Interface:	Intel(R) PRO/1000 MT Network Connection: \Device\NPF_{5A064798-6A61-4599-9D		
	IP address:	fe80::6c22:d696:3c23:f963		
		2002:d4c9:795e:0:7584:eb62:4211:67d5		
	Link-layer he	ader type: Ethernet		
Capture packets in promiscuous mode				
	Limit each packet to 65535 - bytes			
Buffer size: 1 megabyte(s)				
	<u>Capture</u> Filt	er:		
	Help	<u>O</u> K		

You can set the following fields in this dialog box:

IP address	The IP address(es) of the selected interface. If no address could be resolved from the system, "none" will be shown.
Link-layer header type	Unless you are in the rare situation that you need this, just keep the default. For a detailed description, see <u>Section 4.11, "Link-layer header type"</u>
Wireless settings (Windows only)	Here you can set the settings for wireless capture using the AirPCap adapter. For a detailed description, see the AirPCap Users Guide.
Remote settings (Windows only)	Here you can set the settings for remote capture. For a detailed description, see <u>Section 4.8</u> , "The "Remote Capture Interfaces" <u>dialog box"</u>
Capture packets in promiscuous mode	This checkbox allows you to specify that Wireshark should put the interface in promiscuous mode when capturing. If you do not specify this, Wireshark will only capture the packets going to or from your computer (not all packets on your LAN segment).



#### Note

If some other process has put the interface in promiscuous mode you may be capturing in promiscuous mode even if you turn off this option.

Ш	
н	-12
н	-68
н	- <b>1</b>
	- C - L

### Note

Even in promiscuous mode you still won't necessarily see all packets on your LAN segment, see <u>http://</u><u>www.wireshark.org/faq.html#promiscsniff</u> for some more explanations.

Limit each packet to n bytes	This field allows you to specify the maximum amount of data that will be captured for each packet, and is sometimes referred to as the <b>snaplen</b> . If disabled, the value is set to the maximum 65535, which will be sufficient for most protocols. Some rules of thumb:
	• If you are unsure, just keep the default value.
	• If you don't need all of the data in a packet - for example, if you only need the link-layer, IP, and TCP headers - you might want to choose a small snapshot length, as less CPU time is required for copying packets, less buffer space is required for packets, and thus perhaps fewer packets will be dropped if traffic is very heavy.
	• If you don't capture all of the data in a packet, you might find that the packet data you want is in the part that's dropped, or that reassembly isn't possible as the data required for reassembly is missing.
Buffer size: n megabyte(s)	Enter the buffer size to be used while capturing. This is the size of the kernel buffer which will keep the captured packets, until they are written to disk. If you encounter packet drops, try increasing this value.
Capture packets in monitor mode (Unix/Linux only)	This checkbox allows you to setup the Wireless interface to capture all traffic it can receive, not just the traffic on the BSS to which it is associated, which can happen even when you set promiscuous mode. Also it might be necessary to turn this option on in order to see IEEE 802.11 headers and/or radio information from the captured frames.
	Note
	In monitor mode the adapter might disassociate itself from the network it was associated to.
Capture Filter	This field allows you to specify a capture filter. Capture filters are discussed in more details in <u>Section 4.12</u> , "Filtering while <u>capturing</u> ". It defaults to empty, or no filter.
	You can also click on the button labeled "Capture Filter", and Wireshark will bring up the Capture Filters dialog box and allow you to create and/or select a filter. Please see <u>Section 6.6, "Defining and saving filters"</u>

This button allows you to compile the capture filter into BPF code and pop up a window showing you the resulting pseudo code. This

**Compile BPF** 

can help in understanding the working of the capture filter you created.

### 4.7. The "Add New Interfaces" dialog box

As a central point to manage interfaces this dialog box consists of three tabs to add or remove interfaces.

Figure 4.5. The "Add New Interfaces" dialog box

Add new interfaces		
Pipes Local Interfaces Remote Interfaces		
<u>N</u> ew		
Pipe:		Bro
	<u>S</u> ave	

### 4.7.1. Add or remove pipes

Figure 4.6. The "Add New Interfaces - Pipes" dialog box

🗖 Add new ir	nterfaces	
Pipes Local	Interfaces Remote Interfaces	
[ [	Pipes	
	/tmp/pipe1	
New	/tmp/pipe2	
	New pipe	
<u>D</u> elete		
		_
Pipe: Ne	ew pipe	Bro
	<u>Save</u>	2

To successfully add a pipe, this pipe must have already been created. Click the "New" button and type the name of the pipe including its path. Alternatively, the "Browse" button can be used to locate the pipe. With the "Save" button the pipe is added to the list of available interfaces. Afterwards, other pipes can be added.

To remove a pipe from the list of interfaces it first has to be selected. Then click the "Delete" button.

### 4.7.2. Add or hide local interfaces

Figure 4.7. The "Add New Interfaces - Local Interfaces" dialog box

Name	
\\airpcap03	
\\.\airpcap04	
\\.\airpcap05	
\Device\NPF_{5A064798-6A61-4599-9DEB-ECB648DA9EA7}	
\Device\NPF_{15B26C38-C23D-4ED6-83F0-350ABE0DE44A}	
\Device\NPF_{E55BE96C-F8EC-43E4-8225-E991F159225D}	
Device NDE (77594004 0607 4900 9775 655025534552)	

The tab "Local Interfaces" contains a list of available local interfaces, including the hidden ones, which are not shown in the other lists.

If a new local interface is added, for example, a wireless interface has been activated, it is not automatically added to the list to prevent the constant scanning for a change in the list of available interfaces. To renew the list a rescan can be done.

One way to hide an interface is to change the preferences. If the "Hide" checkbox is activated and the "Apply" button clicked, the interface will not be seen in the lists of the "Capture Options" or "Capture Interfaces" dialog box any more. The changes are also saved in the "Preferences" file.

### **4.7.3. Add or hide remote interfaces**

Figure 4.8. The "Add New Interfaces - Remote Interfaces" dialog box

	Add new inter	face	15	
	Pipes Local Inte Remote Interfac		es Remote Interfaces	
	Host	•	Name	
	□ 10.0.1.207			
rpcap://[10.0.1.207]/\\.\airpcap00			rpcap://[10.0.1.207]/\\.\airpcap00	
			rpcap://[10.0.1.207]/\Device\WPF_{0E76EBE1-9CA3-4	
			rpcap://[10.0.1.207]/\Device\NPF_{2DD56791-752F-4	
			rpcap://[10.0.1.207]/\Device\NPF_{9518C1AB-9151-4	KFC-8D45-A17E981A
	<u>A</u> dd	1	Delete	Apply

In this tab interfaces on remote hosts can be added. One or more of these interfaces can be hidden. In contrast to the local interfaces they are not saved in the "Preferences" file.

To remove a host including all its interfaces from the list, it has to be selected. Then click the "Delete" button.

For a detailed description, see Section 4.8, "The "Remote Capture Interfaces" dialog box"

## 4.8. The "Remote Capture Interfaces" dialog box

Besides doing capture on local interfaces Wireshark is capable of reaching out across the network to a so called capture daemon or service processes to receive captured data from.



#### **Microsoft Windows only**

This dialog and capability is only available on Microsoft Windows. On Linux/Unix you can achieve the same effect (securely) through an SSH tunnel.

The Remote Packet Capture Protocol service must first be running on the target platform before Wireshark can connect to it. The easiest way is to install WinPcap from <a href="http://www.winpcap.org/install/default.htm">http://www.winpcap.org/install/default.htm</a>

on the target. Once installation is completed go to the Services control panel, find the Remote Packet Capture Protocol service and start it.



#### Note

Make sure you have outside access to port 2002 on the target platform. This is the port where the Remote Packet Capture Protocol service can be reached, by default.

To access the Remote Capture Interfaces dialog use the "Add New Interfaces - Remote" dialog, see Figure 4.8, "The "Add New Interfaces - Remote Interfaces" dialog box", and select "Add".

### 4.8.1. Remote Capture Interfaces

Figure 4.9. The "Remote Capture Interfaces" dialog box

Add new inte		es res Remote Interfaces	Wireshark: Remote Interfa
Remote Interfa	•	Name rpcap://[10.0.1.207]/\\.\airp rpcap://[10.0.1.207]/\Device rpcap://[10.0.1.207]/\Device rpcap://[10.0.1.207]/\Device	Username;
Add		Delete	<u>Q</u> K <u>C</u> ancel Apply

You have to set the following parameter in this dialog:

HostEnter the IP address or host name of the target platform where<br/>the Remote Packet Capture Protocol service is listening. The drop<br/>down list contains the hosts that have previously been successfully<br/>contacted. The list can be emptied by choosing "Clear list" from the<br/>drop down list.PortSet the port number where the Remote Packet Capture Protocol<br/>service is listening on. Leave open to use the default port (2002).

Null authentication	Select this if you don't need authentication to take place for a remote capture to be started. This depends on the target platform. Configuring the target platform like this makes it insecure.	
Password authentication	This is the normal way of connecting to a target platform. Set the credentials needed to connect to the Remote Packet Capture Protocol service.	

## 4.8.2. Remote Capture Settings

The remote capture can be further fine tuned to match your situation. The **Remote Settings** button in Figure 4.4, "The "Edit Interface Settings" dialog box" gives you this option. It pops up the dialog shown in Figure 4.10, "The "Remote Capture Settings" dialog box".

#### Figure 4.10. The "Remote Capture Settings" dialog box

Į	📶 Edit Interf	ace Settings	
	Capture		
	Interface:	Network adapter 'Intel(R) Gigabit ET Dual Port Server Adapter'	🗖 Remote Captu
	IP address:	10.0.1.207	Capture Options
			Do not captur
	Link-layer he	ader type: Ethernet 💌	Use UDP for d
	🗌 Capture p	oackets in promiscuous mode	Sampling Options –
	Limit each	packet to 65535 - bytes	
	Buffer size:	- megabyte(s)	0 1 of 1
	<u>C</u> apture Filt	er:	C 1 every 1
	Hala	1	<u>O</u> K
	Help		

You can set the following parameters in this dialog:

Do not capture own RPCAP traffic	This option sets a capture filter so that the traffic flowing back from the Remote Packet Capture Protocol service to Wireshark isn't captured as well and also send back. The recursion in this saturates the link with duplicate traffic.	
	You only should switch this off when capturing on an interface other then the interface connecting back to Wireshark.	
Use UDP for data transfer	Remote capture control and data flows over a TCP connection. This option allows you to choose an UDP stream for data transfer.	

Sampling option None	This option instructs the Remote Packet Capture Protocol service to send back all captured packets which have passed the capture filter. This is usually not a problem on a remote capture session with sufficient bandwidth.
Sampling option 1 of x packets	This option limits the Remote Packet Capture Protocol service to send only a sub sampling of the captured data, in terms of number of packets. This allows capture over a narrow band remote capture session of a higher bandwidth interface.
Sampling option 1 every x milliseconds	This option limits the Remote Packet Capture Protocol service to send only a sub sampling of the captured data, in terms of time. This allows capture over a narrow band capture session of a higher bandwidth interface.

## 4.9. The "Interface Details" dialog box

When you select Details from the Capture Interface menu, Wireshark pops up the "Interface Details" dialog box as shown in <u>Figure 4.11, "The "Interface Details" dialog box</u>". This dialog shows various characteristics and statistics for the selected interface.



#### **Microsoft Windows only**

This dialog is only available on Microsoft Windows

#### Figure 4.11. The "Interface Details" dialog box

📶 Wireshark: Interface Details	. 🗆 🗙
Characteristics Statistics 802.3 (Ethernet) 802.11 (WLAN) Task Offload	
Characteristics	
Vendor description Parallels OEM Adapter. (Microsoft's Packet Scheduler)	
Interface \Device\NPF_{5D34CEE1-5D21-4A23-A14B-9412C6A313	EB}
Link status Connected	·
Link speed 1000 MBits/s	
Media supported 802.3 (Ethernet)	
Medium in use 802.3 (Ethernet)	
Physical medium -	
NDIS Driver Version 5.0	
Vendor Driver Version -	
Vendor ID 00:1C:42 (Parallel) NIC: 00	
MAC Options 802.1P Priority: Unsupported, 802.1Q VLAN: Unsupporte	d
VLAN ID -	
Transmit Buffer Space 524288	
Receive Buffer Space 524288	
Transmit Block Size 1514	
Receive Block Size 1514 Maximum Packet Size 1514	
Maximum Packet Size 1514	
Note: accuracy of all of these values are only relying on the network card driver	!
Help	

## 4.10. Capture files and file modes

While capturing, the underlying libpcap capturing engine will grab the packets from the network card and keep the packet data in a (relatively) small kernel buffer. This data is read by Wireshark and saved into the capture file(s) the user specified.

Different modes of operation are available when saving this packet data to the capture file(s).



#### Tip!

Working with large files (several 100 MB's) can be quite slow. If you plan to do a long term capture or capturing from a high traffic network, think about using one of the "Multiple files" options. This will spread the captured packets over several smaller files which can be much more pleasant to work with.



#### Note!

Using Multiple files may cut context related information. Wireshark keeps context information of the loaded packet data, so it can report context related problems (like a stream error) and keeps information about context related protocols (e.g. where data is exchanged at the establishing phase and only referred to in later packets). As it keeps this information only for the loaded file, using one of the multiple file modes may cut these contexts. If the establishing phase is saved in one file and the things you would like to see is in another, you might not see some of the valuable context related information.



#### Tip!

Information about the folders used for the capture file(s), can be found in <u>Appendix A</u>, *Files* <u>and Folders</u>.

"File" option	"Use multiple files" option	''Ring buffer with n files'' option	Mode	Resulting filename(s) used
-	-	-	Single temporary file	wiresharkXXXXXX (where XXXXXX is a unique number)
foo.cap	-	-	Single named file	foo.cap
foo.cap	X	-	Multiple files, continuous	foo_00001_20100205110102.cap, foo_00002_20100205110318.cap,
foo.cap	X	x	Multiple files, ring buffer	foo_00001_20100205110102.cap, foo_00002_20100205110318.cap,
Single temporary file		A temporary file will be created and used (this is the default). After the capturing is stopped, this file can be saved later under a user specified name.		
Single named file		A single capture file will be used. If you want to place the new capture file to a specific folder, choose this mode.		
Multiple files, continuous		Like the "Single named file" mode, but a new file is created and used, after reaching one of the multiple file switch conditions (one of the "Next file every" values).		
Multiple files, ring buffer		Much like "Multiple files continuous", reaching one of the multiple files switch conditions (one of the "Next file every" values) will switch to the next file. This will be a newly created file if value of "Ring buffer with n files" is not reached, otherwise it will replace the oldest of the formerly used files (thus forming a "ring").		

#### Table 4.1. Capture file mode selected by capture options

This mode will limit the maximum disk usage, even for an unlimited amount of capture input data, keeping the latest captured data.

## 4.11. Link-layer header type

In the usual case, you won't have to choose this link-layer header type. The following paragraphs describe the exceptional cases, where selecting this type is possible, so you will have a guide of what to do:

If you are capturing on an 802.11 device on some versions of BSD, this might offer a choice of "Ethernet" or "802.11". "Ethernet" will cause the captured packets to have fake Ethernet headers; "802.11" will cause them to have IEEE 802.11 headers. Unless the capture needs to be read by an application that doesn't support 802.11 headers, you should select "802.11".

If you are capturing on an Endace DAG card connected to a synchronous serial line, this might offer a choice of "PPP over serial" or "Cisco HDLC"; if the protocol on the serial line is PPP, select "PPP over serial", and if the protocol on the serial line is Cisco HDLC, select "Cisco HDLC".

If you are capturing on an Endace DAG card connected to an ATM network, this might offer a choice of "RFC 1483 IP-over-ATM" or "Sun raw ATM". If the only traffic being captured is RFC 1483 LLC-encapsulated IP, or if the capture needs to be read by an application that doesn't support SunATM headers, select "RFC 1483 IP-over-ATM", otherwise select "Sun raw ATM".

If you are capturing on an Ethernet device, this might offer a choice of "Ethernet" or "DOCSIS". If you are capturing traffic from a Cisco Cable Modem Termination System that is putting DOCSIS traffic onto the Ethernet to be captured, select "DOCSIS", otherwise select "Ethernet".

## 4.12. Filtering while capturing

Wireshark uses the libpcap filter language for capture filters. This is explained in the tcpdump man page, which can be hard to understand, so it's explained here to some extent.



#### Tip!

You will find a lot of Capture Filter examples at <u>http://wiki.wireshark.org/CaptureFilters</u>.

You enter the capture filter into the Filter field of the Wireshark Capture Options dialog box, as shown in Figure 4.3, "The "Capture Options" dialog box". The following is an outline of the syntax of the **tcpdump** capture filter language. See the expression option at the tcpdump manual page for details: <u>http:</u>//www.tcpdump.org/tcpdump\_man.html.

A capture filter takes the form of a series of primitive expressions connected by conjunctions (**and/or**) and optionally preceded by **not**:

[not] **primitive** [and | or [not] **primitive** ...]

An example is shown in Example 4.1, "A capture filter for telnet that captures traffic to and from a particular host".

## Example 4.1. A capture filter for telnet that captures traffic to and from a particular host

```
tcp port 23 and host 10.0.0.5
```

This example captures telnet traffic to and from the host 10.0.0.5, and shows how to use two primitives and the **and** conjunction. Another example is shown in Example 4.2, "Capturing all telnet traffic not from 10.0.0.5", and shows how to capture all telnet traffic except that from 10.0.0.5.

#### Example 4.2. Capturing all telnet traffic not from 10.0.0.5

tcp port 23 and not src host 10.0.0.5

XXX - add examples to the following list.

A primitive is simply one of the following:

[src dst] host <host></host>	This primitive allows you to filter on a host IP address or name. You can optionally precede the primitive with the keyword <b>src</b>   <b>dst</b> to specify that you are only interested in source or destination addresses. If these are not present, packets where the specified address appears as either the source or the destination address will be selected.
ether [src dst] host <ehost></ehost>	This primitive allows you to filter on Ethernet host addresses. You can optionally include the keyword <b>src dst</b> between the keywords <b>ether</b> and <b>host</b> to specify that you are only interested in source or destination addresses. If these are not present, packets where the specified address appears in either the source or destination address will be selected.
gateway host <host></host>	This primitive allows you to filter on packets that used <b>host</b> as a gateway. That is, where the Ethernet source or destination was <b>host</b> but neither the source nor destination IP address was <b>host</b> .
[src dst] net <net> [{mask <mask>} {len <len>}]</len></mask></net>	This primitive allows you to filter on network numbers. You can optionally precede this primitive with the keyword <b>src dst</b> to specify that you are only interested in a source or destination network. If neither of these are present, packets will be selected that have the specified network in either the source or destination address. In addition, you can specify either the netmask or the CIDR prefix for the network if they are different from your own.
[tcp udp] [src dst] port <port></port>	This primitive allows you to filter on TCP and UDP port numbers. You can optionally precede this primitive with the keywords <b>src dst</b> and <b>tcp udp</b> which allow you to specify that you are only interested in source or destination ports and TCP or UDP packets respectively. The keywords <b>tcp udp</b> must appear before <b>src dst</b> .
	If these are not specified, packets will be selected for both the TCP and UDP protocols and when the specified address appears in either the source or destination port field.
less greater <length></length>	This primitive allows you to filter on packets whose length was less than or equal to the specified length, or greater than or equal to the specified length, respectively.
ip ether proto <protocol></protocol>	This primitive allows you to filter on the specified protocol at either the Ethernet layer or the IP layer.

ether ip broadcast multicast	This primitive allows you to filter on either Ethernet or IP broadcasts or multicasts.
<expr> relop <expr></expr></expr>	This primitive allows you to create complex filter expressions that select bytes or ranges of bytes in packets. Please see the tcpdump man page at <u>http://www.tcpdump.org/tcpdump_man.html</u> for more details.

## 4.12.1. Automatic Remote Traffic Filtering

If Wireshark is running remotely (using e.g. SSH, an exported X11 window, a terminal server, ...), the remote content has to be transported over the network, adding a lot of (usually unimportant) packets to the actually interesting traffic.

To avoid this, Wireshark tries to figure out if it's remotely connected (by looking at some specific environment variables) and automatically creates a capture filter that matches aspects of the connection.

The following environment variables are analyzed:

SSH_CONNECTION (ssh)	<remote ip=""> <remote port=""> <local ip=""> <local port=""></local></local></remote></remote>
SSH_CLIENT (ssh)	<remote ip=""> <remote port=""> <local port=""></local></remote></remote>
<b>REMOTEHOST</b> (tcsh, others?)	<remote name=""></remote>
DISPLAY (x11)	[remote name]: <display num=""></display>
SESSIONNAME (terminal server)	<remote name=""></remote>

## 4.13. While a Capture is running ...

While a capture is running, the following dialog box is shown:

#### Figure 4.12. The "Capture Info" dialog box

🔏 Wireshark	: Capture fi	om Broadco	. 💶 🗖
Captured Packe	ets		
Total	148	% of total	
SCTP	0		0,0%
TCP	4		2,7%
UDP	102		68,9%
ICMP	0		0,0%
ARP	24		16,2%
OSPF	0		0,0%
GRE	0		0,0%
NetBIOS	0		0,0%
IPX	5		3,4%
VINES	0		0,0%
Other	13		8,8%
Running	00:00:11		Stop

This dialog box will inform you about the number of captured packets and the time since the capture was started. The selection of which protocols are counted cannot be changed.



#### Tip!

This Capture Info dialog box can be hidden, using the "Hide capture info dialog" option in the Capture Options dialog box.

## 4.13.1. Stop the running capture

A running capture session will be stopped in one of the following ways:

<sup>1.</sup> Using the " Stop" button from the **Capture Info dialog box** .



#### Note!

The Capture Info dialog box might be hidden, if the option "Hide capture info dialog" is used.

- <sup>2.</sup> Using the **menu item** "Capture/ Stop".
- <sup>3.</sup> Using the **toolbar item** " Stop".
- 4. Pressing the accelerator keys: Ctrl+E.
- 5. The capture will be automatically stopped, if one of the **Stop Conditions** is exceeded, e.g. the maximum amount of data was captured.

## 4.13.2. Restart a running capture

A running capture session can be restarted with the same capture options as the last time, this will remove all packets previously captured. This can be useful, if some uninteresting packets are captured and there's no need to keep them.

Restart is a convenience function and equivalent to a capture stop following by an immediate capture start. A restart can be triggered in one of the following ways:

- <sup>1.</sup> Using the **menu item** "Capture Restart".
- <sup>2.</sup> Using the **toolbar item** " Restart".

# Chapter 5. File Input / Output and Printing

## 5.1. Introduction

This chapter will describe input and output of capture data.

- Open/Import capture files in various capture file formats
- Save/Export capture files in various capture file formats
- Merge capture files together
- Print packets

## 5.2. Open capture files

Wireshark can read in previously saved capture files. To read them, simply select the menu or toolbar item: "File/ Deen". Wireshark will then pop up the File Open dialog box, which is discussed in more detail in Section 5.2.1, "The "Open Capture File" dialog box".



#### It's convenient to use drag-and-drop!

... to open a file, by simply dragging the desired file from your file manager and dropping it onto Wireshark's main window. However, drag-and-drop is not available/won't work in all desktop environments.

If you haven't previously saved the current capture file, you will be asked to do so, to prevent data loss (this behaviour can be disabled in the preferences).

In addition to its native file format (libpcap format, also used by tcpdump/WinDump and other libpcap/ WinPcap-based programs), Wireshark can read capture files from a large number of other packet capture programs as well. See <u>Section 5.2.2</u>, "Input File Formats" for the list of capture formats Wireshark understands.

## 5.2.1. The "Open Capture File" dialog box

The "Open Capture File" dialog box allows you to search for a capture file containing previously captured packets for display in Wireshark. <u>Table 5.1, "The system specific "Open Capture File" dialog box</u>" shows some examples of the Wireshark Open File Dialog box.



#### The dialog appearance depends on your system!

The appearance of this dialog depends on the system and/or GTK+ toolkit version used. However, the functionality remains basically the same on any particular system.

Common dialog behaviour on all systems:

- Select files and directories.
- Click the Open/Ok button to accept your selected file and open it.
- Click the Cancel button to go back to Wireshark and not load a capture file.

Wireshark extensions to the standard behaviour of these dialogs:

- View file preview information (like the filesize, the number of packets, ...), if you've selected a capture file.
- Specify a display filter with the "Filter:" button and filter field. This filter will be used when opening the new file. The text field background becomes green for a valid filter string and red for an invalid one. Clicking on the Filter button causes Wireshark to pop up the Filters dialog box (which is discussed further in <u>Section 6.3, "Filtering packets while viewing"</u>).

XXX - we need a better description of these read filters


• Specify which type of name resolution is to be performed for all packets by clicking on one of the "... name resolution" check buttons. Details about name resolution can be found in <u>Section 7.7, "Name Resolution"</u>.



#### Save a lot of time loading huge capture files!

You can change the display filter and name resolution settings later while viewing the packets. However, loading huge capture files can take a significant amount of extra time if these settings are changed later, so in such situations it can be a good idea to set at least the filter in advance here.

#### Table 5.1. The system specific "Open Capture File" dialog box



	items like: "Home", "Desktop", and "Filesystem" cannot be removed).
	• If Wireshark doesn't recognize the selected file as a capture file, it will grey out the "Open" button.
Figure 5.3. "Open" - old GTK version	Unix/Linux: GTK version < 2.4
Standards Oynes Cepture Fite     Image: Standard	<ul> <li>This is the file open dialog of former Gimp/GNOME versions - plus some Wireshark extensions.</li> <li>Specific for this dialog:</li> <li>If Wireshark doesn't recognize the selected file as a capture file, it will grey out the "Ok" button.</li> </ul>

## **5.2.2. Input File Formats**

The following file formats from other capture tools can be opened by Wireshark:

- libpcap captures from *Wireshark/TShark/dumpcap*, *tcpdump*, and various other tools using libpcap's/ tcpdump's capture format
- pcap-ng "next-generation" successor to libpcap format
- Sun snoop and atmsnoop
- Shomiti/Finisar Surveyor captures
- Novell LANalyzer captures
- Microsoft Network Monitor captures
- AIX's iptrace captures
- Cinco Networks NetXray captures
- Network Associates Windows-based Sniffer and Sniffer Pro captures
- Network General/Network Associates DOS-based Sniffer (compressed or uncompressed) captures
- AG Group/WildPackets EtherPeek/TokenPeek/AiroPeek/EtherHelp/PacketGrabber captures
- RADCOM's WAN/LAN Analyzer captures
- Network Instruments Observer version 9 captures
- Lucent/Ascend router debug output
- HP-UX's nettl
- Toshiba's ISDN routers dump output

- ISDN4BSD *i4btrace* utility
- traces from the EyeSDN USB S0
- IPLog format from the Cisco Secure Intrusion Detection System
- pppd logs (pppdump format)
- the output from VMS's TCPIPtrace/TCPtrace/UCX\$TRACE utilities
- the text output from the DBS Etherwatch VMS utility
- Visual Networks' Visual UpTime traffic capture
- the output from CoSine L2 debug
- the output from Accellent's 5Views LAN agents
- Endace Measurement Systems' ERF format captures
- Linux Bluez Bluetooth stack hcidump -w traces
- Catapult DCT2000 .out files
- Gammu generated text output from Nokia DCT3 phones in Netmonitor mode
- IBM Series (OS/400) Comm traces (ASCII & UNICODE)
- Juniper Netscreen snoop captures
- Symbian OS btsnoop captures
- Tamosoft CommView captures
- Textronix K12xx 32bit .rf5 format captures
- Textronix K12 text file format captures
- Apple PacketLogger captures
- Captures from Aethra Telecommunications' PC108 software for their test instruments
- ... new file formats are added from time to time

ñ		
Ľ	$-\alpha$	
L	-11	
L	10 A	

#### Opening a file may fail due to invalid packet types!

It may not be possible to read some formats dependent on the packet types captured. Ethernet captures are usually supported for most file formats but it may not be possible to read other packet types (e.g. token ring packets) from all file formats.

## **5.3. Saving captured packets**

You can save captured packets simply by using the Save As... menu item from the File menu under Wireshark. You can choose which packets to save and which file format to be used.



#### Saving may reduce the available information!

Saving the captured packets will slightly reduce the amount of information, e.g. the number of dropped packets will be lost; see <u>Section A.1, "Capture Files"</u> for details.

## 5.3.1. The "Save Capture File As" dialog box

The "Save Capture File As" dialog box allows you to save the current capture to a file. <u>Table 5.2, "The system specific "Save Capture File As" dialog box</u>" shows some examples of this dialog box.



#### The dialog appearance depends on your system!

The appearance of this dialog depends on the system and GTK+ toolkit version used. However, the functionality remains basically the same on any particular system.

#### Table 5.2. The system specific ''Save Capture File As'' dialog box

Figure 5.4. "Save" on native Windows	Microsoft Windows
Wiresbark: Save file as         Image: Constraint of the second seco	<ul> <li>This is the common Windows file save dialog - plus some Wireshark extensions.</li> <li>Specific for this dialog:</li> <li>If available, the "Help" button will lead you to this section of this "User's Guide".</li> <li>If you don't provide a file extension to the filename - e.gpcap, Wireshark will append the standard file extension for that file format.</li> </ul>
File type: libpcap (tcpdump, Ethereal, etc.)	<ul> <li>Unix/Linux: GTK version &gt;= 2.4</li> <li>This is the common Gimp/GNOME file save dialog - plus some Wireshark extensions.</li> <li>Specific for this dialog:</li> <li>Clicking on the + at "Browse for other folders" will allow you to browse files and folders in your file system.</li> </ul>

igure 5.6. "Sav	n Unix/Linux: G	
Wireshark: Save Capture File As	This is the file s	
Create Dir Delete File Renar	ne File	versions - plus
(Constitution)	illisubversion 🔟	
Directories	Files acinclude.m4 acloceHags aipcap.ba aipcap.loader.c aipcap.loader.b aipcap.loader.b aipcap.loader.b aipcap.loader.b aiert_box.c alert_box.b alert_box.b alert_box.b alert_box.b alert_box.b alert_box.b alert_box.c	
Packet Range		
	Captured Displayed	
☆ All packets	120 120	
Selected packet only	1 1	
Marked packets only	0 0	
From first to last marked p.		
Specify a packet range:	0 0	
File type: Wireshark/tcpdump	Vlibpcap	
election: 💷 programmer to subversion		
	OK Cancel	

Unix/Linux: GTK version < 2.4

This is the file save dialog of former Gimp/GNOME versions - plus some Wireshark extensions.

With this dialog box, you can perform the following actions:

- 1. Type in the name of the file you wish to save the captured packets in, as a standard file name in your file system.
- 2. Select the directory to save the file into.
- 3. Select the range of the packets to be saved, see Section 5.9, "The Packet Range frame"
- 4. Specify the format of the saved capture file by clicking on the File type drop down box. You can choose from the types, described in <u>Section 5.3.2</u>, "Output File Formats".



#### The selection of capture formats may be reduced!

Some capture formats may not be available, depending on the packet types captured.



#### File formats can be converted!

- You can convert capture files from one format to another by reading in a capture file and writing it out using a different format.
- 5. Click on the Save/Ok button to accept your selected file and save to it. If Wireshark has a problem saving the captured packets to the file you specified, it will display an error dialog box. After clicking OK on that error dialog box, you can try again.
- 6. Click on the Cancel button to go back to Wireshark and not save the captured packets.

### 5.3.2. Output File Formats

Wireshark can save the packet data in its "native" file format (libpcap) and in the file formats of some other protocol analyzers, so other tools can read the capture data.



#### File formats have different time stamp accuracies!

Saving from the currently used file format to a different format may reduce the time stamp accuracy; see the <u>Section 7.4</u>, "<u>Time Stamps</u>" for details.

The following file formats can be saved by Wireshark (with the known file extensions):

- libpcap, tcpdump and various other tools using tcpdump's capture format (\*.pcap,\*.cap,\*.dmp)
- Accellent 5Views (\*.5vw)
- HP-UX's nettl (\*.TRC0,\*.TRC1)
- Microsoft Network Monitor NetMon (\*.cap)
- Network Associates Sniffer DOS (\*.cap,\*.enc,\*.trc,\*fdc,\*.syc)
- Network Associates Sniffer Windows (\*.cap)
- Network Instruments Observer version 9 (\*.bfr)
- Novell LANalyzer (\*.tr1)
- Sun snoop (\*.snoop,\*.cap)
- Visual Networks Visual UpTime traffic (\*.\*)
- ... new file formats are added from time to time

If the above tools will be more helpful than Wireshark is a different question ;-)



## Third party protocol analyzers may require specific file extensions!

Other protocol analyzers than Wireshark may require that the file has a certain file extension in order to read the files you generate with Wireshark, e.g.:

".cap" for Network Associates Sniffer - Windows

## 5.4. Merging capture files

Sometimes you need to merge several capture files into one. For example this can be useful, if you have captured simultaneously from multiple interfaces at once (e.g. using multiple instances of Wireshark).

Merging capture files can be done in three ways:

- Use the **menu item ''Merge''** from the "File" menu, to open the merge dialog, see <u>Section 5.4.1, "The</u> <u>"Merge with Capture File" dialog box"</u>. This menu item will be disabled, until you have loaded a capture file.
- Use **drag-and-drop** to drop multiple files on the main window. Wireshark will try to merge the packets in chronological order from the dropped files into a newly created temporary file. If you drop only a single file, it will simply replace a (maybe) existing one.

• Use the **mergecap** tool, which is a command line tool to merge capture files. This tool provides the most options to merge capture files, see Section D.8, "mergecap: Merging multiple capture files into one".

## 5.4.1. The "Merge with Capture File" dialog box

This dialog box let you select a file to be merged into the currently loaded file.



#### You will be prompted for an unsaved file first!


If your current data wasn't saved before, you will be asked to save it first, before this dialog box is shown.

Most controls of this dialog will work the same way as described in the "Open Capture File" dialog box, see Section 5.2.1, "The "Open Capture File" dialog box".

Specific controls of this merge dialog are:

Prepend packets to existing file	Prepend the packets from the selected file before the currently loaded packets.
Merge packets chronologically	Merge both the packets from the selected and currently loaded file in chronological order.
Append packets to existing file	Append the packets from the selected file after the currently loaded packets.





Desktop						
	Name					~
3 e-1		and the second second	ALCONO.			
Singaraport (1977)	0	ine pr				
D:\	@ tes	t.cap				
E1	(P)100	innere i				
рн:(	. 💿 tam	G. commence				
🕈 Add 📃 🖛 Remove		(100250)				~
	<				,	
E Biter:			test.cap			
		Format: Size:	libpcap (tcpdump 15317 bytes	Ethereal, etc.)		
Prepend packets to existing file		Sere: Packets:	15317 bytes 120			
Merge packets chronologically			2004-06-22 20:0	2:48		
Append packets to existing file						

- plus some Wireshark extensions.

Figure 5.9. "Merge" - old GTK version	Unix/Linux: GTK version < 2.4
Improve the fragment of Lagrance file       Improve the file         Dente the file file means file       Improve the file         Improve the file file file file file file file fil	This is the file open dialog of former Gimp/GNOME versions - plus some Wireshark extensions.

## 5.5. Import text file

Wireshark can read in an ASCII hex dump and write the data described into a temporary libpcap capture file. It can read hex dumps with multiple packets in them, and build a capture file of multiple packets. It is also capable of generating dummy Ethernet, IP and UDP, TCP, or SCTP headers, in order to build fully processable packet dumps from hexdumps of application-level data only.

Wireshark understands a hexdump of the form generated by **od** -**Ax** -**tx1** -**v**. In other words, each byte is individually displayed and surrounded with a space. Each line begins with an offset describing the position in the file. The offset is a hex number (can also be octal or decimal), of more than two hex digits. Here is a sample dump that can be imported:

000000	00	e0	1e	a7	05	6f	00	10	
800000	5a	a0	b9	12	08	00	46	00	
000010	03	68	00	00	00	00	0a	2e	
000018	ee	33	0f	19	08	7f	0f	19	
000020	03	80	94	04	00	00	10	01	
000028	16	a2	0a	00	03	50	00	0c	
000030	01	01	0f	19	03	80	11	01	

There is no limit on the width or number of bytes per line. Also the text dump at the end of the line is ignored. Bytes/hex numbers can be uppercase or lowercase. Any text before the offset is ignored, including email forwarding characters '>'. Any lines of text between the bytestring lines is ignored. The offsets are used to track the bytes, so offsets must be correct. Any line which has only bytes without a leading offset is ignored. An offset is recognized as being a hex number longer than two characters. Any text after the bytes is ignored (e.g. the character dump). Any hex numbers in this text are also ignored. An offset of zero is indicative of starting a new packet, so a single text file with a series of hexdumps can be converted into a packet capture with multiple packets. Packets may be preceded by a timestamp. These are interpreted according to the format given. If not the first packet is timestamped with the current time the import takes place. Multiple packets are read in with timestamps differing by one microsecond each. In general, short of these restrictions, Wireshark is pretty liberal about reading in hexdumps and has been tested with a variety of mangled outputs (including being forwarded through email multiple times, with limited line wrap etc.)

There are a couple of other special features to note. Any line where the first non-whitespace character is '#' will be ignored as a comment. Any line beginning with #TEXT2PCAP is a directive and options can be inserted after this command to be processed by Wireshark. Currently there are no directives implemented; in the future, these may be used to give more fine grained control on the dump and the way it should be processed e.g. timestamps, encapsulation type etc. Wireshark also allows the user to read in dumps of application-level data, by inserting dummy L2, L3 and L4 headers before each packet. The user can

elect to insert Ethernet headers, Ethernet and IP, or Ethernet, IP and UDP/TCP/SCTP headers before each packet. This allows Wireshark or any other full-packet decoder to handle these dumps.

## 5.5.1. The "File import" dialog box

This dialog box lets you select a file to be imported and set import parameters.

#### Figure 5.10. The "File Import" dialog

🛛 💿 Wireshark: Ir	nport from Text	_ <b>_</b> ×
Input		
Filename:		📙 <u>B</u> rowse
⊙ Hexadecir Offsets: ○ Octal ○ Decimal	nal	
Date/Time Format:		
_Import		
Encapsulation type: Eth	ernet	<b>\</b>
 _ ⊡ Dummy header —		
⊖ Ethernet	Ethertype (hex):	
O IP∨4	Protocol (dec):	
	Source port:	
○ ТСР	Destination port:	
⊖ SCTP	Tag:	
🔾 SCTP (DATA)	PPI:	
Max. frame length:		
<u>H</u> elp		<mark>∭</mark> <u>C</u> ancel <u></u> €

Specific controls of this import dialog are split in two sections:

- Input Determine which input file has to be imported and how it is to be interpreted.
- Import Determine how the data is to be imported.

The input parameters are as follows:

Filename / Browse	Enter the name of the text file to import. You can use <b>Browse</b> to browse for a file.
Offsets	Select the radix of the offsets given in the text file to import. This is usually hexadecimal, but decimal and octal are also supported.
Date/Time	Tick this checkbox if there are timestamps associated with the frames in the text file to import you would like to use. Otherwise the current time is used for timestamping the frames.
Format	This is the format specifier used to parse the timestamps in the text file to import. It uses a simple syntax to describe the format of the timestamps, using %H for hours, %M for minutes, %S for seconds, etc. The straightforward HH:MM:SS format is covered by %T. For a full definition of the syntax look for <b>strftime(3)</b> .

The import parameters are as follows:

Encapsulation type	Here you can select which type of frames you are importing. This all depends on from what type of medium the dump to import was taken. It lists all types that Wireshark understands, so as to pass the capture file contents to the right dissector.
Dummy header	When Ethernet encapsulation is selected you have to option to prepend dummy headers to the frames to import. These headers can provide artificial Ethernet, IP, UDP or TCP or SCTP headers and SCTP data chunks. When selecting a type of dummy header the applicable entries are enabled, others are grayed out and default values are used.
Max. frame length	You may not be interested in the full frames from the text file, just the first part. Here you can define how much data from the start of the frame you want to import. If you leave this open the maximum is set to 64000 bytes.

Once all input and import parameters are setup click **OK** to start the import.



#### You will be prompted for an unsaved file first!

If your current data wasn't saved before, you will be asked to save it first, before this dialog box is shown.

When completed there will be a new capture file loaded with the frames imported from the text file.

## 5.6. File Sets

When using the "Multiple Files" option while doing a capture (see: <u>Section 4.10, "Capture files and file</u> <u>modes</u>"), the capture data is spread over several capture files, called a file set.

As it can become tedious to work with a file set by hand, Wireshark provides some features to handle these file sets in a convenient way.

#### How does Wireshark detect the files of a file set?

A filename in a file set uses the format Prefix\_Number\_DateTimeSuffix which might look like this: "test\_00001\_20060420183910.pcap". All files of a file set share the same prefix (e.g. "test") and suffix (e.g. ".pcap") and a varying middle part.

To find the files of a file set, Wireshark scans the directory where the currently loaded file resides and checks for files matching the filename pattern (prefix and suffix) of the currently loaded file.

This simple mechanism usually works well, but has its drawbacks. If several file sets were captured with the same prefix and suffix, Wireshark will detect them as a single file set. If files were renamed or spread over several directories the mechanism will fail to find all files of a set.

The following features in the "File Set" submenu of the "File" menu are available to work with file sets in a convenient way:

- The List Files dialog box will list the files Wireshark has recognized as being part of the current file set.
- Next File closes the current and opens the next file in the file set.
- **Previous File** closes the current and opens the previous file in the file set.

## 5.6.1. The "List Files" dialog box

🛽 Wireshark: 17 Files in Set			
Filename	Created	Last Modified	Size
test1_00001_20050819181503.pcap	2005.08.19 18:15:03	2005.08.19 18:15:05	1067 Bytes
O test1_00002_20050819181505.pcap	2005.08.19 18:15:05	2005.08.19 18:15:05	1108 Bytes
O test1_00003_20050819181505.pcap	2005,08,19 18:15:05	2005.08.19 18:15:06	1093 Bytes
O test1_00004_20050819181506.pcap	2005.08.19 18:15:06	2005.08.19 18:15:07	1031 Bytes
O test1_00005_20050819181507.pcap	2005.08.19 18:15:07	2005.08.19 18:15:07	1070 Bytes
O test1_00006_20050819181507.pcap	2005.08.19 18:15:07	2005.08.19 18:15:08	1126 Bytes
O test1_00007_20050819181508.pcap	2005.08.19 18:15:08	2005.08.19 18:15:09	1074 Bytes
O test1_00008_20050819181509.pcap	2005.08.19 18:15:09	2005.08.19 18:15:10	1037 Bytes
O test1_00009_20050819181510.pcap	2005.08.19 18:15:10	2005.08.19 18:15:12	1060 Bytes
🔿 test1_00010_20050819181512.pcap	2005.08.19 18:15:12	2005.08.19 18:15:13	1079 Bytes
🔿 test1_00011_20050819181513.pcap	2005.08.19 18:15:13	2005.08.19 18:15:14	1029 Bytes
O test1_00012_20050819181514.pcap	2005.08.19 18:15:14	2005.08.19 18:15:16	1119 Bytes
O test1_00013_20050819181516.pcap	2005.08.19 18:15:16	2005.08.19 18:15:17	1029 Bytes
🔿 test1_00014_20050819181517.pcap	2005.08.19 18:15:17	2005.08.19 18:15:18	1085 Bytes
🔿 test1_00015_20050819181518.pcap	2005.08.19 18:15:18	2005.08.19 18:15:18	1083 Bytes
O test1_00016_20050819181518.pcap	2005.08.19 18:15:18	2005.08.19 18:15:18	1058 Bytes
O test1_00017_20050819181518.pcap	2005.08.19 18:15:18	2005.08.19 18:15:18	1386 Bytes
	n directory: D:/fileset		
			<b>X</b> ⊆lose

#### Figure 5.11. The "List Files" dialog box

Each line contains information about a file of the file set:

- **Filename** the name of the file. If you click on the filename (or the radio button left to it), the current file will be closed and the corresponding capture file will be opened.
- Created the creation time of the file
- Last Modified the last time the file was modified
- Size the size of the file

The last line will contain info about the currently used directory where all of the files in the file set can be found.

The content of this dialog box is updated each time a capture file is opened/closed.

The Close button will, well, close the dialog box.

## 5.7. Exporting data

Wireshark provides several ways and formats to export packet data. This section describes general ways to export data from Wireshark.



#### Note!

There are more specialized functions to export specific data, which will be described at the appropriate places.

XXX - add detailed descriptions of the output formats and some sample output, too.

## 5.7.1. The "Export as Plain Text File" dialog box

Export packet data into a plain ASCII text file, much like the format used to print packets.

📶 Wireshark: Exp	ort File				
Save in:	🔋 Packet An	alysis Data		•	← 🗈 💣 💷 マ
C.	Name	*			Date modified
Recent Places			No items mate	h your s	earch.
Desktop					
Libraries					
Computer					
Network	•				
	File <u>n</u> ame:	Slow NFS			-
	Save as type:	Plain text	(*.bd)		-
Packet Range —				Pa	cket Format
		Captured	O Displayed	- F	Packet summary line
<ul> <li>All packets</li> </ul>		11759	11759	E F	Packet details:
C Selected pa		1	1		As displayed
C Marked pac		0	0		Packet Bytes
C First to last n	narked	0	0		Each packet on a ne
C Range:	ored packets	<b>0</b>	0		
		0	0		

• **Export to file:** frame chooses the file to export the packet data to.

- The Packet Range frame is described in <u>Section 5.9, "The Packet Range frame"</u>.
- The Packet Details frame is described in <u>Section 5.10, "The Packet Format frame"</u>.

## 5.7.2. The "Export as PostScript File" dialog box

Export packet data into PostScript, much like the format used to print packets.



#### Tip!

You can easily convert PostScript files to PDF files using ghostscript. For example: export to a file named foo.ps and then call: **ps2pdf foo.ps** 

Wireshark: Exp	ort File				
Save in:	🐌 Packet Ana	alysis Data		•	← 🗈 💣 📰▼
œ.	Name	~		_	Date modified
Recent Places			No items mate	h your s	earch.
Desktop					
Libraries					
Computer					
Network	•		III		
	File <u>n</u> ame:	Slow NFS			•
	Save as type:	CSV (Com	ma Separated Va	lues sum	mary) (*.cs) 💌
Packet Range —				Pa	ecket Format
		Captured	C Displayed		Date modified search.
<ul> <li>All packets</li> </ul>		11759	11759		
C Selected pa	ecket	1	1		As displayed
C Marked pac		0	0	l I	Packet Bytes
C First to last	marked	0	0		
C Range:	nored packets	0	0		
	1	~			

Figure 5.13. The "Export as PostScript File" dialog box

• **Export to file:** frame chooses the file to export the packet data to.

- The Packet Range frame is described in <u>Section 5.9, "The Packet Range frame"</u>.
- The Packet Details frame is described in Section 5.10, "The Packet Format frame".

## 5.7.3. The "Export as CSV (Comma Separated Values) File" dialog box

XXX - add screenshot

Export packet summary into CSV, used e.g. by spreadsheet programs to im-/export data.

- **Export to file:** frame chooses the file to export the packet data to.
- The Packet Range frame is described in <u>Section 5.9, "The Packet Range frame"</u>.

## 5.7.4. The "Export as C Arrays (packet bytes) file" dialog box

XXX - add screenshot

Export packet bytes into C arrays so you can import the stream data into your own C program.

- Export to file: frame chooses the file to export the packet data to.
- The Packet Range frame is described in <u>Section 5.9</u>, "The Packet Range frame".

## 5.7.5. The "Export as PSML File" dialog box

Export packet data into PSML. This is an XML based format including only the packet summary. The PSML file specification is available at: <u>http://www.nbee.org/doku.php?id=netpdl:psml\_specification</u>.

Wireshark: Exp	ort File				
Save in:	🐌 Packet Anal	ysis Data		•	← 🗈 💣 📰 ▼
Ca.	Name	*			Date modified
Recent Places			No items mate	h your s:	earch.
Desktop					
Libraries					
Computer					
Network	•				
	File <u>n</u> ame:	Slow NFS			<b>-</b>
	Save as type:	PSML (XM	IL packet summa	ary) (*.psm	l) 🔽
Packet Range —				Pa	
	(	Captured	O Displayed		Packet summary line
All packets		11759	11759		Packet details:
C Selected pa		1	1		As displayed
C Marked pac		0	0	l I r	Packet Bytes
C First to last r	narked	0	0		Each packet on a ne
C Range:	nored nackets	0	0		
	iorona poloticito	0	0		

• **Export to file:** frame chooses the file to export the packet data to.

• The Packet Range frame is described in <u>Section 5.9, "The Packet Range frame"</u>.

There's no such thing as a packet details frame for PSML export, as the packet format is defined by the PSML specification.

## 5.7.6. The "Export as PDML File" dialog box

Export packet data into PDML. This is an XML based format including the packet details. The PDML file specification is available at: <u>http://www.nbee.org/doku.php?id=netpdl:pdml\_specification</u>.



The PDML specification is not officially released and Wireshark's implementation of it is still in an early beta state, so please expect changes in future Wireshark versions.

🗖 Wireshark: Exp	ort File				
Save <u>i</u> n:	📔 Packet Ana	lysis Data		-	← 🗈 📸 🖛
Æ	Name	~			Date modified
2			No items mate	h your s	earch.
Recent Places				·	
Desktop					
Libraries					
Computer					
Network	•			_	
	File <u>n</u> ame:	Slow NFS			•
	Save as type:	PDML (XI	ML packet detail)	(*.pdml)	-
Packet Range —				Pa	cket Format
		Captured	C Displayed		Packet summary line
<ul> <li>All packets</li> </ul>		11759	11759		Packet details:
C Selected pa	cket	1	1		As displayed
C Marked pac		0	0	l r	Packet Bytes
C First to last r	marked	0	0		
C Range:		0	0		Each packet on a ne
Remove Igr	iored packets	0	0		

• **Export to file:** frame chooses the file to export the packet data to.

• The Packet Range frame is described in <u>Section 5.9, "The Packet Range frame"</u>.

There's no such thing as a packet details frame for PDML export, as the packet format is defined by the PDML specification.

## 5.7.7. The "Export selected packet bytes" dialog box

Export the bytes selected in the "Packet Bytes" pane into a raw binary file.

🗖 Wireshark: Exp	ort Raw Data			
Save in:	🔒 Packet Analys	sis Data	•	⇔ 🗈 📸 📰 ▼
C	Name	*		Date modified
Recent Places			No items mate	h your search.
Hecenit Haces				
Desktop				
Libraries				
Computer				
Network				
	•			
	File <u>n</u> ame:	NFS bytes.dat		
	Save as type:	Raw data (*.bin, *.d	lat, ".raw)	
20 bytes of raw bina	ary data will be writte	en		

Figure 5.16. The "Export Selected Packet Bytes" dialog box

• Name: the filename to export the packet data to.

- The **Save in folder:** field lets you select the folder to save to (from some predefined folders).
- Browse for other folders provides a flexible way to choose a folder.

## 5.7.8. The "Export Objects" dialog box

This feature scans through HTTP streams in the currently open capture file or running capture and takes reassembled objects such as HTML documents, image files, executables and anything else that can be transferred over HTTP and lets you save them to disk. If you have a capture running, this list is automatically updated every few seconds with any new objects seen. The saved objects can then be opened with the proper viewer or executed in the case of executables (if it is for the same platform you are running Wireshark on) without any further work on your part. This feature is not available when using GTK2 versions below 2.4.

Figure 5.17. The "Export Objects" dialog box

Packet num	Hostname	Content Type	Bytes	Filename
1546	www.wireshark.org	text/html	8837	www.wireshark.org
1593	www.wireshark.org	text/css	4243	ws-1.css
1845	www.wireshark.org	application/x-javascript	1185	common.js
2488	www.wireshark.org	image/png	26763	front_screen.png
2592	www.wireshark.org	image/png	8783	wslogomedblue113.png
2978	www.wireshark.org	image/png	6525	wsiconinst80.png
2987	www.wireshark.org	image/png	159	cg_fade_bg.png
3071	www.wireshark.org	image/png	296	top_navbar_bg.png
3441	ads. wireshark. org	image/gif	43	adlog.php?bannerid=12&clientid=2&zoneid=0&source=front█=0&ca
3525	www.google-analytics.com	image/gif	35	&utmac=UA-605389-2&utmcc=_utma%3D87653150.554435287.117044
< <u>     M</u> elp				X Close Save As Save A

Columns:

- **Packet num:** The packet number in which this object was found. In some cases, there can be multiple objects in the same packet.
- Hostname: The hostname of the server that sent the object as a response to an HTTP request.
- **Content Type:** The HTTP content type of this object.
- **Bytes:** The size of this object in bytes.
- **Filename:** The final part of the URI (after the last slash). This is typically a filename, but may be a long complex looking string, which typically indicates that the file was received in response to a HTTP POST request.

Buttons:

- Help: Opens this section in the user's guide.
- **Close:** Closes this dialog.
- Save As: Saves the currently selected object as a filename you specify. The default filename to save as is taken from the filename column of the objects list.
- Save All: Saves all objects in the list using the filename from the filename column. You will be asked what directory / folder to save them in. If the filename is invalid for the operating system / file system you are running Wireshark on, then an error will appear and that object will not be saved (but all of the others will be).

## 5.8. Printing packets

To print packets, select the "Print..." menu item from the File menu. When you do this, Wireshark pops up the Print dialog box as shown in Figure 5.18, "The "Print" dialog box".

## 5.8.1. The "Print" dialog box

Figure 5.18. The "Print" dialog box

🗖 Wireshark: Print			
Printer Plain text			
O PostScript			
Output to file: d:\ethe	real.out		Browse
Packet Range			Packet Format
	⊆aptured	Displayed	Packet summary line
<ul> <li>All packets</li> </ul>	11	11	Packet details:
Selected packet only	1	1	🚫 All coļlapsed
<ul> <li>Marked packets only</li> </ul>			<ul> <li>As displayed</li> </ul>
O From first to last marked packet		0	◯ All expanded
Specify a packet range:	0		Packet bytes
			Each packet on a new page
			Print 🗶 Cancel

The following fields are available in the Print dialog box:

Printer

This field contains a pair of mutually exclusive radio buttons:

- Plain Text specifies that the packet print should be in plain text.
- **PostScript** specifies that the packet print process should use PostScript to generate a better print output on PostScript aware printers.
- **Output to file:** specifies that printing be done to a file, using the filename entered in the field or selected with the browse button.

This field is where you enter the **file** to print to if you have selected Print to a file, or you can click the button to browse the filesystem. It is greyed out if Print to a file is not selected.

• Print command specifies that a command be used for printing.



#### Note!

These **Print command** fields are not available on windows platforms.

This field specifies the command to use for printing. It is typically **lpr**. You would change it to specify a particular queue if you need to print to a queue other than the default. An example might be:

lpr -Pmypostscript

This field is greyed out if **Output to file:** is checked above.

Packet Range Select the packets to be printed, see <u>Section 5.9</u>, "The Packet Range frame"

**Packet Format** Select the output format of the packets to be printed. You can choose, how each packet is printed, see Figure 5.20, "The "Packet Format" frame"

## 5.9. The Packet Range frame

The packet range frame is a part of various output related dialog boxes. It provides options to select which packets should be processed by the output function.

#### Figure 5.19. The "Packet Range" frame

<u>C</u> aptured	<u>D</u> isplayed
120	120
1	1
0	0
	120 1 0


If the **Captured** button is set (default), all packets from the selected rule will be processed. If the **Displayed** button is set, only the currently displayed packets are taken into account to the selected rule.

- All packets will process all packets.
- Selected packet only process only the selected packet.
- Marked packets only process only the marked packets.
- From first to last marked packet process the packets from the first to the last marked one.
- **Specify a packet range** process a user specified range of packets, e.g. specifying **5,10-15,20-** will process the packet number five, the packets from packet number ten to fifteen (inclusive) and every packet from number twenty to the end of the capture.

## 5.10. The Packet Format frame

The packet format frame is a part of various output related dialog boxes. It provides options to select which parts of a packet should be used for the output function.

#### Figure 5.20. The "Packet Format" frame



- Packet summary line enable the output of the summary line, just as in the "Packet List" pane.
- **Packet details** enable the output of the packet details tree.
  - All collapsed the info from the "Packet Details" pane in "all collapsed" state.
  - As displayed the info from the "Packet Details" pane in the current state.
  - All expanded the info from the "Packet Details" pane in "all expanded" state.
- Packet bytes enable the output of the packet bytes, just as in the "Packet Bytes" pane.
- Each packet on a new page put each packet on a separate page (e.g. when saving/printing to a text file, this will put a form feed character between the packets).

# Chapter 6. Working with captured packets

## 6.1. Viewing packets you have captured

Once you have captured some packets, or you have opened a previously saved capture file, you can view the packets that are displayed in the packet list pane by simply clicking on a packet in the packet list pane, which will bring up the selected packet in the tree view and byte view panes.

You can then expand any part of the tree view by clicking on the **plus** sign (the symbol itself may vary) to the left of that part of the payload, and you can select individual fields by clicking on them in the tree view pane. An example with a TCP packet selected is shown in Figure 6.1, "Wireshark with a TCP packet selected for viewing". It also has the Acknowledgment number in the TCP header selected, which shows up in the byte view as the selected bytes.

🛯 test. pcap -	Wireshark					
<u>File Edit View</u>	Go ⊆apture	e <u>A</u> nalyze <u>S</u> ta	itistics <u>H</u> elp			
		6	× % 📇 🖸	(+ + + + + + + + + + + + + + + + + + +	<b>₹ ₽</b>	<b>. . .</b>
Filter:				<ul> <li></li></ul>	pression 🏷⊆lear	<b>У</b> <u>А</u> рріу
No Time	Sour		Destination		Info	
30 1.25		.168.0.1	192.100.0.2	TCP		j sey-i Ack-isv # tel http > 3197 [
31 1.26		.168.0.1	192.168.0.2	TCP		, ACK] Seg=1 Ack=
32 1.26	5819 192	.168.0.2	192.168.0.1	TCP	5000 > 1025 [PSH	, ACK] Seq=1 Ack=
33 1.267		.168.0.1	192.168.0.2	TCP		] Seq=510 Ack=20
34 1.274		.168.0.1	192.168.0.2	TCP TCP		, ACK] Seq=1 Ack=
35 1.274 36 1.274		.168.0.2	192.168.0.1 192.168.0.2	ТСР		, ACK] Seq=190 Ac , ACK] Seq=20 Ack
37 1.27		.168.0.2	192.168.0.1	ТСР		7 Seg=191 Ack=21
38 1.270		.168.0.1	192.168.0.2	TCP		, ACK] Seg=26645
39 1.28:	1649 192	.168.0.1	192.168.0.2	TCP	[TCP Window Upda	te] 1025 > 5000 [
40 1.28		.168.0.1	192.168.0.2	TCP	1025 > 5000 [FIN	, ACK] Seq=510 Ac
						5
			tes captured)			
	,		a (00:09:5b:2d:75:9	• ·		):cd:02)
	,		.1 (192.168.0.1), D:		• •	
		· · · ·	c Port: http (80), [	)st Port: 3197 (3	3197), Seq: 20, /	Ack: 190, Len: O
	ort: http (					
	ion port: 3	• •				
	number: 20	•	e sequence number)			
	dgement num		(relative ack numbe	r)		
Header 1	ength: 20 b	ytes				
						>
000 00 0b 5	d 20 cd 02	00 09 56 24	75 9a 08 00 45 00	1 [-u	F	
010 00 28 0			c0 a8 00 01 c0 a8	.(@		
	0 50 Oc 7d		3c 38 dd 9b 50 11	P.} h.<8.	.P.	
030 Oc 00 9	3 ca 00 00	00 00 00 00	00 00	•••••		

#### Figure 6.1. Wireshark with a TCP packet selected for viewing

You can also select and view packets the same way, while Wireshark is capturing, if you selected "Update list of packets in real time" in the Wireshark Capture Preferences dialog box.

In addition, you can view individual packets in a separate window as shown in Figure 6.2, "Viewing a packet in a separate window". Do this by selecting the packet in which you are interested in the packet list pane, and then select "Show Packet in New Windows" from the Display menu. This allows you to easily compare two or even more packets.

Figure 6.2. Viewing a packet in a separate window

<b>1</b> 3	36 1.274	987	192.1	68.0	0.1	192.	.168	3.0.	2 T(	:P h	ittp	> 3	8197	[FIN	I, AC	K] S	eq=2	0 Ac	k=1	90 W	in=3	807	2 Lei	n=0			×
⊞ F	Frame 36	(60	byte		ı wi	re,	60	byt	es (	apt	cune	≘d)															~
ΞE	Ethernet	II,	Snc:	Net	gea	r_2a	1:75	:9a	(00	:09	9:5Ł	:20	1:75	:9a)	, Ds	t: 1	92.1	68.0	.2 (	(00 : 0	)b:5	d:2	0:cd	:02)			
÷Ι	Internet	Pro	toco1	, Sr	'C:	192.	168	.0.	1 (:	192.	168	3.0.	1),	Dst	: 19	2.16	8.0.	2 (1	92.1	.68.0	).2)						-
	Transmis	sion	Cont	rol	Pro	tocc	51,	Snc	Por	·t:	htt	tp (	(80)	, Ds	t Po	rt:	3197	(31	97),	See	q: 20	o, .	Ack:	190,	Len:	0	_
	Source		+. 64	++~ 1	1001																						$\mathbf{x}$
<																										>	
0000 0010 0020 0030	00 28	00	20 cc 84 00 50 0c ca 00	: 7d		00		14	3c :	38 c			45 0 c0 a 50 1			.@. }		1E (8F									

## 6.2. Pop-up menus

You can bring up a pop-up menu over either the "Packet List", its column header, or "Packet Details" pane by clicking your right mouse button at the corresponding pane.

## 6.2.1. Pop-up menu of the "Packet List" column header

🗖 te	est.c	ap -	Wir	esha	urk															Z
File	Edit	⊻ie	ew g	<u>5</u> 0	<u>⊂</u> aptu	re į	<u>A</u> naly.	ze g	tatistic	s 1	elept	ion <u>y</u>	Took	s	Help					
e,	<u>i</u>	0	<u>اھ</u>	1			X	2	8	C	~ <		)		<b>₹</b> 1	<u>ا</u> ا			Ð	Q Q 🖻   🎬 🖻 🕵 %   💢
Filter	:														•	E×	pressio	on (	lea	r Apply
No.	2 3 4 5 6 7 8 9 10 11 12	0.3 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0	0000 2991 2992 0256 0443 0507 0550 0820 0550 0820 1119 2261	39 14 59 66 52 84 53 38 45 56 82	19 19 19 19 19 19 19 19 19 19	jit: 2.1 2.1 2.1 2.1 2.1 2.1 2.1 2.1 2.1 2.1	58.( 58.( 58.( 58.( 58.( 58.( 58.( 58.(	0.1 0.2 0.2 0.2 0.2 0.2 0.2 0.2 0.1 0.2 0.2 0.2 0.2	d:02		Bro 192 224 192 239 192 192 192 192 192	.168 .0.0 .168 .255 .168 .168 .168 .168		Sc No Ali Ali Co Re Di	ort Asce ort Desc o Sortin ign Left ign Cen ign Righ olumn P esize Co ename ( splayed de Colu	:endir g : (def: iter nt refer olumn Colum	ng ault) ences n Title.			<pre>uitous ARP for 192.168.0.2 (f equery NBSTAT *&lt;00&gt;&lt;00&gt;&lt;00&gt;&lt;() ination Unreachable (Port un lembership Report / Join group idard query SRV _]daptcp.nbp (ARCH * HTTP/1.1 idard query SOA nb10061d.ww004 //1.1 200 oK stration NB NB10061D&lt;00&gt; idard query A proxyconf.ww004. &lt;2 &gt; http [SYN] Seq=0 win=6424 &gt;&gt; ncu-2 [SYN, ACK] Seq=0 Act &gt;&gt; ncu-2 [SYN, Act &gt;&gt; ncu-2 [SY</pre>
<pre>     Ethernet II, Src: Fujitsu_20:cd:02 (00:0b: Remove Column )ear_2d:75:9a (00:09:5b:2d:75     Internet Protocol, Src: 192.168.0.2 (192.100000000000000000000000000000000000</pre>																				
0000 0010 0020 0030			01 10	3 4; c 7;	d 75 8 40 c 00 0 00	00	80 3 c	06 36	61	2c f8	C0 00	18 0 00 0		2	45 00 c0 a8 70 02	3	.0.H	@	ā,	E. ,p.
F	ile: "C	:/tes	t.cap'	14 K	B 00:0	0:02				Pack	ets:	120 Di	isplaye	ed:	120 Ma	arked:	0 Load	d time: (	0:00	D Profile: Default

Figure 6.3. Pop-up menu of the "Packet List" column header

The following table gives an overview of which functions are available in this header, where to find the corresponding function in the main menu, and a short description of each item.

Item	Identical to main menu's item:	Description
Sort Ascending		Sort the packet list in ascending order based on this column.
Sort Descending		Sort the packet list in descending order based on this column.
No Sort		Remove sorting order based on this column.
 Align Left		Set left alignment of the values in this column.
Align Center		Set center alignment of the values in this column.
Align Right		Set right alignment of the values in this column.
Column Preferences		Open the Preferences dialog box on the column tab.
Resize Column		Resize the column to fit the values.
Rename Column Title		Allows you to change the title of the column header.
Displayed Column	View	This menu items folds out with a list of all configured columns. These columns can now be shown or hidden in the packet list.
Hide Column		Allows you to hide the column from the packet list.
Remove Column		Allows you to remove the column from the packet list.

### Table 6.1. The menu items of the "Packet List" column header pop-up menu

# 6.2.2. Pop-up menu of the "Packet List" pane

🔼 te	est.c	ap -	Wir	esha	ırk																				-		×
File	<u>E</u> dit	⊻ie	w i	<u>G</u> o	⊆aptu	ıre	<u>A</u> nal	yze	Stat	istics	Tele	phor	Υ <u>ν</u>	<u>T</u> ools	Hel	р											
e)	Ë.	0	<b>Q</b> í			3 6	3	6	3		Q	\$	\$		Ŧ	垫		0		0	**	×.	Y	•	*	1	Ĵ
Filter	•															•	Expression	. cl	ear Ap	ply							
о.		Time				urce					Des	tinat	ion.				Protocol	Info									1
			0000					20:		02		oac					ARP		tuit								
	2	0.2	2991	.39				0.1			19	2.1	.68	.0.2	!		NBNS	Nan	ie que	ery	NBS	TAT	*<00	)><0	0><0	00><	33
			2992					0.2			- 19	2.1	.68	.0.1			ICMP		tina								
			256					0.2				4.0					IGMP		Membe								
			)443					0.2						.0.1			DNS		Indari					lap.	_tq	p.nb	)Ç
			)486			_		0.2							i.25	0	SSDP		EARCH								
			0507					0.2						.0.1			DNS		Indari				nb1	.006	1d.\	ww00	12
			)550					0.1						.0.2			SSDP		P/1.1								
			820					0.2						.0.2			NBNS		jistra								
			.119					0.2					.68	.0.1	-		DNS		Indari								
			2261					0.2			19		CO.	n 4 Iark D	ackat	(toggle			1-2 >								
	12	1.2	2272	82	19	92.1	168.	0.1			19	2				et (togi	•		p > 1	ncu-	-2 [	SYN,	ACK	(] S	eq=	0 AC	ł
														-												>	•
θE	rame	- 11	: 6	i2 h	vte	s n	n w	ire	(40	96 b	its)		95	et In	ne Ket	erence	e (toggle)		ts)								
										:d:0			N	lanua	llv Res	solve A	ddress		gear_	2d:	75:	9a (	00:0	9:5	h:2r	1:75	in
										8.0					· _				že.	~ ~ ~		~ ~ `	• `	_			1
										Sn					as Filte			•	-	ected				Le	n: (	0	il.
								196)					Ρ	repar	e a Fill	ter		- 1	<u>N</u> o	t Sele	cted					-	
								p (8					C	onve	rsatior	n Filter		- •		<u>a</u> nd S	Select	ed					
					x: !				-				C	oloriz	e Con	versati	ion	- <b>F</b>		<u>o</u> r Se	lecter	ł					
					ber			(re	lat	ive	sec	ıu	S	CTP				- F		a <u>n</u> d r	not Se	lected					
					h: 2							'	F	ollow	TCP S	tream				o <u>r</u> no	t Sele	cted					L
÷	Fla	iqs :	0x	:02	(SYI	CN	1						F	ollow	UDP S	itream		1									
					642								F	ollow	SSL St	ream											•
<												-	-					-								>	Ĩ
000		0 0	0 5	b 20	1 75	. D.	- 00	) Ob	c	d 20	Led			ору				_	1	F							Ť
0000								00 (		u 20 1 20			28 D	ecord	e As				a	. E.							
0020	ōō	ōō	īō	c 70	- 00	5	0 30	36	9	5 f8	00	4							-,	.p.							
0030	) f	a f	0 2	7 e(	0 00	0 0	0 02	2 04	0	5 b4	01	46		rint						•							
													S	how I	Packet	in Nev	v Window										
	ile: "C	:/tes	t.cap'	' 14 K	B 00:	00:0	2			Pé	ackets	: 120	) Dis	olave	d: 120	I Marke	ed: O Load tir	ne: 0:	00	Profile	e: De	fault					

Figure 6.4. Pop-up menu of the "Packet List" pane

The following table gives an overview of which functions are available in this pane, where to find the corresponding function in the main menu, and a short description of each item.

Item		dentical to main nenu's item:	Description
Mark Pac (toggle)	c <b>ket</b> E	Edit	Mark/unmark a packet.
Ignore Pac (toggle)	cket E	Edit	Ignore or inspect this packet while dissecting the capture file.
Set Ti Reference (toggle)	ime E	Edit	Set/reset a time reference.
Manually Resolve Addre	ess		Allows you to enter a name to resolve for the selected address.
Apply as Filter	r A	Analyze	Prepare and apply a display filter based on the currently selected item.
Prepare a Filto	er A	Analyze	Prepare a display filter based on the currently selected item.

Item	Identical to main menu's item:	Description
Conversation Filter	-	This menu item applies a display filter with the address information from the selected packet. E.g. the IP menu entry will set a filter to show the traffic between the two IP addresses of the current packet. XXX - add a new section describing this better.
Colorize Conversation	-	This menu item uses a display filter with the address information from the selected packet to build a new colorizing rule.
SCTP	-	Allows you to analyze and prepare a filter for this SCTP association.
Follow TCP Stream	Analyze	Allows you to view all the data on a TCP stream between a pair of nodes.
Follow UDP Stream	Analyze	Allows you to view all the data on a UDP datagram stream between a pair of nodes.
Stream	Analyze	Same as "Follow TCP Stream" but for SSL. XXX - add a new section describing this better.
 Copy/ Summary (Text)	-	Copy the summary fields as displayed to the clipboard, as tab- separated text.
Copy/ Summary (CSV)	-	Copy the summary fields as displayed to the clipboard, as comma-separated text.
Copy/ As Filter		Prepare a display filter based on the currently selected item and copy that filter to the clipboard.
Copy/ Bytes (Offset Hex Text)	-	Copy the packet bytes to the clipboard in hexdump-like format.
Copy/ Bytes (Offset Hex)	-	Copy the packet bytes to the clipboard in hexdump-like format, but without the text portion.
Copy/ Bytes (Printable Text Only)	-	Copy the packet bytes to the clipboard as ASCII text, excluding non-printable characters.
Copy/ Bytes (Hex Stream)	-	Copy the packet bytes to the clipboard as an unpunctuated list of hex digits.
Copy/ Bytes (Binary Stream)	-	Copy the packet bytes to the clipboard as raw binary. The data is stored in the clipboard as MIME-type "application/octet-stream".
Decode As	Analyze	Change or apply a new relation between two dissectors.
Print	File	Print packets.
Show Packet in New Window	View	Display the selected packet in a new window.

### 6.2.3. Pop-up menu of the "Packet Details" pane

📶 test.cap - Wireshark			
<u>File Edit View Go Capture Analyze Statis</u>	tics Telephony	<u>T</u> ools <u>H</u> elp	
24 24 24 24 24 1 1 1 2 2 2 2 2	l 🔍 🖕	🔹 🎝 🕇 🕹   🗐 📑   🤆	2, Q, Q, 🖻   📓 🖻 畅 %   💢
Filter:		▼ Expression Cle	aavApply
lo, Time Source	Destina	Expand Subtrees	
1 0.000000 Fuiitsu_20:cd:0		Expand All	tous ARP for 192.168.0.2 (
2 0.299139 192.168.0.1	192.1	Collapse All	
3 0.299214 192.168.0.2	192.1	Apply as Column	ation unreachable (Port un
4 1.025659 192.168.0.2	224.0		- in grout
5 1.044366 192.168.0.2	192.1	Apply as Filter	Selected
6 1.048652 192.168.0.2	239.2	Prepare a Filter	Not Selected
7 1.050784 192.168.0.2	192.1	Colorize with Filter	and Selected d. ww002
81.055053 192.168.0.1	192.1	Follow TCP Stream	or Selected
9 1.082038 192.168.0.2	192.1	Follow UDP Stream	and not Selected 0>
10 1.111945 192.168.0.2	192.1	Follow SSL Stream	or not Selected .ww004.
11 1.226156 192.168.0.2	192.1	Cody	> http [SYN] Seq=0 Win=6424
12 1.227282 192.168.0.1	192.1	Export Selected Packet Bytes	ncu-2 [SYN, ACK] Seq=0 Acl
	н -	Export Scietted Fucket Bytes	- >
∋ Frame 11: 62 bytes on wire (49	a bits). (	🥑 🛛 Wiki Protocol Page	
∃ Ethernet II, Src: Fujitsu_20:c		Filter Field Reference	r_2d:75:9a (00:09:5b:2d:75
€ Internet Protocol, Src: 192.16		Protocol Help	(192.168.0.1)
Transmission Control Protocol,		Protocol Preferences	tp (80), Seq: 0, Len: 0
Source port: ncu-2 (3196)			-
Destination port: http (80)	1	🕞 Decode As	
[Stream index: 5]		Disable Protocol	
	ive seque	Resolve Name	
Header length: 28 bytes		Go to Corresponding Packet	
⊞ Flags: 0x02 (SYN)		go to corresponding racible	
Window size: 64240			
		Ш	>
		08 00 45 00[-u	
		00 02 c0 a8 .0.H@	
	1 78 00 00 1 b4 01 01	00 00 70 02 .P<6 04 02	·····b·
	. DA OI OI		
There from filmer a charter	D		on Disfler Differil
Flags (tcp.flags), 2 bytes	Packets: 120	Displayed: 120 Marked: 0 Load time: 0:	UU Pronie: Derault

Figure 6.5. Pop-up menu of the "Packet Details" pane

The following table gives an overview of which functions are available in this pane, where to find the corresponding function in the main menu, and a short description of each item.

Item	Identical to main menu's item:	Description
Expand Subtrees	View	Expand the currently selected subtree.
Expand All	View	Expand all subtrees in all packets in the capture.
Collapse All	View	Wireshark keeps a list of all the protocol subtrees that are expanded, and uses it to ensure that the correct subtrees are expanded when you display a packet. This menu item collapses the tree view of all packets in the capture list.
Apply as Column		Use the selected protocol item to create a new column in the packet list.
Apply as Filter	Analyze	Prepare and apply a display filter based on the currently selected item.
Prepare a Filter	Analyze	Prepare a display filter based on the currently selected item.

Item	Identical to main menu's item:	Description
Colorize with Filter	-	This menu item uses a display filter with the information from the selected protocol item to build a new colorizing rule.
Follow TCP Stream	Analyze	Allows you to view all the data on a TCP stream between a pair of nodes.
tream		Allows you to view all the data on a UDP datagram stream between a pair of nodes.
Follow SSL Stream	Analyze	Same as "Follow TCP Stream" but for SSL. XXX - add a new section describing this better.
Copy/ Description	Edit	Copy the displayed text of the selected field to the system clipboard.
Copy/ Fieldname	Edit	Copy the name of the selected field to the system clipboard.
Copy/ Value	Edit	Copy the value of the selected field to the system clipboard.
Copy/ As Filter	Edit	Prepare a display filter based on the currently selected item and copy it to the clipboard.
Copy/ Bytes (Offset Hex Text)	-	Copy the packet bytes to the clipboard in hexdump-like format; similar to the Packet List Pane command, but copies only the bytes relevant to the selected part of the tree (the bytes selected in the Packet Bytes Pane).
Copy/ Bytes (Offset Hex)	-	Copy the packet bytes to the clipboard in hexdump-like format, but without the text portion; similar to the Packet List Pane command, but copies only the bytes relevant to the selected part of the tree (the bytes selected in the Packet Bytes Pane).
Copy/ Bytes (Printable Text Only)		Copy the packet bytes to the clipboard as ASCII text, excluding non-printable characters; similar to the Packet List Pane command, but copies only the bytes relevant to the selected part of the tree (the bytes selected in the Packet Bytes Pane).
Copy/ Bytes (Hex Stream)	-	Copy the packet bytes to the clipboard as an unpunctuated list of hex digits; similar to the Packet List Pane command, but copies only the bytes relevant to the selected part of the tree (the bytes selected in the Packet Bytes Pane).
Copy/ Bytes (Binary Stream)	-	Copy the packet bytes to the clipboard as raw binary; similar to the Packet List Pane command, but copies only the bytes relevant to the selected part of the tree (the bytes selected in the Packet Bytes Pane). The data is stored in the clipboard as MIME-type "application/octet-stream".
Export Selected Packet Bytes	File	This menu item is the same as the File menu item of the same name. It allows you to export raw packet bytes to a binary file.
 Wiki Protocol Page	-	Show the wiki page corresponding to the currently selected protocol in your web browser.
Filter Field Reference	-	Show the filter field reference web page corresponding to the currently selected protocol in your web browser.

Item	Identical to main menu's item:	Description
Protocol Preferences	-	The menu item takes you to the properties dialog and selects the page corresponding to the protocol if there are properties associated with the highlighted field. More information on preferences can be found in Figure 10.8, "The preferences dialog box".
Decode As	Analyze	Change or apply a new relation between two dissectors.
Disable Protocol		Allows you to temporarily disable a protocol dissector, which may be blocking the legitimate dissector.
Resolve Name	View	Causes a name resolution to be performed for the selected packet, but NOT every packet in the capture.
Go to Corresponding Packet	Go	If the selected field has a corresponding packet, go to it. Corresponding packets will usually be a request/response packet pair or such.

# 6.3. Filtering packets while viewing

Wireshark has two filtering languages: One used when capturing packets, and one used when displaying packets. In this section we explore that second type of filter: Display filters. The first one has already been dealt with in <u>Section 4.12</u>, "Filtering while capturing".

Display filters allow you to concentrate on the packets you are interested in while hiding the currently uninteresting ones. They allow you to select packets by:

- Protocol
- The presence of a field
- The values of fields
- A comparison between fields
- ... and a lot more!

To select packets based on protocol type, simply type the protocol in which you are interested in the **Filter:** field in the filter toolbar of the Wireshark window and press enter to initiate the filter. <u>Figure 6.6</u>, "Filtering on the <u>TCP protocol</u>" shows an example of what happens when you type **tcp** in the filter field.



#### Note!

All protocol and field names are entered in lowercase. Also, don't forget to press enter after entering the filter expression.

Ede       Edit       Yew       Go       Cal       C		
ilter:       tcp       Expression	Edit Yiew Go Capture Analyze Statistics Help	
<pre>b Time Source Destination Protocol Info 11 1.226156 192.168.0.2 192.168.0.1 TCP 3196 &gt; http [SYN] Seq=0 Len=0 MSS 12 1.227282 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [SYN, ACK] Seq=0 Ack= 13 1.227351 192.168.0.2 192.168.0.1 TCP 3196 &gt; http [ACK] Seq=1 Ack=1 Win 14 1.227451 192.168.0.2 192.168.0.1 TCP SUBSCRIBE /uppn/Service/Layer3For 15 1.229309 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [ACK] Seq=1 Ack=256 W 16 1.222421 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [ACK] Seq=1 Ack=256 W 16 1.222421 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [ACK] Seq=1 Ack=256 W 16 1.229421 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [ACK] Seq=0 Ack= 19 1.250171 192.168.0.1 192.168.0.1 TCP SOOO SND Seq=0 Len=0 MSS 18 1.248391 192.168.0.1 192.168.0.1 TCP SOOO SND Seq=0 Len=0 MSS 18 1.248391 192.168.0.1 192.168.0.1 TCP SOOO SND Seq=0 Ack= 19 1.25042 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [FIN, ACK] Seq=256 Ac 21 1.250842 192.168.0.1 192.168.0.1 TCP 3196 &gt; http [FIN, ACK] Seq=256 Ac 21 1.250842 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [FIN, ACK] Seq=256 Ac 21 1.250842 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [FIN, ACK] Seq=26611 25 1.25322 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [FIN, ACK] Seq=26611 25 1.25322 192.168.0.1 192.168.0.2 TCP http &gt; 3196 [FIN, ACK] Seq=26611 25 1.25322 192.168.0.1 192.168.0.2 TCP http &gt; 3197 [FNN, ACK] Seq=0 Ack= 27 1.254532 192.168.0.2 192.168.0.1 TCP 3197 &gt; http [SNN] Seq=0 Len=0 MSS 26 1.254532 192.168.0.2 192.168.0.1 TCP 3197 &gt; http [SNN] Seq=0 Len=0 MSS 26 1.254532 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) 3 Internet Protocol, Src: 192.168.0.2 (192.168.0.2 TCP http &gt; 3197 [SNN] ACK] Seq=1 Ack=1 Win 27 1.254532 192.168.0.2 (192.168.0.2 TCP http &gt; 3197 [SNN] ACK] Seq=0 Ack= 27 1.254532 192.168.0.2 (192.168.0.2 TCP http &gt; 3197 [SNN] ACK] Seq=0 Ack= 27 1.254532 192.168.0.2 (192.168.0.2 TCP http &gt; 3197 [SNN] ACK] Seq=0 Ack= 200 00 00 00 95 b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 200 00 01 00 05 00 5d 20 cd 02 08 00 45 00[-u]E. 200 00 01 00 70 00</pre>		
11       1.226156       192.168.0.2       192.168.0.2       TCP       3196 > http [SYN] Seq=0 Len=0 MSS         12       1.227282       192.168.0.1       192.168.0.2       TCP       http > 3196 [SYN, ACK] Seq=0 Ack=         13       1.227325       192.168.0.2       192.168.0.1       TCP       3196 s http [ACK] Seq=1 Ack=1 Win         14       1.227325       192.168.0.2       192.168.0.1       TCP       http > 3196 [ACK] Seq=1 Ack=256 W         15       1.229309       192.168.0.1       192.168.0.2       TCP       http > 3196 [ACK] Seq=1 Ack=256 W         16       1.22421       192.168.0.1       192.168.0.2       TCP       http > 3196 [ACK] Seq=1 Ack=256 W         17       1.438351       192.168.0.1       192.168.0.2       TCP       http > 3196 [ACK] Seq=1 Ack=256 W         18       1.248391       192.168.0.2       TCP       http > 3196 [FN, ACK] Seq=0 Len=0 MSS         19       1.250171       192.168.0.2       TCP       3196 > http [FN, ACK] Seq=0 Len=0 MSS         20       1.250840       192.168.0.1       TCP       1025 S S000 [SVN] Seq=0 Len=0 MSS         21       1.250840       192.168.0.1       TCP       3196 > http [FN, ACK] Seq=256 Ack=19         21       1.250840       192.168.0.1       TCP       3196 [FIN,	tcp 🔻 Expression Clear	Apply
12 1.22782       192.168.0.1       192.168.0.2       TCP       http > 3196       SCN, ACK       Seq=1 Ack=1 Win         13 1.227325       192.168.0.2       192.168.0.1       TCP       3196 > http [ACK] Seq=1 Ack=1 Win         14 1.227451       192.168.0.2       192.168.0.2       TCP       HTTP SUBSCRIBE /upnp/service/Layer3For         15 1.229309       192.168.0.1       192.168.0.2       TCP       http > 3196 [ACK] Seq=1 Ack=256 W         17 1.248355       192.168.0.1       192.168.0.2       TCP       ICP Windw Update] http > 3196         17 1.248351       192.168.0.2       192.168.0.1       TCP S000 > 1025 [SVN, ACK] Seq=0 Ack=19         19 1.250171       192.168.0.2       192.168.0.2       TCP S000 > 1025 [SVN, ACK] Seq=0 Ack=20         19 1.250271       192.168.0.2       192.168.0.1       TCP S000 > 1025 [SVN, ACK] Seq=2 Ack         20 1.250285       192.168.0.1       192.168.0.2       TCP Http > 3196 [FIN, ACK] Seq=256 Ac         21 1.250810       192.168.0.1       192.168.0.2       TCP Http > 3196 [FIN, ACK] Seq=27 Ack=135         23 1.251868       192.168.0.1       192.168.0.2       TCP http > 3196 [FIN, ACK] Seq=1Ack=1 Win         24 1.252826       192.168.0.1       192.168.0.2       TCP http > 3197 [SVN] Seq=0 Len=0 MSS         26 1.254502       192.168.0.2       192.1	Time Source Destination Protocol Info	
13       1.227325       192.168.0.2       192.168.0.1       TCP       3196 > http [ACK] Seg=1 Ack=1 Win         14       1.227451       192.168.0.1       192.168.0.1       HTTP       SUBSCRIBE / µmp/service/Layer3For         15       1.229309       192.168.0.1       192.168.0.2       TCP       http > 3196 [ACK] Seg=1 Ack=256 W         16       1.229309       192.168.0.1       192.168.0.2       TCP       Interval       Seg=1 Ack=256 W         16       1.229309       192.168.0.1       192.168.0.2       TCP       Interval       Seg=1 Ack=256 W         17       1.248355       192.168.0.1       192.168.0.2       TCP       Interval       Seg=0 Lene/0 MSS         18       1.248351       192.168.0.1       192.168.0.2       HTP       HTP/1.0 200 0K       Seg=0 Ack=1         19       1.50.21       192.168.0.1       192.168.0.2       HTP       HTP/1.0 200 0K       Seg=256 Ack=1         20       1.250842       192.168.0.1       192.168.0.2       TCP       http > 3196 [FIN, ACK] Seg=257 Ack=115         21       1.250842       192.168.0.1       192.168.0.2       TCP       http > 3196 [FIN, ACK] Seg=256 Ac         21       1.250842       192.168.0.1       192.168.0.2       TCP       1025 > 5000 [ACK] Seg=1 Ack		
14       1.227451       192.168.0.2       192.168.0.1       HTP       SUBSCRIBE /unp/service/Layer3For         15       1.229309       192.168.0.1       192.168.0.2       TCP       http       3196       [ACK] Seq=1 Ack=256 W         16       1.229309       192.168.0.1       192.168.0.2       TCP       http       3196       [ACK] Seq=1 Ack=256 W         17       1.248351       192.168.0.1       192.168.0.2       TCP       1025 > 5000       [SVN] Seq=0 Len=0 MSS         18       1.248391       192.168.0.2       TCP       1025 > 5000       SVN] Seq=0 Len=0 MSS         19       1.250171       192.168.0.2       192.168.0.1       TCP       3196       FIN, ACK] Seq=256 Ac         20       1.250840       192.168.0.1       192.168.0.2       TCP       3196       FIN, ACK] Seq=257 Ack=14         21       1.250842       192.168.0.1       192.168.0.2       TCP       1025 > 5000       ACK       Seq=247 Ack=1.4         23       1.251868       192.168.0.1       192.168.0.2       TCP       1025 > 5000       ACK       Seq=247 Ack=1.4         24       1.252826       192.168.0.1       192.168.0.2       TCP       http > 3196       FIN, ACK] Seq=26611         25       1.254532 <t< td=""><td></td><td></td></t<>		
15       1.229309       192.168.0.1       192.168.0.2       TCP       http > 3196 [ACK] Seq=1 Ack=256 W         16       1.252421       192.168.0.1       192.168.0.2       TCP       [TCP Window Update] http > 3196         17       1.248355       192.168.0.1       192.168.0.2       TCP       [TCP Window Update] http > 3196         18       1.248355       192.168.0.1       192.168.0.2       TCP       1025 > 5000 [SN] Seq=0 Len=0 MSS         19       1.250171       192.168.0.1       192.168.0.1       TCP S000 > 1025 [SN, ACK] Seq=0 Ack=         19       1.250171       192.168.0.1       192.168.0.2       HTTP HTTP/1.0 200 0K         20       1.250285       192.168.0.1       192.168.0.1       TCP 3196 > http [FIN, ACK] Seq=256 Ac         21       1.250842       192.168.0.2       192.168.0.1       TCP 1025 > 5000 [ACK] Seq=256 Ac         21       1.250842       192.168.0.1       192.168.0.2       TCP http > 3196 [FIN, ACK] Seq=256 Ac         23       1.251868       192.168.0.1       192.168.0.2       TCP http > 3196 [FIN, ACK] Seq=26 Ack=         24       1.252826       192.168.0.2       192.168.0.1       TCP http > 3197 [SN, ACK] Seq=0 Ack=         25       1.25323       192.168.0.2       192.168.0.1       TCP http > 3197 [SN, ACK] Seq=0 Ack= <td></td> <td></td>		
16       1.322421       192.168.0.1       192.168.0.2       TCP       TCP       TCP       Mindow Update]       http s       3196         17       1.248355       192.168.0.1       192.168.0.2       TCP       1025 > 5000       [SYN]       Seq=0 Len=0       MSS         18       1.248391       192.168.0.2       192.168.0.1       TCP       1025 > 5000       [SYN]       Ack         19       1.55027       192.168.0.2       192.168.0.2       HTTP       HTTP/1.0       200       0X         20       1.250285       192.168.0.2       192.168.0.2       HTTP       HTTP/1.0       200       0X         21       1.250285       192.168.0.2       192.168.0.2       HTTP       HTTP/1.0       200       0X         22       1.250842       192.168.0.1       192.168.0.2       TCP       http > 3196       FIN. ACK       Seq=256 Ac         21       1.250842       192.168.0.1       192.168.0.2       TCP       1025 > 5000       [ACK]       Seq=24.4ck=1 Win         24       1.253826       192.168.0.1       192.168.0.1       TCP       3196       FIN. ACK]       Seq=26611         25       1.253323       192.168.0.2       TCP       http > 3197       SVM. ACK]<		
17 1.248355 192.168.0.1 192.168.0.2 TCP 1025 > 5000 [SYN] Seq=0 Len=0 MSS 18 1.248391 192.168.0.2 192.168.0.1 TCP 5000 > 1025 [SYN, ACK] Seq=0 Ack 19 1.250171 192.168.0.1 192.168.0.1 TCP 3196 > http [FIN, ACK] Seq=256 AC 20 1.250840 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=256 AC 21 1.250840 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=256 AC 23 1.250842 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=256 AC 24 1.252826 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=256 AC 25 1.25323 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=26611 25 1.25323 192.168.0.1 192.168.0.2 TCP http > 3197 [SYN, ACK] Seq=26611 25 1.25323 192.168.0.1 192.168.0.2 TCP http > 3197 [SYN, ACK] Seq=26611 25 1.254502 192.168.0.1 192.168.0.2 TCP http > 3197 [SYN, ACK] Seq=0 Ack= 27 1.254532 192.168.0.1 192.168.0.2 TCP http > 3197 [SYN, ACK] Seq=0 Ack= 27 1.254532 192.168.0.2 192.168.0.1 TCP 3197 > http [SYN] Seq=0 Len=0 MSS 26 1.254502 192.168.0.2 192.168.0.1 TCP 3197 > http [SYN, ACK] Seq=0 Ack= 27 1.254532 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) 3 Frame 11 (62 bytes on wire, 62 bytes captured) 3 Ethernet II, Src: 192.168.0.2 (192.168.0.2), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) 4 Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) 5 Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) 5 Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0 200 00 00 95b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 200 00 00 053 18 48 40 00 80 06 61 2c cd 80 00 2c da 8 .0.He a, 200 00 00 c7 c0 05 03 c3 65 f5 00 00 00 00 00 00 00 00 00 00 00 00 00		
18 1.248391 192.168.0.2 192.168.0.1 TCP 5000 > 1025 [SYN, ACK] Seq=0 Ack= 19 1.250171 192.168.0.1 192.168.0.2 HTTP HTTP/1.0 200 OK 20 1.250285 192.168.0.2 192.168.0.1 TCP 3196 > http [FIN, ACK] Seq=256 Ac 21 1.250842 192.168.0.1 192.168.0.1 TCP 3196 > http [FIN, ACK] Seq=256 Ac 21 1.250842 192.168.0.1 192.168.0.1 TCP 3196 > http [ACK] Seq=257 Ack=115 23 1.251868 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=256 Ac 192.168.0.1 192.168.0.2 TCP 1025 > 5000 [ACK] Seq=21 Ack=1 Win 24 1.252826 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=26611 25 1.253323 192.168.0.2 192.168.0.1 TCP 3197 > http [SVN] Seq=0 Len-0 MSS 26 1.254502 192.168.0.2 192.168.0.1 TCP 3197 > http [SVN] Seq=0 Len-0 MSS 26 1.254502 192.168.0.2 192.168.0.1 TCP 3197 > http [SVN] Seq=0 Len-0 MSS 26 1.254502 192.168.0.2 192.168.0.1 TCP 3197 > http [SVN] Seq=0 Len-0 MSS 26 1.254502 192.168.0.2 192.168.0.1 TCP 3197 > http [SVN] Seq=0 Len-0 MSS 26 1.254502 192.168.0.2 192.168.0.1 TCP 3197 > http [SVN] Seq=0 Len-0 MSS 26 1.254502 192.168.0.2 (00:0b15d120:cd102), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) 9 Frame 11 (62 bytes on wire, 62 bytes captured) 9 Ethernet II, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) 10 Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0 200 00 00 9 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 200 00 00 c7 c0 00 50 3c 36 95 f6 00 00 00 00 00 07 00 2], P<6p.		
19 1.250171       192.168.0.1       192.168.0.2       HTTP       HTTP/1.0       200 0K         20 1.250285       192.168.0.2       192.168.0.1       TCP       3196 > http       FIN, ACK] Seq=256 Ac         21 1.250840       192.168.0.1       192.168.0.2       TCP       3196 > http       FIN, ACK] Seq=257 Ack=15         23 1.251868       192.168.0.1       192.168.0.1       TCP       3196 > http       ACK] Seq=114 Ac         23 1.251868       192.168.0.1       192.168.0.2       TCP       1025 > 5000 [ACK] Seq=12 Ack=1 Win         24 1.252826       192.168.0.1       192.168.0.2       TCP       http > 3196 [FIN, ACK] Seq=26611         25 1.253323       192.168.0.2       192.168.0.1       TCP 3197 > http [SYN] Seq=0 Len=0 MSS       Seq=0 Ack=1 Win         26 1.254502       192.168.0.2       192.168.0.1       TCP 3197 > http [SYN] Seq=0 Ack=1 Win         27 1.254532       192.168.0.2       192.168.0.1       TCP 3197 > http [SYN] Seq=0 Ack=1 Win         27 1.254532       192.168.0.2       192.168.0.1       TCP 3197 > http [SYN] Seq=1 Ack=1 Win         28 Frame 11 (62 bytes on wire, 62 bytes captured)       Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a)         200 00 00 00 Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1)       Transmission Control Protocol, Src Port:		
21 1.250810       192.168.0.1       192.168.0.2       TCP       http > 3196       FIN. ACK] Seq=114 AC         22 1.250842       192.168.0.2       192.168.0.1       TCP       3196       http [ACK] Seq=257       Ack=115         23 1.251868       192.168.0.1       192.168.0.2       TCP       3196       http [ACK] Seq=257       Ack=115         23 1.251868       192.168.0.1       192.168.0.2       TCP       3196       FIN. ACK] Seq=257       Ack=11 Win         24 1.252826       192.168.0.1       192.168.0.2       TCP       http > 3196       FIN. ACK] Seq=26611         25 1.253323       192.168.0.2       192.168.0.1       TCP       http > 3197       StM       Seq=0       Ack=1 Win         25 1.25352       192.168.0.2       192.168.0.1       TCP       http > 3197       StM       Seq=0       Ack=2 7         26 1.254502       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=1       Ack=1 Win         26 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=1       Ack=1 Win         27 1.254532       192.168.0.2       (00:0bi5d:20:cd:02), Dst: Netgear_2d:75:9a       (00:09:5b:2d:75:9a)       Http: Ack=1       Ack=1 Win         28 Frame 11 (62 bytes on wire, 62 bytes captured)		
22 1.250842       192.168.0.2       192.168.0.1       TCP       3196 > http [ACK] Seq=257 Ack=115         23 1.251868       192.168.0.1       192.168.0.2       TCP       1025 > 5000 [ACK] Seq=1 Ack=1 Win         24 1.252826       192.168.0.1       192.168.0.2       TCP       http > 3196 [FIN, ACK] Seq=26611         25 1.253823       192.168.0.2       192.168.0.1       TCP       3197 > http [SVN] Seq=0 Len=0 MSS         26 1.254502       192.168.0.1       192.168.0.2       TCP       http > 3197 [SVN, ACK] Seq=1 Ack=1 Win         27 1.254532       192.168.0.1       192.168.0.2       TCP       http > 3197 [SVN, ACK] Seq=0 Ack=27         27 1.254532       192.168.0.2       TCP       http > 3197 [SVN, ACK] Seq=1 Ack=1 Win         27 1.254532       192.168.0.2       TCP       http > 3197 [SVN, ACK] Seq=1 Ack=1 Win         3 Frame 11 (62 bytes on wire, 62 bytes captured)       Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a)         3 Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1)       Internet (80), Seq: 0, Len: 0         2000 000 09 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00      [-u]		
23 1.251868 192.168.0.1 192.168.0.2 TCP 1025 > 5000 [ACK] Seq=1 Ack=1 Win 24 1.252826 192.168.0.1 192.168.0.2 TCP http > 3196 [FIN, ACK] Seq=2 Ack=1 25 1.25323 192.168.0.2 192.168.0.1 TCP 3197 http [SVN] Seq=0 Len-0 MSS 26 1.254502 192.168.0.2 192.168.0.2 TCP http > 3197 [SVN, ACK] Seq=0 Ack=2 27 1.254532 192.168.0.2 192.168.0.1 TCP 3197 > http [ACK] Seq=1 Ack=1 Win Frame 11 (62 bytes on wire, 62 bytes captured) 9 Frame 11 (62 bytes on wire, 62 bytes captured) 9 Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) 9 Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) 1 Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0 000 00 9 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 010 00 30 18 48 40 00 80 06 61 2c cd 80 00 2c da 8 .0.H# a, 020 00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 00 70 2], P<6p.		
24 1.252826       192.168.0.1       192.168.0.2       TCP       http > 3196       [FIN, Ack] Seq=26611         25 1.253323       192.168.0.2       192.168.0.1       TCP       3197 > http [SYN] Seq=0 Len=0 MSS         26 1.254502       192.168.0.1       192.168.0.2       TCP       3197 > http [SYN] Seq=0 Ack=         27 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=0 Ack=         27 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=0 Ack=         27 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=0 Ack=         27 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=0 Ack=         27 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=1 Ack=1 Win         3       Frame 11 (62 bytes on wire, 62 bytes captured)       10       102.168.0.2       102.168.0.2       102.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1       192.168.0.1		
25 1.253323       192.168.0.2       192.168.0.1       TCP       3197 > http       [SVN] Seq=0 Len=0 MSS         26 1.254502       192.168.0.1       192.168.0.2       TCP       http > 3197 [SVN, ACK] Seq=0 Ack=         27 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=1 Ack=1 Win         3 Frame 11 (62 bytes on wire, 62 bytes captured)		
26 1.254502 192.168.0.1 192.168.0.2 TCP http > 319 <sup>2</sup> [SYN, ACK] Seq=0 Ack= 27 1.254532 192.168.0.2 192.168.0.1 TCP 3197 > http [ACK] Seq=0 Ack=1 Win Frame 11 (62 bytes on wire, 62 bytes captured) 9 Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) 9 Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) 9 Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0 000 00 95 b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.He a,		
27 1.254532       192.168.0.2       192.168.0.1       TCP       3197 > http [ACK] Seq=1 Ack=1 Win         3 Frame 11 (62 bytes on wire, 62 bytes captured)		
Prame 11 (62 bytes on wire, 62 bytes captured) Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0           000         00         95 b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00        [-u]E.           000         00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8         .0.He a,		
Frame 11 (62 bytes on wire, 62 bytes captured)         Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a)         Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1)         Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0         000 00 09 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E.         010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.He a,	2/ 1.254552 152.106.0.2 152.106.0.1 (CF 515/ )	HCCP DACKS SEG-I ACK-I WIII
Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0 000 00 09 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.He a, 020 00 10 c7 c0 00 50 3c 36 5f 80 00 00 00 00 70 02].P<6		>
Ethernet II, Src: 192.168.0.2 (00:0b:5d:20:cd:02), Dst: Netgear_2d:75:9a (00:09:5b:2d:75:9a) Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0 000 00 09 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.He a, 020 00 10 c7 c0 00 50 3c 36 5f 80 00 00 00 00 70 02].P<6	ame 11 (62 hytes on wire 62 hytes centured)	
Internet Protocol, Src: 192.168.0.2 (192.168.0.2), Dst: 192.168.0.1 (192.168.0.1) Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0		D-00-Eh-04-7E-0->
Transmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), Seq: 0, Len: 0 00 00 09 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 010 00 30 18 48 40 00 80 06 61 2c cd a8 00 02 cd a8 .0.H@ a, 020 00 10 c 7c 00 50 3c 36 95 f8 00 00 00 00 70 2].P<6p.		•
000 00 09 5b 2d 75 9a 00 0b 5d 20 cd 02 08 00 45 00[-u]E. 010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.H@ a, 20 00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 07 02 .P<6p.		
010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.H@ a, 020 00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 70 02	ansmission Control Protocol, Src Port: 3196 (3196), Dst Port: http (80), 1	Seq: O, Len: O
010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.H@ a, 020 00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 70 02		
010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.H@ a, 020 00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 70 02		
010 00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.H@ a, 020 00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 70 02	00 09 5h 2d 75 9a 00 0h 5d 20 cd 02 08 00 45 00	
020 00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 70 02 .P<6p. 030 fa f0 27 e0 00 00 02 04 05 b4 01 01 04 02'	00 30 18 48 40 00 80 06 61 2c c0 a8 00 02 c0 a8 .0.He a,	
330 fa f0 27 e0 00 00 02 04 05 b4 01 01 04 02'	00 01 0c 7c 00 50 3c 36 95 f8 00 00 00 00 70 02 .P<6p.	
	ta to 27 eo 00 00 02 04 05 b4 01 01 04 02'	

Figure 6.6. Filtering on the TCP protocol

As you might have noticed, only packets of the TCP protocol are displayed now (e.g. packets 1-10 are hidden). The packet numbering will remain as before, so the first packet shown is now packet number 11.



#### Note!

When using a display filter, all packets remain in the capture file. The display filter only changes the display of the capture file but not its content!

You can filter on any protocol that Wireshark understands. You can also filter on any field that a dissector adds to the tree view, but only if the dissector has added an abbreviation for the field. A list of such fields is available in Wireshark in the **Add Expression...** dialog box. You can find more information on the **Add Expression...** dialog box in <u>Section 6.5</u>, "The "Filter Expression" dialog box".

For example, to narrow the packet list pane down to only those packets to or from the IP address 192.168.0.1, use **ip.addr==192.168.0.1**.



#### Note!

To remove the filter, click on the **Clear** button to the right of the filter field.

# 6.4. Building display filter expressions

Wireshark provides a simple but powerful display filter language that allows you to build quite complex filter expressions. You can compare values in packets as well as combine expressions into more specific expressions. The following sections provide more information on doing this.



### Tip!

You will find a lot of Display Filter examples at the **Wireshark Wiki Display Filter page** at <u>http://wiki.wireshark.org/DisplayFilters</u>.

### 6.4.1. Display filter fields

Every field in the packet details pane can be used as a filter string, this will result in showing only the packets where this field exists. For example: the filter string: **tcp** will show all packets containing the tcp protocol.

There is a complete list of all filter fields available through the menu item "Help/Supported Protocols" in the page "Display Filter Fields" of the Supported Protocols dialog.

XXX - add some more info here and a link to the statusbar info.

### 6.4.2. Comparing values

You can build display filters that compare values using a number of different comparison operators. They are shown in <u>Table 6.4</u>, "Display Filter comparison operators".



#### Tip!

You can use English and C-like terms in the same way, they can even be mixed in a filter string!

English	C-like	Description and example
eq	==	Equal
		ip.src==10.0.0.5
ne	! =	Not equal
		ip.src!=10.0.0.5
gt	>	Greater than
		frame.len > 10
lt	<	Less than
		frame.len < 128
ge	>=	Greater than or equal to
		frame.len ge 0x100
le	<=	Less than or equal to
		frame.len <= 0x20

#### Table 6.4. Display Filter comparison operators

In addition, all protocol fields are typed. <u>Table 6.5</u>, "<u>Display Filter Field Types</u>" provides a list of the types and example of how to express them.

Туре	Example
Unsigned integer (8-bit, 16-bit, 24-bit, 32-bit)	You can express integers in decimal, octal, or hexadecimal. The following display filters are equivalent:
	ip.len le 1500 ip.len le 02734 ip.len le 0x436
Signed integer (8-bit, 16-bit, 24-bit, 32-bit)	
Boolean	A boolean field is present in the protocol decode only if its value is true. For example, <b>tcp.flags.syn</b> is present, and thus true, only if the SYN flag is present in a TCP segment header.
	Thus the filter expression <b>tcp.flags.syn</b> will select only those packets for which this flag exists, that is, TCP segments where the segment header contains the SYN flag. Similarly, to find source-routed token ring packets, use a filter expression of <b>tr.sr</b> .
Ethernet address (6 bytes)	Separators can be a colon (:), dot (.) or dash (-) and can have one or two bytes between separators:
	<pre>eth.dst == ff:ff:ff:ff:ff:ff eth.dst == ff-ff-ff-ff-ff-ff eth.dst == ffff.fffff</pre>
IPv4 address	ip.addr == 192.168.0.1
	Classless InterDomain Routing (CIDR) notation can be used to test if an IPv4 address is in a certain subnet. For example, this display filter will find all packets in the 129.111 Class-B network:
	ip.addr == 129.111.0.0/16
IPv6 address	ipv6.addr == ::1
IPX address	ipx.addr == 0000000.ffffffffff
String (text)	http:request.uri == "http://www.wireshark.org/"

#### **Table 6.5. Display Filter Field Types**

# 6.4.3. Combining expressions

You can combine filter expressions in Wireshark using the logical operators shown in <u>Table 6.6, "Display</u> <u>Filter Logical Operations"</u>

#### Table 6.6. Display Filter Logical Operations

English	C-like	Description and example			
and	&&	jical AND			
		ip.src==10.0.0.5 and tcp.flags.fin			

English	C-like	Description and example		
or		Logical OR		
		ip.scr==10.0.0.5 or ip.src==192.1.1.1		
xor	~~	Logical XOR		
		tr.dst[0:3] == 0.6.29 xor tr.src[0:3] == 0.6.29		
not	!	Logical NOT		
		not llc		
[]		Substring Operator		
		Wireshark allows you to select subsequences of a sequence in rather elaborate ways. After a label you can place a pair of brackets [] containing a comma separated list of range specifiers.		
		eth.src[0:3] == 00:00:83		
		The example above uses the n:m format to specify a single range. In this case n is the beginning offset and m is the length of the range being specified.		
		eth.src[1-2] == 00:83		
		The example above uses the n-m format to specify a single range. In this case n is the beginning offset and m is the ending offset.		
		eth.src[:4] == 00:00:83:00		
		The example above uses the :m format, which takes everything from the beginning of a sequence to offset m. It is equivalent to 0:m		
		eth.src[4:] == 20:20		
		The example above uses the n: format, which takes everything from offset n to the end of the sequence.		
		eth.src[2] == 83		
		The example above uses the n format to specify a single range. In this case the element in the sequence at offset n is selected. This is equivalent to n:1.		
		eth.src[0:3,1-2,:4,4:,2] == 00:00:83:00:83:00:00:83:00:20:20:83		
		Wireshark allows you to string together single ranges in a comma separated list to form compound ranges as shown above.		

## 6.4.4. A common mistake



### Warning!

Using the != operator on combined expressions like: eth.addr, ip.addr, tcp.port, udp.port and alike will probably not work as expected!

Often people use a filter string to display something like **ip.addr** == 1.2.3.4 which will display all packets containing the IP address 1.2.3.4.

Then they use **ip.addr != 1.2.3.4** to see all packets not containing the IP address 1.2.3.4 in it. Unfortunately, this does **not** do the expected.

Instead, that expression will even be true for packets where either source or destination IP address equals 1.2.3.4. The reason for this, is that the expression **ip.addr != 1.2.3.4** must be read as "the packet contains a field named ip.addr with a value different from 1.2.3.4". As an IP datagram contains both a source and a destination address, the expression will evaluate to true whenever at least one of the two addresses differs from 1.2.3.4.

If you want to filter out all packets containing IP datagrams to or from IP address 1.2.3.4, then the correct filter is !(ip.addr == 1.2.3.4) as it reads "show me all the packets for which it is not true that a field named ip.addr exists with a value of 1.2.3.4", or in other words, "filter out all packets for which there are no occurrences of a field named ip.addr with the value 1.2.3.4".

# 6.5. The "Filter Expression" dialog box

When you are accustomed to Wireshark's filtering system and know what labels you wish to use in your filters it can be very quick to simply type a filter string. However if you are new to Wireshark or are working with a slightly unfamiliar protocol it can be very confusing to try to figure out what to type. The Filter Expression dialog box helps with this.



#### Tip!

The "Filter Expression" dialog box is an excellent way to learn how to write Wireshark display filter strings.

Л	Wireshark: Filter Expression			
	Field name		Relation	Value (protocol)
	2dparityfec	^	is present	
	3COMXN5			Predefined values:
			!=	
			>	
	🗄 802.11 Radiotap		<	
	802.3 Slow protocols     802.3 Slow p		>=	
	± 9P		<=	
	AAL1		contains	
	AAL3/4		matches	
	AARP     AAR			
	ACtrace			
	ADP     ADP			Range (offset:length)
	I AFP	~		
				🖉 OK 🛛 🗶 Cancel

Figure 6.7. The "Filter Expression" dialog box

When you first bring up the Filter Expression dialog box you are shown a tree list of field names, organized by protocol, and a box for selecting a relation.

**Field Name** Select a protocol field from the protocol field tree. Every protocol with filterable fields is listed at the top level. (You can search for a particular protocol entry by entering the

first few letters of the protocol name). By clicking on the "+" next to a protocol name you can get a list of the field names available for filtering for that protocol.

**Relation** Select a relation from the list of available relation. The **is present** is a unary relation which is true if the selected field is present in a packet. All other listed relations are binary relations which require additional data (e.g. a **Value** to match) to complete.

When you select a field from the field name list and select a binary relation (such as the equality relation ==) you will be given the opportunity to enter a value, and possibly some range information.

Value	You may enter an appropriate value in the <b>Value</b> text box. The <b>Value</b> will also indicate the type of value for the <b>field name</b> you have selected (like character string).
Predefined values	Some of the protocol fields have predefined values available, much like enum's in C. If the selected protocol field has such values defined, you can choose one of them here.
Range	XXX - add an explanation here!
ОК	When you have built a satisfactory expression click <b>OK</b> and a filter string will be built for you.
Cancel	You can leave the <b>Add Expression</b> dialog box without any effect by clicking the <b>Cancel</b> button.

# 6.6. Defining and saving filters

You can define filters with Wireshark and give them labels for later use. This can save time in remembering and retyping some of the more complex filters you use.

To define a new filter or edit an existing one, select the **Capture Filters...** menu item from the Capture menu or the **Display Filters...** menu item from the Analyze menu. Wireshark will then pop up the Filters dialog as shown in Figure 6.8, "The "Capture Filters" and "Display Filters" dialog boxes".



#### Note!

The mechanisms for defining and saving capture filters and display filters are almost identical. So both will be described here, differences between these two will be marked as such.



### Warning!

You must use **Save** to save your filters permanently. **Ok** or **Apply** will not save the filters, so they will be lost when you close Wireshark.

Wireshark	: Display Filter			
Edit	Filter			
	tpkt_long			
	tpkt_only			
New	ethernet broadcast			
	ip broadcast			
	dcerpc DCERPC fault			
Delete				
Properties	<u> </u>			
	broadcast			
Filter string:         ip.addr == 255.255.255.255				
🔯 <u>H</u> elp	QK ✓ ApplySave ズ ⊆lose			

Figure 6.8. The "Capture Filters" and "Display Filters" dialog boxes

New	This button adds a new filter to the list of filters. The currently entered values from Filter name and Filter string will be used. If any of these fields are empty, it will be set to "new".				
Delete	This button deletes the selected filter. It will be greyed out, if no filter is selected.				
Filter	You can select a filter from this list (which will fill in the filter name and filter string in the fields down at the bottom of the dialog box).				
Filter name:	You can change the name of the currently selected filter here.				
	Note!				
	The filter name will only be used in this dialog to identify the filter for your convenience, it will not be used elsewhere. You can add multiple filters with the same name, but this is not very useful.				
Filter string:	You can change the filter string of the currently selected filter here. Display Filter only: the string will be syntax checked while you are typing.				
Add Expression	Display Filter only: This button brings up the Add Expression dialog box which assists in building filter strings. You can find more information about the Add Expression dialog in <u>Section 6.5</u> , "The "Filter Expression" dialog box"				
ОК	Display Filter only: This button applies the selected filter to the current display and closes the dialog.				
Apply	Display Filter only: This button applies the selected filter to the current display, and keeps the dialog open.				
Save	Save the current settings in this dialog. The file location and format is explained in <u>Appendix A, <i>Files and Folders</i></u> .				

Close

Close this dialog. This will discard unsaved settings.

# 6.7. Defining and saving filter macros

You can define filter macros with Wireshark and give them labels for later use. This can save time in remembering and retyping some of the more complex filters you use.

XXX - add an explanation of this.

# 6.8. Finding packets

You can easily find packets once you have captured some packets or have read in a previously saved capture file. Simply select the **Find Packet...** menu item from the **Edit** menu. Wireshark will pop up the dialog box shown in Figure 6.9, "The "Find Packet" dialog box".

### 6.8.1. The "Find Packet" dialog box

Figure 6.9. The "Find Packet" dialog box

🛙 Wireshark: Find Packet				
Find				
	r 🔘 Hex value 🔘 String			
Eilter:				
Search In	String Options	Direction		
<ul> <li>Packet list</li> </ul>	Case sensitive	◯ Up		
O Packet details	Character set:	⊙ <u>D</u> own		
Packet bytes	ASCII Unicode & Non-Unicode			
🔯 <u>H</u> elp	Eind	<b>X</b> ⊆ancel		

You might first select the kind of thing to search for:

#### • Display filter

Simply enter a display filter string into the **Filter:** field, select a direction, and click on OK.

For example, to find the three way handshake for a connection from host 192.168.0.1, use the following filter string:

ip.src==192.168.0.1 and tcp.flags.syn==1

For more details on display filters, see Section 6.3, "Filtering packets while viewing"

• Hex Value

Search for a specific byte sequence in the packet data.

For example, use "00:00" to find the next packet including two null bytes in the packet data.

• String

Find a string in the packet data, with various options.

The value to be found will be syntax checked while you type it in. If the syntax check of your value succeeds, the background of the entry field will turn green, if it fails, it will turn red.

You can choose the search direction:

• Up

Search upwards in the packet list (decreasing packet numbers).

• Down

Search downwards in the packet list (increasing packet numbers).

### 6.8.2. The "Find Next" command

"Find Next" will continue searching with the same options used in the last "Find Packet".

### 6.8.3. The "Find Previous" command

"Find Previous" will do the same thing as "Find Next", but with reverse search direction.

# 6.9. Go to a specific packet

You can easily jump to specific packets with one of the menu items in the Go menu.

### 6.9.1. The "Go Back" command

Go back in the packet history, works much like the page history in current web browsers.

### 6.9.2. The "Go Forward" command

Go forward in the packet history, works much like the page history in current web browsers.

### 6.9.3. The "Go to Packet" dialog box

Figure 6.10. The "Go To Packet" dialog box



This dialog box will let you enter a packet number. When you press **OK**, Wireshark will jump to that packet.

### 6.9.4. The "Go to Corresponding Packet" command

If a protocol field is selected which points to another packet in the capture file, this command will jump to that packet.



#### Note!

As these protocol fields now work like links (just as in your Web browser), it's easier to simply double-click on the field to jump to the corresponding field.

### 6.9.5. The "Go to First Packet" command

This command will simply jump to the first packet displayed.

### 6.9.6. The "Go to Last Packet" command

This command will simply jump to the last packet displayed.

# 6.10. Marking packets

You can mark packets in the "Packet List" pane. A marked packet will be shown with black background, regardless of the coloring rules set. Marking a packet can be useful to find it later while analyzing in a large capture file.



### Warning!

The packet marks are not stored in the capture file or anywhere else, so all packet marks will be lost if you close the capture file.

You can use packet marking to control the output of packets when saving/exporting/printing. To do so, an option in the packet range is available, see <u>Section 5.9</u>, "The Packet Range frame".

There are three functions to manipulate the marked state of a packet:

- Mark packet (toggle) toggles the marked state of a single packet.
- Mark all displayed packets set the mark state of all displayed packets.
- Unmark all packets reset the mark state of all packets.

These mark functions are available from the "Edit" menu, and the "Mark packet (toggle)" function is also available from the pop-up menu of the "Packet List" pane.

# 6.11. Ignoring packets

You can ignore packets in the "Packet List" pane. Wireshark will then pretend that this packets does not exist in the capture file. An ignored packet will be shown with white background and gray foreground, regardless of the coloring rules set.



### Warning!

The packet ignored marks are not stored in the capture file or anywhere else, so all packet ignored marks will be lost if you close the capture file.

There are three functions to manipulate the ignored state of a packet:

- Ignore packet (toggle) toggles the ignored state of a single packet.
- Ignore all displayed packets set the ignored state of all displayed packets.
- Un-Ignore all packets reset the ignored state of all packets.

These ignore functions are available from the "Edit" menu, and the "Ignore packet (toggle)" function is also available from the pop-up menu of the "Packet List" pane.

# 6.12. Time display formats and time references

While packets are captured, each packet is timestamped. These timestamps will be saved to the capture file, so they will be available for later analysis.

A detailed description of timestamps, timezones and alike can be found at: Section 7.4, "Time Stamps".

The timestamp presentation format and the precision in the packet list can be chosen using the View menu, see Figure 3.5, "The "View" Menu".

The available presentation formats are:

- Date and Time of Day: 1970-01-01 01:02:03.123456 The absolute date and time of the day when the packet was captured.
- Time of Day: 01:02:03.123456 The absolute time of the day when the packet was captured.
- Seconds Since Beginning of Capture: 123.123456 The time relative to the start of the capture file or the first "Time Reference" before this packet (see Section 6.12.1, "Packet time referencing").
- Seconds Since Previous Captured Packet: 1.123456 The time relative to the previous captured packet.
- Seconds Since Previous Displayed Packet: 1.123456 The time relative to the previous displayed packet.
- Seconds Since Epoch (1970-01-01): 1234567890.123456 The time relative to epoch (midnight UTC of January 1, 1970).

The available precisions (aka. the number of displayed decimal places) are:

- Automatic The timestamp precision of the loaded capture file format will be used (the default).
- Seconds, Deciseconds, Centiseconds, Milliseconds, Microseconds or Nanoseconds The timestamp precision will be forced to the given setting. If the actually available precision is smaller, zeros will be appended. If the precision is larger, the remaining decimal places will be cut off.

Precision example: If you have a timestamp and it's displayed using, "Seconds Since Previous Packet", : the value might be 1.123456. This will be displayed using the "Automatic" setting for libpcap files (which is microseconds). If you use Seconds it would show simply 1 and if you use Nanoseconds it shows 1.123456000.

### 6.12.1. Packet time referencing

The user can set time references to packets. A time reference is the starting point for all subsequent packet time calculations. It will be useful, if you want to see the time values relative to a special packet, e.g. the start of a new request. It's possible to set multiple time references in the capture file.



### Warning!

The time references will not be saved permanently and will be lost when you close the capture file.



#### Note!

Time referencing will only be useful, if the time display format is set to "Seconds Since Beginning of Capture". If one of the other time display formats are used, time referencing will have no effect (and will make no sense either).

To work with time references, choose one of the "Time Reference" items in the "Edit" menu , see <u>Section 3.6, "The "Edit" menu</u>", or from the pop-up menu of the "Packet List" pane.

- Set Time Reference (toggle) Toggles the time reference state of the currently selected packet to on or off.
- Find Next Find the next time referenced packet in the "Packet List" pane.
- Find Previous Find the previous time referenced packet in the "Packet List" pane.

#### Figure 6.11. Wireshark showing a time referenced packet

🗷 tes	st.pcap - Wiresl	hark				X
Eile	<u>E</u> dit ⊻iew <u>G</u> o	⊆apture Analyze St	atistics <u>H</u> elp			
		🕷 ( do 🔀	x 🖏 📇 🔍	\$ \$ \$		
E	lter:			- + Đ	<pression apply<="" td="" ∑⊆lear="" ✔=""><td></td></pression>	
No	Time	Source	Destination	Protocol	Info	
	4 1.025659	192.168.0.2	igmp.mcast.net	IGMP	V3 Membership Report	
	5 1.044366	192.168.0.2	192.168.0.1	DNS	Standard query SRV _ldaptcp.nbg	
	6 1.048652	192.168.0.2	239.255.255.250	UDP	Source port: 3193 Destination po	
	7 1.050784 8 1.055053	192.168.0.2 192.168.0.1	192.168.0.1 192.168.0.2	DNS UDP	Standard query SOA nb10061d.ww004 Source port: 1900 Destination po	
	9 1.082038	192.168.0.2	192.168.0.255	NBNS	Registration NB NB10061D<00>	
	10 *REF*	192.168.0.2	192.168.0.1	DNS	Standard query A proxyconf.ww004.	
	11 0.114211	192.168.0.2	192.168.0.1	TCP	3196 > http [SYN] Seq=0 Len=0 MSS	
	12 0.115337	192.168.0.1	192.168.0.2	TCP	http > 3196 [SYN, ACK] Seq=0 Ack=	
	13 0.115380	192.168.0.2	192.168.0.1	TCP	3196 > http [ACK] Seg=1 Ack=1 Win	
	14 0.115506 15 0.117364	192.168.0.2 192.168.0.1	192.168.0.1 192.168.0.2	TCP TCP	3196 > http [PSH, ACK] Seq=1 Ack= http > 3196 [ACK] Seq=1 Ack=256 W	
	16 0.120476	192.168.0.1	192.168.0.2	TCP	TCP Window Update http > 3196	
	17 0.136410	192.168.0.1	192.168.0.2	TCP	1025 > 5000 [SYN] Seq=0 Len=0 MSS	5
	10.0.100110	100 100 0.0	100 100 0 1	700	TRADE FOR ACTIC RAL	
<					>	
		n: 0x1847 (6215)				
	Flags: 0x00					
	Fragment offs					
	Time to live:					
	Protocol: UDP	(0×11)				
+	Header checks	um: 0xa109 [connec	:t]			
	Source: 192.1	68.0.2 (192.168.0	2)			
	Destination:	192.168.0.1 (192.:	68.0.1)			1
0000	00 09 5b 2d 3	75 9a 00 0b 5d 20	cd 02 08 00 45 00	[-u]	.E.	
010	00 49 18 47 (	00 00 80 11 a1 09	c0 a8 00 02 c0 a8 .1	.G		
0200	00 01 0b d2 (			5.5 Fi.!.		
0030 0040	00 00 00 00 00 0			p roxyc w004.s iemer		
0050	65 74 00 00 0					~
	);/test.pcap" 14 KB	00,00,02			P: 120 D: 120 M: 0	-

A time referenced packet will be marked with the string \*REF\* in the Time column (see packet number 10). All subsequent packets will show the time since the last time reference.

# **Chapter 7. Advanced Topics**

# 7.1. Introduction

In this chapter some of the advanced features of Wireshark will be described.

# 7.2. Following TCP streams

If you are working with TCP based protocols it can be very helpful to see the data from a TCP stream in the way that the application layer sees it. Perhaps you are looking for passwords in a Telnet stream, or you are trying to make sense of a data stream. Maybe you just need a display filter to show only the packets of that TCP stream. If so, Wireshark's ability to follow a TCP stream will be useful to you.

Simply select a TCP packet in the packet list of the stream/connection you are interested in and then select the Follow TCP Stream menu item from the Wireshark Tools menu (or use the context menu in the packet list). Wireshark will set an appropriate display filter and pop up a dialog box with all the data from the TCP stream laid out in order, as shown in Figure 7.1, "The "Follow TCP Stream" dialog box".



### Note!

It is worthwhile noting that Follow TCP Stream installs a display filter to select all the packets in the TCP stream you have selected.

### 7.2.1. The "Follow TCP Stream" dialog box

🕼 Follow TCP Stream	$\times$
Stream Content SUBSCRIBE /upp/service/Layer3Forwarding HTTP/1.1 NT: upprevent Callback: <http: (compatible;="" 0="" 0k="" 1.0="" 1.0;="" 192.168.0.1="" 192.168.0.2:5000="" 200="" 4.0="" 5.1)="" close="" connection:="" content-length:="" hots:="" http="" mozilla="" no-cache="" notifys="" nt="" pragma:="" second-1800="" server:="" sid:="" td="" timeout:="" upnp="" upnp-device="Host/1.0" user-agent:="" uuid:cf<="" windows=""><td></td></http:>	
Save As Brint Entire conversation (368 bytes)	
Image: Second	3m

Figure 7.1. The "Follow TCP Stream" dialog box

The stream content is displayed in the same sequence as it appeared on the network. Traffic from A to B is marked in red, while traffic from B to A is marked in blue. If you like, you can change these colors in the Edit/Preferences "Colors" page.

Non-printable characters will be replaced by dots. XXX - What about line wrapping (maximum line length) and CRNL conversions?

The stream content won't be updated while doing a live capture. To get the latest content you'll have to reopen the dialog.

You can choose from the following actions:

- 1. Save As: Save the stream data in the currently selected format.
- 2. **Print**: Print the stream data in the currently selected format.
- 3. **Direction**: Choose the stream direction to be displayed ("Entire conversation", "data from A to B only" or "data from B to A only").
- 4. Filter out this stream: Apply a display filter removing the current TCP stream data from the display.
- 5. Close: Close this dialog box, leaving the current display filter in effect.

You can choose to view the data in one of the following formats:

- 1. **ASCII**: In this view you see the data from each direction in ASCII. Obviously best for ASCII based protocols, e.g. HTTP.
- 2. **EBCDIC**: For the big-iron freaks out there.
- 3. **HEX Dump**: This allows you to see all the data. This will require a lot of screen space and is best used with binary protocols.
- 4. C Arrays: This allows you to import the stream data into your own C program.
- 5. **Raw**: This allows you to load the unaltered stream data into a different program for further examination. The display will look the same as the ASCII setting, but "Save As" will result in a binary file.

## 7.3. Expert Infos

The expert infos is a kind of log of the anomalies found by Wireshark in a capture file.

The general idea behind the following "Expert Info" is to have a better display of "uncommon" or just notable network behaviour. This way, both novice and expert users will hopefully find probable network problems a lot faster, compared to scanning the packet list "manually".



### Expert infos are only a hint!

Take expert infos as a hint what's worth looking at, but not more. For example: The absence of expert infos doesn't necessarily mean everything is ok!



# The amount of expert infos largely depends on the protocol being used!

While some common protocols like TCP/IP will show detailed expert infos, most other protocols currently won't show any expert infos at all.

The following will first describe the components of a single expert info, then the User Interface.

### 7.3.1. Expert Info Entries

Each expert info will contain the following things which will be described in detail below:

Packet #	Severity	Group	Protocol	Summary	
1	Note	Sequence	TCP	Duplicate ACK (#1)	
2	Chat	Sequence	ТСР	Connection reset (RST)	
8	Note	Sequence	ТСР	Keep-Alive	
9	Warn	Sequence	ТСР	Fast retransmission (suspected)	

#### Table 7.1. Some example expert infos

### 7.3.1.1. Severity

Every expert info has a specific severity level. The following severity levels are used, in parentheses are the colors in which the items will be marked in the GUI:

- Chat (grey): information about usual workflow, e.g. a TCP packet with the SYN flag set
- Note (cyan): notable things, e.g. an application returned an "usual" error code like HTTP 404
- Warn (yellow): warning, e.g. application returned an "unusual" error code like a connection problem
- Error (red): serious problem, e.g. [Malformed Packet]

### 7.3.1.2. Group

There are some common groups of expert infos. The following are currently implemented:

- Checksum: a checksum was invalid
- **Sequence**: protocol sequence suspicious, e.g. sequence wasn't continuous or a retransmission was detected or ...
- Response Code: problem with application response code, e.g. HTTP 404 page not found
- **Request Code**: an application request (e.g. File Handle == x), usually Chat level
- Undecoded: dissector incomplete or data can't be decoded for other reasons
- **Reassemble**: problems while reassembling, e.g. not all fragments were available or an exception happened while reassembling
- **Protocol**: violation of protocol specs (e.g. invalid field values or illegal lengths), dissection of this packet is probably continued
- Malformed: malformed packet or dissector has a bug, dissection of this packet aborted
- **Debug**: debugging (should not occur in release versions)

It's possible that more such group values will be added in the future ...

### 7.3.1.3. Protocol

The protocol in which the expert info was caused.

### 7.3.1.4. Summary

Each expert info will also have a short additional text with some further explanation.

### 7.3.2. "Expert Info" dialog

From the main menu you can open the expert info dialog, using: "Analyze/Expert Info"

XXX - add explanation of the dialogs context menu.

2	Wireshark	: 92 Expert	Infos				×
	Errors: 0 Wa	rnings: 2 Nol	es: 12 Chats: 2 Details				
	Group 🔻	Protocol 🔹	Summary	•	Count	•	
	∃ Sequence	TCP	Previous segment lost (common at capture star	rt)	11		
	🗄 Sequence	TCP	Fast retransmission (suspected)		5		

### 7.3.2.1. Errors / Warnings / Notes / Chats tabs


An easy and quick way to find the most interesting infos (rather than using the Details tab), is to have a look at the separate tabs for each severity level. As the tab label also contains the number of existing entries, it's easy to find the tab with the most important entries.

There are usually a lot of identical expert infos only differing in the packet number. These identical infos will be combined into a single line - with a count column showing how often they appeared in the capture file. Clicking on the plus sign shows the individual packet numbers in a tree view.

### 7.3.2.2. Details tab

The Details tab provides the expert infos in a "log like" view, each entry on its own line (much like the packet list). As the amount of expert infos for a capture file can easily become very large, getting an idea of the interesting infos with this view can take quite a while. The advantage of this tab is to have all entries in the sequence as they appeared, this is sometimes a help to pinpoint problems.

### 7.3.3. "Colorized" Protocol Details Tree



The protocol field causing an expert info is colorized, e.g. uses a cyan background for a note severity level. This color is propagated to the toplevel protocol item in the tree, so it's easy to find the field that caused the expert info.

For the example screenshot above, the IP "Time to live" value is very low (only 1), so the corresponding protocol field is marked with a cyan background. To easier find that item in the packet tree, the IP protocol toplevel item is marked cyan as well.

### 7.3.4. "Expert" Packet List Column (optional)

Source	Destination	Expert	Protocol	Info
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
192.168.0.2	205.196.219.244		TCP	gat-1md > http [ACK] Seq
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
192.168.0.2	205.196.219.244		TCP	gat-1md > http [ACK] Seq
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
205.196.219.244	192.168.0.2	Warn	TCP	TCP Previous segment lo
192.168.0.2	205.196.219.244		TCP	<pre>gat-lmd &gt; http [ACK] Seq</pre>
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
192.168.0.2	205,196,219,244	Note	TCP	[TCP Dup ACK 626#1] gat-
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
192.168.0.2	205.196.219.244	Note	TOP	[TCP Dup ACK 626#2] gat-
205.196.219.244	192.168.0.2		TCP	[TCP segment of a reasser
192.168.0.2	205.196.219.244	Note	TCP	[TCP Dup ACK 626#3] gat-
205.196.219.244	192.168.0.2	Chat	HTTP	[TCP_Retransmission] HTT
192.168.0.2	205.196.219.244		TCP	<pre>gat-lmd &gt; http [ACK] Seq</pre>
192.168.0.2	205.196.219.244	Chat	HTTP	GET /favicon.ico HTTP/1.
205.196.219.244	192.168.0.2	Chat	HTTP	HTTP/1.1 200 OK (image/x)
192.168.0.2	205.196.219.244		TCP	<pre>centra &gt; http [ACK] Seg=</pre>

An optional "Expert Info Severity" packet list column is available (since SVN 22387  $\rightarrow$  0.99.7), that displays the most significant severity of a packet, or stays empty if everything seems ok. This column is not displayed by default, but can be easily added using the Preferences Columns page described in Section 10.5, "Preferences".

# 7.4. Time Stamps

Time stamps, their precisions and all that can be quite confusing. This section will provide you with information about what's going on while Wireshark processes time stamps.

While packets are captured, each packet is time stamped as it comes in. These time stamps will be saved to the capture file, so they also will be available for (later) analysis.

So where do these time stamps come from? While capturing, Wireshark gets the time stamps from the libpcap (WinPcap) library, which in turn gets them from the operating system kernel. If the capture data is loaded from a capture file, Wireshark obviously gets the data from that file.

### 7.4.1. Wireshark internals

The internal format that Wireshark uses to keep a packet time stamp consists of the date (in days since 1.1.1970) and the time of day (in nanoseconds since midnight). You can adjust the way Wireshark displays the time stamp data in the packet list, see the "Time Display Format" item in the <u>Section 3.7, "The "View"</u> menu" for details.

While reading or writing capture files, Wireshark converts the time stamp data between the capture file format and the internal format as required.

While capturing, Wireshark uses the libpcap (WinPcap) capture library which supports microsecond resolution. Unless you are working with specialized capturing hardware, this resolution should be adequate.

### 7.4.2. Capture file formats

Every capture file format that Wireshark knows supports time stamps. The time stamp precision supported by a specific capture file format differs widely and varies from one second "0" to one nanosecond "0.123456789". Most file formats store the time stamps with a fixed precision (e.g. microseconds), while some file formats are even capable of storing the time stamp precision itself (whatever the benefit may be).

The common libpcap capture file format that is used by Wireshark (and a lot of other tools) supports a fixed microsecond resolution "0.123456" only.



#### Note!

Writing data into a capture file format that doesn't provide the capability to store the actual precision will lead to loss of information. Example: If you load a capture file with nanosecond resolution and store the capture data to a libpcap file (with microsecond resolution) Wireshark obviously must reduce the precision from nanosecond to microsecond.

### 7.4.3. Accuracy

It's often asked: "Which time stamp accuracy is provided by Wireshark?". Well, Wireshark doesn't create any time stamps itself but simply gets them from "somewhere else" and displays them. So accuracy will depend on the capture system (operating system, performance, ...) that you use. Because of this, the above question is difficult to answer in a general way.



#### Note!

USB connected network adapters often provide a very bad time stamp accuracy. The incoming packets have to take "a long and winding road" to travel through the USB cable until they actually reach the kernel. As the incoming packets are time stamped when they are processed by the kernel, this time stamping mechanism becomes very inaccurate.

Conclusion: don't use USB connected NIC's when you need precise time stamp accuracy! (XXX - are there any such NIC's that generate time stamps on the USB hardware?)

# 7.5. Time Zones

If you travel across the planet, time zones can be confusing. If you get a capture file from somewhere around the world time zones can even be a lot more confusing ;-)

First of all, there are two reasons why you may not need to think about time zones at all:

- You are only interested in the time differences between the packet time stamps and don't need to know the exact date and time of the captured packets (which is often the case).
- You don't get capture files from different time zones than your own, so there are simply no time zone problems. For example: everyone in your team is working in the same time zone as yourself.

#### What are time zones?

People expect that the time reflects the sunset. Dawn should be in the morning maybe around 06:00 and dusk in the evening maybe at 20:00. These times will obviously vary depending on the season. It would be very confusing if everyone on earth would use the same global time as this would correspond to the sunset only at a small part of the world.

For that reason, the earth is split into several different time zones, each zone with a local time that corresponds to the local sunset.

The time zone's base time is UTC (Coordinated Universal Time) or Zulu Time (military and aviation). The older term GMT (Greenwich Mean Time) shouldn't be used as it is slightly incorrect (up to 0.9 seconds difference to UTC). The UTC base time equals to 0 (based at Greenwich, England) and all time zones have an offset to UTC between -12 to +14 hours!

For example: If you live in Berlin you are in a time zone one hour earlier than UTC, so you are in time zone "+1" (time difference in hours compared to UTC). If it's 3 o'clock in Berlin it's 2 o'clock in UTC "at the same moment".

Be aware that at a few places on earth don't use time zones with even hour offsets (e.g. New Delhi uses UTC+05:30)!

Further information can be found at: <u>http://en.wikipedia.org/wiki/Time\_zone</u> and <u>http://en.wikipedia.org/wiki/Coordinated\_Universal\_Time</u>.

#### What is daylight saving time (DST)?

Daylight Saving Time (DST), also known as Summer Time, is intended to "save" some daylight during the summer months. To do this, a lot of countries (but not all!) add a DST hour to the already existing UTC offset. So you may need to take another hour (or in very rare cases even two hours!) difference into your "time zone calculations".

Unfortunately, the date at which DST actually takes effect is different throughout the world. You may also note, that the northern and southern hemispheres have opposite DST's (e.g. while it's summer in Europe it's winter in Australia).

Keep in mind: UTC remains the same all year around, regardless of DST!

Further information can be found at: <u>http://en.wikipedia.org/wiki/Daylight\_saving</u>.

Further time zone and DST information can be found at: <u>http://wwp.greenwichmeantime.com/</u> and <u>http://</u> www.timeanddate.com/worldclock/.

### 7.5.1. Set your computer's time correctly!

If you work with people around the world, it's very helpful to set your computer's time and time zone right.

You should set your computers time and time zone in the correct sequence:

- 1. Set your time zone to your current location
- 2. Set your computer's clock to the local time

This way you will tell your computer both the local time and also the time offset to UTC.



#### Tip!

If you travel around the world, it's an often made mistake to adjust the hours of your computer clock to the local time. Don't adjust the hours but your time zone setting instead! For your computer, the time is essentially the same as before, you are simply in a different time zone with a different local time!

### Tip!

You can use the Network Time Protocol (NTP) to automatically adjust your computer to the correct time, by synchronizing it to Internet NTP clock servers. NTP clients are available for all operating systems that Wireshark supports (and for a lot more), for examples see: <u>http:</u>//www.ntp.org/.

### 7.5.2. Wireshark and Time Zones

So what's the relationship between Wireshark and time zones anyway?

Wireshark's native capture file format (libpcap format), and some other capture file formats, such as the Windows Sniffer, EtherPeek, AiroPeek, and Sun snoop formats, save the arrival time of packets as UTC values. UN\*X systems, and "Windows NT based" systems (Windows NT 4.0, 2000, XP, Server 2003, Vista, Server 2008, 7) represent time internally as UTC. When Wireshark is capturing, no conversion is necessary. However, if the system time zone is not set correctly, the system's UTC time might not be correctly set even if the system clock appears to display correct local time. "Windows 9x based" systems (Windows 95, Windows 98, Windows Me) represent time internally as local time. When capturing, WinPcap has to convert the time to UTC before supplying it to Wireshark. If the system's time zone is not set correctly, that conversion will not be done correctly.

Other capture file formats, such as the Microsoft Network Monitor, DOS-based Sniffer, and Network Instruments Observer formats, save the arrival time of packets as local time values.

Internally to Wireshark, time stamps are represented in UTC; this means that, when reading capture files that save the arrival time of packets as local time values, Wireshark must convert those local time values to UTC values.

Wireshark in turn will display the time stamps always in local time. The displaying computer will convert them from UTC to local time and displays this (local) time. For capture files saving the arrival time of packets as UTC values, this means that the arrival time will be displayed as the local time in your time zone, which might not be the same as the arrival time in the time zone in which the packet was captured. For capture files saving the arrival time of packets as local time values, the conversion to UTC will be done using your time zone's offset from UTC and DST rules, which means the conversion will not be done correctly; the conversion back to local time for display might undo this correctly, in which case the arrival time will be displayed as the arrival time in which the packet was captured.

	Los Angeles	New York	Madrid	London	Berlin	Tokyo
Capture File (UTC)	10:00	10:00	10:00	10:00	10:00	10:00
Local Offset to UTC	-8	-5	-1	0	+1	+9

#### Table 7.2. Time zone examples for UTC arrival times (without DST)

	Los Angeles	New York	Madrid	London	Berlin	Tokyo
Displayed Time (Local Time)	02:00	05:00	09:00	10:00	11:00	19:00

An example: Let's assume that someone in Los Angeles captured a packet with Wireshark at exactly 2 o'clock local time and sends you this capture file. The capture file's time stamp will be represented in UTC as 10 o'clock. You are located in Berlin and will see 11 o'clock on your Wireshark display.

Now you have a phone call, video conference or Internet meeting with that one to talk about that capture file. As you are both looking at the displayed time on your local computers, the one in Los Angeles still sees 2 o'clock but you in Berlin will see 11 o'clock. The time displays are different as both Wireshark displays will show the (different) local times at the same point in time.

**Conclusion**: You may not bother about the date/time of the time stamp you currently look at, unless you must make sure that the date/time is as expected. So, if you get a capture file from a different time zone and/ or DST, you'll have to find out the time zone/DST difference between the two local times and "mentally adjust" the time stamps accordingly. In any case, make sure that every computer in question has the correct time and time zone setting.

# 7.6. Packet Reassembling

### 7.6.1. What is it?

Network protocols often need to transport large chunks of data, which are complete in themselves, e.g. when transferring a file. The underlying protocol might not be able to handle that chunk size (e.g. limitation of the network packet size), or is stream-based like TCP, which doesn't know data chunks at all.

In that case the network protocol has to handle the chunk boundaries itself and (if required) spread the data over multiple packets. It obviously also needs a mechanism to determine the chunk boundaries on the receiving side.



### Tip!

Wireshark calls this mechanism reassembling, although a specific protocol specification might use a different term for this (e.g. desegmentation, defragmentation, ...).

### 7.6.2. How Wireshark handles it

For some of the network protocols Wireshark knows of, a mechanism is implemented to find, decode and display these chunks of data. Wireshark will try to find the corresponding packets of this chunk, and will show the combined data as additional pages in the "Packet Bytes" pane (for information about this pane, see Section 3.20, "The "Packet Bytes" pane").

#### Figure 7.2. The "Packet Bytes" pane with a reassembled tab

0000															SkE.	~
	01 48 3														.H3 Q	
	09 32 4															
0030	00 00 0	0 00	) a0	de	97	6C	d1	11	82	71	00	57	80	†0	lq.w	
Frame	(342 bytes)	) Re	assem	nbled	DCE	E/RPC	(160	14 by	tes)							



#### Note!

Reassembling might take place at several protocol layers, so it's possible that multiple tabs in the "Packet Bytes" pane appear.



#### Note!

You will find the reassembled data in the last packet of the chunk.

An example: In a **HTTP** GET response, the requested data (e.g. an HTML page) is returned. Wireshark will show the hex dump of the data in a new tab "Uncompressed entity body" in the "Packet Bytes" pane.

Reassembling is enabled in the preferences by default. The defaults were changed from disabled to enabled in September 2005. If you created your preference settings before this date, you might look if reassembling is actually enabled, as it can be extremely helpful while analyzing network packets.

The enabling or disabling of the reassemble settings of a protocol typically requires two things:

- 1. the lower level protocol (e.g., TCP) must support reassembly. Often this reassembly can be enabled or disabled via the protocol preferences.
- 2. the higher level protocol (e.g., HTTP) must use the reassembly mechanism to reassemble fragmented protocol data. This too can often be enabled or disabled via the protocol preferences.

The tooltip of the higher level protocol setting will notify you if and which lower level protocol setting also has to be considered.

# 7.7. Name Resolution

Name resolution tries to convert some of the numerical address values into a human readable format. There are two possible ways to do these conversions, depending on the resolution to be done: calling system/network services (like the gethostname() function) and/or resolve from Wireshark specific configuration files. For details about the configuration files Wireshark uses for name resolution and alike, see <u>Appendix A</u>, *Files and Folders*.

The name resolution feature can be enabled individually for the protocol layers listed in the following sections.

### 7.7.1. Name Resolution drawbacks

Name resolution can be invaluable while working with Wireshark and may even save you hours of work. Unfortunately, it also has its drawbacks.

- Name resolution will often fail. The name to be resolved might simply be unknown by the name servers asked, or the servers are just not available and the name is also not found in Wireshark's configuration files.
- The resolved names are not stored in the capture file or somewhere else. So the resolved names might not be available if you open the capture file later or on a different machine. Each time you open a capture file it may look "slightly different", simply because you can't connect to the name server (which you could connect to before).
- **DNS may add additional packets to your capture file.** You may see packets to/from your machine in your capture file, which are caused by name resolution network services of the machine Wireshark captures from. XXX are there any other such packets than DNS ones?
- **Resolved DNS names are cached by Wireshark.** This is required for acceptable performance. However, if the name resolution information should change while Wireshark is running, Wireshark won't notice a change in the name resolution information once it gets cached. If this information changes while Wireshark is running, e.g. a new DHCP lease takes effect, Wireshark won't notice it. XXX - is this true for all or only for DNS info?



### Tip!

The name resolution in the packet list is done while the list is filled. If a name could be resolved after a packet was added to the list, that former entry won't be changed. As the name resolution results are cached, you can use "View/Reload" to rebuild the packet list, this time with the correctly resolved names. However, this isn't possible while a capture is in progress.

### 7.7.2. Ethernet name resolution (MAC layer)

Try to resolve an Ethernet MAC address (e.g. 00:09:5b:01:02:03) to something more "human readable".

**ARP name resolution (system service)**: Wireshark will ask the operating system to convert an Ethernet address to the corresponding IP address (e.g.  $00:09:5b:01:02:03 \rightarrow 192.168.0.1$ ).

**Ethernet codes (ethers file)**: If the ARP name resolution failed, Wireshark tries to convert the Ethernet address to a known device name, which has been assigned by the user using an ethers file (e.g.  $00:09:5b:01:02:03 \rightarrow$  homerouter).

**Ethernet manufacturer codes (manuf file)**: If neither ARP or ethers returns a result, Wireshark tries to convert the first 3 bytes of an ethernet address to an abbreviated manufacturer name, which has been assigned by the IEEE (e.g.  $00:09:5b:01:02:03 \rightarrow Netgear_01:02:03$ ).

### 7.7.3. IP name resolution (network layer)

Try to resolve an IP address (e.g. 216.239.37.99) to something more "human readable".

**DNS/concurrent DNS name resolution (system/library service)**: Wireshark will ask the operating system (or the concurrent DNS library), to convert an IP address to the hostname associated with it (e.g.  $216.239.37.99 \rightarrow$  www.1.google.com). The DNS service is using synchronous calls to the DNS server. So Wireshark will stop responding until a response to a DNS request is returned. If possible, you might consider using the concurrent DNS library (which won't wait for a name server response).



### Warning!

Enabling network name resolution when your name server is unavailable may significantly slow down Wireshark while it waits for all of the name server requests to time out. Use concurrent DNS in that case.

**DNS vs. concurrent DNS**: here's a short comparison: Both mechanisms are used to convert an IP address to some human readable (domain) name. The usual DNS call gethostname() will try to convert the address to a name. To do this, it will first ask the systems hosts file (e.g. /etc/hosts) if it finds a matching entry. If that fails, it will ask the configured DNS server(s) about the name.

So the real difference between DNS and concurrent DNS comes when the system has to wait for the DNS server about a name resolution. The system call gethostname() will wait until a name is resolved or an error occurs. If the DNS server is unavailable, this might take quite a while (several seconds).

The concurrent DNS service works a bit differently. It will also ask the DNS server, but it won't wait for the answer. It will just return to Wireshark in a very short amount of time. The actual (and the following) address fields won't show the resolved name until the DNS server returns an answer. As mentioned above, the values get cached, so you can use View/Reload to "update" these fields to show the resolved values.

**hosts name resolution (hosts file)**: If DNS name resolution failed, Wireshark will try to convert an IP address to the hostname associated with it, using a hosts file provided by the user (e.g. 216.239.37.99  $\rightarrow$  www.google.com).

### 7.7.4. IPX name resolution (network layer)

ipxnet name resolution (ipxnets file): XXX - add ipxnets name resolution explanation.

### 7.7.5. TCP/UDP port name resolution (transport layer)

Try to resolve a TCP/UDP port (e.g. 80) to something more "human readable".

**TCP/UDP port conversion (system service)**: Wireshark will ask the operating system to convert a TCP or UDP port to its well known name (e.g.  $80 \rightarrow http$ ).

XXX - mention the role of the /etc/services file (but don't forget the files and folders section)!

# 7.8. Checksums

Several network protocols use checksums to ensure data integrity.



### Tip!

Applying checksums as described here is also known as redundancy checking.

#### What are checksums for?

Checksums are used to ensure the integrity of data portions for data transmission or storage. A checksum is basically a calculated summary of such a data portion.

Network data transmissions often produce errors, such as toggled, missing or duplicated bits. As a result, the data received might not be identical to the data transmitted, which is obviously a bad thing.

Because of these transmission errors, network protocols very often use checksums to detect such errors. The transmitter will calculate a checksum of the data and transmits the data together with the checksum. The receiver will calculate the checksum of the received data with the same algorithm as the transmitter. If the received and calculated checksums don't match a transmission error has occurred.

Some checksum algorithms are able to recover (simple) errors by calculating where the expected error must be and repairing it.

If there are errors that cannot be recovered, the receiving side throws away the packet. Depending on the network protocol, this data loss is simply ignored or the sending side needs to detect this loss somehow and retransmits the required packet(s).

Using a checksum drastically reduces the number of undetected transmission errors. However, the usual checksum algorithms cannot guarantee an error detection of 100%, so a very small number of transmission errors may remain undetected.

There are several different kinds of checksum algorithms; an example of an often used checksum algorithm is CRC32. The checksum algorithm actually chosen for a specific network protocol will depend on the expected error rate of the network medium, the importance of error detection, the processor load to perform the calculation, the performance needed and many other things.

Further information about checksums can be found at: <u>http://en.wikipedia.org/wiki/Checksum</u>.

### 7.8.1. Wireshark checksum validation

Wireshark will validate the checksums of several protocols, e.g.: IP, TCP, UDP, ...

It will do the same calculation as a "normal receiver" would do, and shows the checksum fields in the packet details with a comment, e.g.: [correct], [invalid, must be 0x12345678] or alike.

Checksum validation can be switched off for various protocols in the Wireshark protocol preferences, e.g. to (very slightly) increase performance.

If the checksum validation is enabled and it detected an invalid checksum, features like packet reassembling won't be processed. This is avoided as incorrect connection data could "confuse" the internal database.

### 7.8.2. Checksum offloading

The checksum calculation might be done by the network driver, protocol driver or even in hardware.

For example: The Ethernet transmitting hardware calculates the Ethernet CRC32 checksum and the receiving hardware validates this checksum. If the received checksum is wrong Wireshark won't even see the packet, as the Ethernet hardware internally throws away the packet.

Higher level checksums are "traditionally" calculated by the protocol implementation and the completed packet is then handed over to the hardware.

Recent network hardware can perform advanced features such as IP checksum calculation, also known as checksum offloading. The network driver won't calculate the checksum itself but will simply hand over an empty (zero or garbage filled) checksum field to the hardware.



#### Note!

Checksum offloading often causes confusion as the network packets to be transmitted are handed over to Wireshark before the checksums are actually calculated. Wireshark gets these "empty" checksums and displays them as invalid, even though the packets will contain valid checksums when they leave the network hardware later.

Checksum offloading can be confusing and having a lot of [invalid] messages on the screen can be quite annoying. As mentioned above, invalid checksums may lead to unreassembled packets, making the analysis of the packet data much harder.

You can do two things to avoid this checksum offloading problem:

- Turn off the checksum offloading in the network driver, if this option is available.
- Turn off checksum validation of the specific protocol in the Wireshark preferences.

# **Chapter 8. Statistics**

# 8.1. Introduction

Wireshark provides a wide range of network statistics which can be accessed via the **Statistics** menu.

These statistics range from general information about the loaded capture file (like the number of captured packets), to statistics about specific protocols (e.g. statistics about the number of HTTP requests and responses captured).

- General statistics:
  - **Summary** about the capture file.
  - Protocol Hierarchy of the captured packets.
  - Conversations e.g. traffic between specific IP addresses.
  - Endpoints e.g. traffic to and from an IP addresses.
  - **IO Graphs** visualizing the number of packets (or similar) in time.
- Protocol specific statistics:
  - Service Response Time between request and response of some protocols.
  - Various other protocol specific statistics.



#### Note!

The protocol specific statistics requires detailed knowledge about the specific protocol. Unless you are familiar with that protocol, statistics about it will be pretty hard to understand.

# 8.2. The "Summary" window

General statistics about the current capture file.

	rk: Summary		_ <b>D</b> ×						
File									
Name:	/home/stig/htt	p.pcap							
Length:	1713904 bytes								
Format:	Wireshark/tcpc	lump/ libpca	р						
Packet size limit:	65535 bytes								
Time									
First packet:	2007-11-30 20	:49:42							
Last packet:	2007-11-30 20	:50:14							
Elapsed:	00:00:32								
Capture									
Interface:	eth0								
Dropped packets:	unknown								
Capture filter:	none								
Display	1								
	http or dns								
Display filter:									
Traffic	Captured	Displayed	Marked						
	Captured 2239	Displayed 367	Marked 0						
Traffic	2239								
Traffic Packets	2239	367							
Traffic Packets Between first and last packet	2239 32.374 sec 69.160	367 19.684 sec							
Traffic Packets Between first and last packet Avg. packets/sec	2239 32.374 sec 69.160	367 19.684 sec 18.645							
Traffic Packets Between first and last packet Avg. packets/sec Avg. packet size	2239 32.374 sec 69.160 749.467 bytes	367 19.684 sec 18.645 575.507 bytes							
Traffic Packets Between first and last packet Avg. packets/sec Avg. packet size Bytes	2239 32.374 sec 69.160 749.467 bytes 1678056	367 19.684 sec 18.645 575.507 bytes 211211							

#### Figure 8.1. The "Summary" window

- File: general information about the capture file.
- Time: the timestamps when the first and the last packet were captured (and the time between them).
- **Capture**: information from the time when the capture was done (only available if the packet data was captured from the network and not loaded from a file).
- **Display**: some display related information.
- **Traffic**: some statistics of the network traffic seen. If a display filter is set, you will see values in the Captured column, and if any packages are marked, you will see values in the Marked column. The values in the **Captured** column will remain the same as before, while the values in the **Displayed** column will reflect the values corresponding to the packets shown in the display. The values in the **Marked** column will reflect the values corresponding to the marked packages.

# 8.3. The "Protocol Hierarchy" window

The protocol hierarchy of the captured packets.

Wireshark:				cs			
	Display filt	er: http o	r dns				
Protocol	% Packets	Packets	Bytes	Mbit/s	End Packets	End Bytes	End Mbit/s
▽ Frame	100.00%	367	211211	0.086	0	0	0.000
▽ Ethernet	100.00%	367	211211	0.086	0	0	0.000
▽ Internet Protocol	100.00%	367	211211	0.086	0	0	0.000
▽ Transmission Control Protocol	93.46%	343	207029	0.084	113	82553	0.034
∽ Hypertext Transfer Protocol	62.67%	230	124476	0.051	189	93393	0.038
Compuserve GIF	7.36%	27	17114	0.007	27	17114	0.007
Line-based text data	3.27%	12	12265	0.005	12	12265	0.005
JPEG File Interchange Format	0.27%	1	990	0.000	1	990	0.000
eXtensible Markup Language	0.27%	1	714	0.000	1	714	0.000
▽ User Datagram Protocol	6.54%	24	4182	0.002	0	0	0.000
Domain Name Service	6.54%	24	4182	0.002	24	4182	0.002
2 Help						[	Close

#### Figure 8.2. The "Protocol Hierarchy" window

This is a tree of all the protocols in the capture. You can collapse or expand subtrees, by clicking on the plus / minus icons. By default, all trees are expanded.

Each row contains the statistical values of one protocol. The **Display filter** will show the current display filter.

The following columns containing the statistical values are available:

- **Protocol**: this protocol's name
- % Packets: the percentage of protocol packets, relative to all packets in the capture
- Packets: the absolute number of packets of this protocol
- Bytes: the absolute number of bytes of this protocol
- MBit/s: the bandwidth of this protocol, relative to the capture time
- End Packets: the absolute number of packets of this protocol (where this protocol was the highest protocol to decode)
- End Bytes: the absolute number of bytes of this protocol (where this protocol was the highest protocol to decode)
- End MBit/s: the bandwidth of this protocol, relative to the capture time (where this protocol was the highest protocol to decode)



#### Note!

Packets will usually contain multiple protocols, so more than one protocol will be counted for each packet. Example: In the screenshot IP has 99,17% and TCP 85,83% (which is together much more than 100%).



#### Note!

Protocol layers can consist of packets that won't contain any higher layer protocol, so the sum of all higher layer packets may not sum up to the protocols packet count. Example: In the screenshot TCP has 85,83% but the sum of the subprotocols (HTTP, ...) is much less. This may be caused by TCP protocol overhead, e.g. TCP ACK packets won't be counted as packets of the higher layer).

#### Note!

A single packet can contain the same protocol more than once. In this case, the protocol is counted more than once. For example: in some tunneling configurations the IP layer can appear twice.

# 8.4. Conversations

Statistics of the captured conversations.

### 8.4.1. What is a Conversation?

A network conversation is the traffic between two specific endpoints. For example, an IP conversation is all the traffic between two IP addresses. The description of the known endpoint types can be found in Section 8.5.1, "What is an Endpoint?".

### 8.4.2. The "Conversations" window

The conversations window is similar to the endpoint Window; see <u>Section 8.5.2</u>, "<u>The "Endpoints"</u> <u>window</u>" for a description of their common features. Along with addresses, packet counters, and byte counters the conversation window adds four columns: the time in seconds between the start of the capture and the start of the conversation ("Rel Start"), the duration of the conversation in seconds, and the average bits (not bytes) per second in each direction.

		 T	CP Conv	ersations -	- Filter: l	http or dns			
Address A	Port A	Address B		Packets		Packets A->B	Bytes A-	>B Packets	A<-B
10.211.55.3	60790	193.69.165.21	http	126	72615	63	28028	63	
10.211.55.3	60789	193.69.165.21	http	104	64791	52	23330	52	
10.211.55.3	41144	128.121.50.122	http	18	9991	9	6794	9	
10.211.55.3	41145	128.121.50.122	http	18	8994	9	6885	9	
10.211.55.3	45168	193.69.165.57	http	4	3336	2	970	2	
10.211.55.3	51236	81.93.163.17	Las		2001	<u> </u>	1500	<u> </u>	
10.211.55.3	45169	193.69.165.5 Ap	ply as Fil	ter	• s	Selected	•	A <-> B	
10.211.55.3	50948	81.7.166.249 Pre	epare a P	ilter	• •	Not Selected	•	A> B	
10.211.55.3	41632	194.237.107. Fin	d Packet		- ▶ .	and Selected	•	А < В	
10.211.55.3	51305	193.69.165.2	lorizo Ca	nversation	h	or Selected	•	A <-> ANY	
10.211.55.3	58101	80.76.145.17	101128 CC	niversation					
10.211.55.3	41623	209.85.141.99	http	4	1967 ·	and not Select	ed 🕨	A> ANY	
10.211.55.3	43305	62.70.11.43	http	2	1959 .	or not Selected	4 F	A < ANY	
10.211.55.3	51291	193.69.165.29	http	2	1876	1	541	ANY <-> B	
< l								ANY < B	
Name reso	lution			_	Limit t	o display filter		ANY> B	

#### Figure 8.3. The "Conversations" window

Each row in the list shows the statistical values for exactly one conversation.

**Name resolution** will be done if selected in the window and if it is active for the specific protocol layer (MAC layer for the selected Ethernet endpoints page).

Limit to display filter will only show conversations matching the current display filter.

The copy button will copy the list values to the clipboard in CSV (Comma Separated Values) format.



This window will be updated frequently, so it will be useful, even if you open it before (or while) you are doing a live capture.

### 8.4.3. The protocol specific "Conversation List" windows

Before the combined window described above was available, each of its pages was shown as a separate window. Even though the combined window is much more convenient to use, these separate windows are still available. The main reason is that they might process faster for very large capture files. However, as the functionality is exactly the same as in the combined window, they won't be discussed in detail here.

# 8.5. Endpoints

Statistics of the endpoints captured.



#### Tip!

If you are looking for a feature other network tools call a **hostlist**, here is the right place to look. The list of Ethernet or IP endpoints is usually what you're looking for.

### 8.5.1. What is an Endpoint?

A network endpoint is the logical endpoint of separate protocol traffic of a specific protocol layer. The endpoint statistics of Wireshark will take the following endpoints into account:

- Ethernet: an Ethernet endpoint is identical to the Ethernet's MAC address.
- Fibre Channel: XXX insert info here.
- **FDDI**: a FDDI endpoint is identical to the FDDI MAC address.
- IPv4: an IP endpoint is identical to its IP address.
- **IPX**: an IPX endpoint is concatenation of a 32 bit network number and 48 bit node address, be default the Ethernets' MAC address.
- JXTA: a JXTA endpoint is a 160 bit SHA-1 URN.
- NCP: XXX insert info here.
- **RSVP**: XXX insert info here.
- SCTP: a SCTP endpoint is a combination of the host IP addresses (plural) and the SCTP port used. So different SCTP ports on the same IP address are different SCTP endpoints, but the same SCTP port on different IP addresses of the same host are still the same endpoint.

- **TCP**: a TCP endpoint is a combination of the IP address and the TCP port used, so different TCP ports on the same IP address are different TCP endpoints.
- Token Ring: a Token Ring endpoint is identical to the Token Ring MAC address.
- **UDP**: a UDP endpoint is a combination of the IP address and the UDP port used, so different UDP ports on the same IP address are different UDP endpoints.
- USB: XXX insert info here.
- WLAN: XXX insert info here.



### Broadcast / multicast endpoints

Broadcast / multicast traffic will be shown separately as additional endpoints. Of course, as these endpoints are virtual endpoints, the real traffic will be received by all (multicast: some) of the listed unicast endpoints.

### 8.5.2. The "Endpoints" window

This window shows statistics about the endpoints captured.

#### Figure 8.4. The "Endpoints" window

			Endpoir	nts: h	ttp.p	осар			D
Ethernet: 2 Fibre	Channel	FDDI IPv	/4:16 IPX JX	TA N	CP F	SVP SCTP	TCP	: 51 Token Ring UDP: 2	USB WLAN
IPv4 Endpoints - Filter: http or dns									
Address	Packets	Bytes	Tx Packets *	T× B	ytes	Rx Packets	R×I	Bytes	<b>A</b>
10.211.55.3	367	211211	184	9100	)5	183	120	)206	
193.69.165.21	230	137406	115	8604	18	115	513	358	
128.121.50.122	36	18985	18	5306	5	18	136	579	
193.69.165.29	28	18580	14	1023	35	14	834	15	
10.211.55.1	24	4182	12	3275	5	12	907	7	
193.69.165.57	8	5824	4	388			100		
62.70.11.43	6	3596	3	20: 1	Apply	as Filter	•	Selected	
81.7.166.249	6	5165	3	188	Prepa	ire a Filter	•	Not Selected	
81.93.163.170	7	3581	3	140	Find F	rame		and Selected	
209.85.141.99	4	1967	2	580	Colori	ze Host Tra	ffic	or Selected	
81.93.172.130	4	1610	2	524	COION	ze Host ira			
194.237.107.53	4	3817	2	1830	)	2	198	and not Selected	
193.88.71.150	4	2193	2	1037	7	2	115	5 or not Selected	
66.102.9.99	2	1060	1	425		1	635	5	
194.237.107.154	2	1252	1	277		1	975	5	•
🗹 Name resolutio	n				🗹 L	imit to disp	lay filt	er	
<u>H</u> elp								<b>Copy</b>	Close

For each supported protocol, a tab is shown in this window. Each tab label shows the number of endpoints captured (e.g. the tab label "Ethernet: 5" tells you that five ethernet endpoints have been captured). If no endpoints of a specific protocol were captured, the tab label will be greyed out (although the related page can still be selected).

Each row in the list shows the statistical values for exactly one endpoint.

**Name resolution** will be done if selected in the window and if it is active for the specific protocol layer (MAC layer for the selected Ethernet endpoints page). As you might have noticed, the first row has a name resolution of the first three bytes "Netgear", the second row's address was resolved to an IP address (using

ARP) and the third was resolved to a broadcast (unresolved this would still be: ff:ff:ff:ff:ff:ff:ff); the last two Ethernet addresses remain unresolved.

Limit to display filter will only show conversations matching the current display filter.

The copy button will copy the list values to the clipboard in CSV (Comma Separated Values) format.

### Tip!

This window will be updated frequently, so it will be useful, even if you open it before (or while) you are doing a live capture.


### 8.5.3. The protocol specific "Endpoint List" windows

Before the combined window described above was available, each of its pages was shown as a separate window. Even though the combined window is much more convenient to use, these separate windows are still available. The main reason is that they might process faster for very large capture files. However, as the functionality is exactly the same as in the combined window, they won't be discussed in detail here.

# 8.6. The "IO Graphs" window

User configurable graph of the captured network packets.

You can define up to five differently colored graphs.



#### Figure 8.5. The "IO Graphs" window

The user can configure the following things:

#### • Graphs

- Graph 1-5: enable the specific graph 1-5 (only graph 1 is enabled by default)
- Color: the color of the graph (cannot be changed)

- **Filter**: a display filter for this graph (only the packets that pass this filter will be taken into account for this graph)
- **Style**: the style of the graph (Line/Impulse/FBar/Dot)
- X Axis
  - Tick interval: an interval in x direction lasts (10/1 minutes or 10/1/0.1/0.01/0.001 seconds)
  - Pixels per tick: use 10/5/2/1 pixels per tick interval
  - View as time of day: option to view x direction labels as time of day instead of seconds or minutes since beginning of capture
- Y Axis
  - Unit: the unit for the y direction (Packets/Tick, Bytes/Tick, Bits/Tick, Advanced...) [XXX describe the Advanced feature.]
  - Scale: the scale for the y unit (Logarithmic, Auto, 10, 20, 50, 100, 200, 500, ...)

The save button will save the currently displayed portion of the graph as one of various file formats.

The **copy** button will copy values from selected graphs to the clipboard in CSV (Comma Separated Values) format.



### Tip!

Click in the graph to select the first package in the selected interval.

# 8.7. Service Response Time

The service response time is the time between a request and the corresponding response. This information is available for many protocols.

Service response time statistics are currently available for the following protocols:

- DCE-RPC
- Fibre Channel
- H.225 RAS
- LDAP
- LTE MAC
- MGCP
- ONC-RPC
- SMB

As an example, the DCE-RPC service response time is described in more detail.



### Note!

The other Service Response Time windows will work the same way (or only slightly different) compared to the following description.

### 8.7.1. The "Service Response Time DCE-RPC" window

The service response time of DCE-RPC is the time between the request and the corresponding response.

First of all, you have to select the DCE-RPC interface:

#### Figure 8.6. The "Compute DCE-RPC statistics" window

🖸 Wiresha	ark: Compute DCE-RPC SRT statistics 💦 🗖 🔀
Program:	ATSVC - EPM Version: 1 V
Eilter:	
	Create Stat

You can optionally set a display filter, to reduce the amount of packets.

#### Figure 8.7. The "DCE-RPC Statistic for ..." window

2	DCE-	RPC Service Response Time	statis	stics	for EPM m	ajor versio	n 3: test 🔳	
	DCE-RPC Service Response Time statistics for EPM major version 3: test.pcap Filter:							
	ndex	Procedure	Calls	•	Min SRT	Max SRT	Avg SRT	
				×	lose			

Each row corresponds to a method of the interface selected (so the EPM interface in version 3 has 7 methods). For each method the number of calls, and the statistics of the SRT time is calculated.

## 8.8. Compare two capture files

Compare two capture files.

This feature works best when you have merged two capture files chronologically, one from each side of a client/server connection.

The merged capture data is checked for missing packets. If a matching connection is found it is checked for:

- IP header checksums
- Excessive delay (defined by the "Time variance" setting)
- Packet order

#### Figure 8.8. The "Compare" window

Compare two capture file	s: wsweb co	mpare 2010-04-22.pcap	- • •
- Co Nu Sci an Eq All	mpare Statis Imber of pac opes: start: d: start: ual packets: owed variati	:kets total:208 1st file:98, 2nd file:110 1 stop:4 5 stop:8	
IP Id Problem	Cour	nt Delta	*
15638 Not arrived in tin	ne 2	225.062000	
15824 Not arrived in tin	ne 2	128.999000	
⊞ 16413 Not arrived in tin	ne 2	326.914000	
16644 Packet lost	1	0.000000	
16645 Packet lost	1	0.000000	
16646 Packet lost	1	0.00000	
16647 Packet lost	1	0.000000	
16648 Packet lost	1	0.000000	
16649 Packet lost	1	0.000000	E
17073 Not arrived in tin	ne 2	78.630000	
17755 Not arrived in tin	ne 2	14.971000	
17756 Not arrived in tin	ne 2	14.499000	
⊞ 17757 Not arrived in tin	ne 2	9.909000	
20804 Not arrived in tin	ne 2	154.061000	
	ne 2	277.575000	
20919 Not arrived in tin	ne 2	274.044000	
	ne 2	97.442000	-
Help			<u>C</u> lose

You can configure the following:

- **Start compare:** Start comparing when this many IP IDs are matched. A zero value starts comparing immediately.
- Stop compare: Stop comparing when we can no longer match this many IP IDs. Zero always compares.
- Endpoint distinction: Use MAC addresses or IP time-to-live values to determine connection endpoints.
- Check order: Check for the same IP ID in the previous packet at each end.
- **Time variance:** Trigger an error if the packet arrives this many milliseconds after the average delay.
- Filter: Limit comparison to packets that match this display filter.

The info column contains new numbering so the same packets are parallel.

The color filtering differentiate the two files from each other. A "zebra" effect is create if the Info column is sorted.



If you click on an item in the error list its corresponding packet will be selected in the main window.

# **8.9. WLAN Traffic Statistics**

Tip!

Statistics of the captured WLAN traffic. This window will summarize the wireless network traffic found in the capture. Probe requests will be merged into an existing network if the SSID matches.

#### Figure 8.9. The "WLAN Traffic Statistics" window

	Wireshark: WLAN Traffic Statistics: w1.pcap										
WLAN Traffic Statistics											
BSSID	Channel	SSID .	Beacons	Data Packets	Probe Req	Probe Resp	Auth	Deauth	Other	Percent	Protection
00:13:1a:a0:12:c0			0	58	0	0	0	0	0	0.04%	
00:02:e3:46:99:f8	11	AMX	744	6	0	14	0	0	0	0.46%	WEP
00:0e:2e:c2:15:07	1	Fortress GB	13	0	0	0	0	0	0	0.01%	
00:13:1a:6e:91:e0	1	Telenor Mobil WLAN	130030	9683	15	15441	3	0	2	94.43%	
🗌 Name resolutio	n			🗹 Only	/ show existi	ng networks					
🕜 <u>H</u> elp										<u>C</u> opy	Close

Each row in the list shows the statistical values for exactly one wireless network.

Name resolution will be done if selected in the window and if it is active for the MAC layer.

**Only show existing networks** will exclude probe requests with a SSID not matching any network from the list.

The copy button will copy the list values to the clipboard in CSV (Comma Separated Values) format.



#### Tip!

This window will be updated frequently, so it will be useful, even if you open it before (or while) you are doing a live capture.

## 8.10. The protocol specific statistics windows

The protocol specific statistics windows display detailed information of specific protocols and might be described in a later version of this document.

Some of these statistics are described at the http://wiki.wireshark.org/Statistics pages.

# **Chapter 9. Telephony**

# 9.1. Introduction

Wireshark provides a wide range of telephony related network statistics which can be accessed via the **Telephony** menu.

These statistics range from specific signaling protocols, to analysis of signaling and media flows. If encoded in a compatible encoding the media flow can even be played.

# 9.2. RTP Analysis

The RTP analysis function takes the selected RTP stream (and the reverse stream, if possible) and generates a list of statistics on it.

	🛛 🖸 Wireshark: RTP Stream Analysis									
Forwa	Forward Direction Reversed Direction									
Analysing stream from 10.1.3.143 port 5000 to 10.1.6.18 port 2006 SSRC = 0xDEE0EE8F										
Pacl▼	Sequei	Delta(r	Filtered Jitte	Skew(ms	) IP BW(k	Mark	Status			^
34	59133	0.00	0.00	0.00	2.24	SET	[ Ok ]			
35	59134	29.97	0.00	0.03	4.48		[ Ok ]			
36	59135	30.13	0.01	-0.10	6.72		[ Ok ]			
37	59136	30.11	0.02	-0.21	8.96		[ Ok ]			
38	59137	30.11	0.02	-0.32	11.20		[ Ok ]			
39	59138	30.18	0.03	- <mark>0</mark> .51	13.44		[ Ok ]			
41	59139	28.73	0.11	0.76	15.68		[ Ok ]			
43	59140	29.99	0.10	0.77	17.92		[ Ok ]			
45	59141	29.99	0.10	0.78	20.16		[ Ok ]			-
	Max delta = 34.83 ms at packet no. 274 Max jitter = 0.83 ms. Mean jitter = 0.37 ms. Max skew = -4.14 ms. Total RTP packets = 236 (expected 236) Lost RTP packets = 0 (0.00%) Sequence errors = 0 Duration 7.05 s (-60 ms clock drift, corresponding to 7932 Hz (-0.85%)									
Save	payload	Save as	s CSV 😂	<u>R</u> efresh	🎨 jump to		Graph	Next non-Ok	X <u>C</u> lose	

### Figure 9.1. The "RTP Stream Analysis" window

Starting with basic data as packet number and sequence number, further statistics are created based on arrival time, delay, jitter, packet size, etc.

Besides the per packet statistics, the lower pane shows the overall statistics, with minimums and maximums for delta, jitter and clock skew. Also an indication of lost packets is included.

The RTP Stream Analysis window further provides the option to save the RTP payload (as raw data or, if in a PCM encoding, in an Audio file). Other options a to export and plot various statistics on the RTP streams.

# 9.3. VoIP Calls

The VoIP Calls window shows a list of all detected VoIP calls in the captured traffic. It finds calls by their signaling.

More details are described at the http://wiki.wireshark.org/VoIP\_calls page.

# 9.4. LTE MAC Traffic Statistics

Statistics of the captured LTE MAC traffic. This window will summarize the LTE MAC traffic found in the capture.

### Figure 9.2. The "LTE MAC Traffic Statistics" window

0		BCH E	Bytes: 0		PC	CH Frames	: 0		PCH Byt	tes: 0	
ata (20 UE	s)										
	UL Fra	mes UL	Bytes UL	CRC Errors	UL ReTX	Frames	DL Frames	DL Bytes	DL CRC E	rrors DL R	eTX Frames
		0	0	0		0	138	41538		0	0
		0	0	0		0	140	42140		0	0
							140	42140			0
		0	0	0		0	140	42140		0	0
		0	0	0		0	139	41839		0	0
details											
CCCH	LCID 1	LCID 2	LCID 3	LCID 4	LCID 5	LCID 6	LCID 7	LCID 8	LCID 9	LCID 10	Predefined
0	0	-	-	-	0	0	0	0	0	0	
			-	-						0	
140 1540	140 22400	0		-	0	0	-	0	0	0	
	details CCCH	details CCCH LCID 1 0 0 0	ata (20 UEs) UL Frames UL 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	UL Frames         UL Bytes         UL           0         0         0         0           0	UL Frames         UL Bytes         UL CRC Errors           0	UL Frames         UL Bytes         UL CRC Errors         UL ReTX           0         0         0         0         0           0	UL Frames         UL Bytes         UL CRC Errors         UL ReTX Frames         0           0	UL Frames         UL Bytes         UL CRC Errors         UL ReTX Frames         DL Frames           0         0         0         0         138           0         0         0         0         140           0         0         0         0         140           0         0         0         0         140           0         0         0         0         140           0         0         0         0         140           0         0         0         0         140           0         0         0         0         140           0         0         0         0         140           0         0         0         0         140           0         0         0         0         139           details         0         0         0         0         0           0         0         0         0         0         0         0           0         0         0         0         0         0         0         0	UL Frames         UL Bytes         UL CRC Errors         UL RETX Frames         DL Frames         DL Bytes           0         0         0         0         138         41538           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         139         41839           details         0         0         0         0         0         0           0         0         0         0         0         0         0         0         0           0         0         0         0         0         0         0         0         0         0           0         0	UL Frames         UL Bytes         UL CRC Errors         UL ReTX Frames         DL Frames         DL Bytes         DL CRC E           0         0         0         0         138         41538           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         140         42140           0         0         0         0         139         41839           details         CCCH         LCID 1         LCID 2         LCID 3         LCID 4         LCID 5         LCID 6         LCID 7         LCID 8         LCID 9           0         0         0         0         0         0         0         0         0         0	UL Frames       UL Bytes       UL CRC Errors       UL RETX Frames       DL Frames       DL Bytes       DL CRC Errors       DL R         0       0       0       0       138       41538       0         0       0       0       0       140       42140       0         0       0       0       0       140       42140       0         0       0       0       0       139       41839       0         details

The top pane shows statistics for common channels. Each row in the middle pane shows statistical highlights for exactly one UE/C-RNTI. In the lower pane, you can see the for the currently selected UE/C-RNTI the traffic broken down by individual channel.

# 9.5. LTE RLC Traffic Statistics

Statistics of the captured LTE RLC traffic. This window will summarize the LTE RLC traffic found in the capture.

Wireshark: LTE RLC Traffic Statistics: test04_multi_ue.out (2 UEs, 22 frames)           Show RLC PDUs found inside logged MAC frames									
_2 UEs									
UEId						UL Frames	UL Bytes	DL Frames	DL Bytes
1						12	213	0	0
2						10	202	0	0
Channels of se		-	UL Bytes	UL ACKs	UL NACKs	DL Frames	DL Bytes	DL ACKs	DL NACKs
сссн	TM	1	6	0	0	1	24	0	0
SRB-1	AM		41		0		4		0
Filter on select			Set DL o	lisplay filte	r for this cha	nnel Set U	_ / DL disp	lay filter for t	his channel
🕐 <u>H</u> elp									⊗ <u>C</u> lose

### Figure 9.3. The "LTE RLC Traffic Statistics" window

At the top, the check-box allows this window to include RLC PDUs found withing MAC PDUs or not. This will affect both the PDUs counted as well as the display filters generated (see below).

The upper list shows summaries of each active UE. Each row in the lower list shows statistical highlights for individual channels within the selected UE.

The lower part of the windows allows display filters to be generated and set for the selected channel. Note that in the case of Acknowledged Mode channels, if a single direction is chosen, the generated filter will show data in that direction and control PDUs in the opposite direction.

## 9.6. The protocol specific statistics windows

The protocol specific statistics windows display detailed information of specific protocols and might be described in a later version of this document.

Some of these statistics are described at the <u>http://wiki.wireshark.org/Statistics</u> pages.

# Chapter 10. Customizing Wireshark

# **10.1. Introduction**

Wireshark's default behaviour will usually suit your needs pretty well. However, as you become more familiar with Wireshark, it can be customized in various ways to suit your needs even better. In this chapter we explore:

- How to start Wireshark with command line parameters
- How to colorize the packet list
- How to control protocol dissection
- How to use the various preference settings

# **10.2. Start Wireshark from the command line**

You can start Wireshark from the command line, but it can also be started from most Window managers as well. In this section we will look at starting it from the command line.

Wireshark supports a large number of command line parameters. To see what they are, simply enter the command **wireshark -h** and the help information shown in <u>Example 10.1</u>, "Help information available from Wireshark" (or something similar) should be printed.

#### **Example 10.1. Help information available from Wireshark**

Wireshark 1.7.0 (SVN Rev 38783 from /trunk) Interactively dump and analyze network traffic. See http://www.wireshark.org for more information. Copyright 1998-2011 Gerald Combs <gerald@wireshark.org> and contributors. This is free software; see the source for copying conditions. There is NO warranty; not even for MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. Usage: wireshark [options] ... [ <infile> ] Capture interface: -i <interface> name or idx of interface (def: first non-loopback) -f <capture filter> packet filter in libpcap filter syntax -s <snaplen> packet snapshot length (def: 65535) don't capture in promiscuous mode -p -k start capturing immediately (def: do nothing) update packet display when new packets are captured -.5 -1 turn on automatic scrolling while -S is in use – T capture in monitor mode, if available -B <buffer size> size of kernel buffer (def: 1MB) link layer type (def: first appropriate) -y <link type> -D print list of interfaces and exit -L print list of link-layer types of iface and exit Capture stop conditions: -c <packet count> stop after n packets (def: infinite) -a <autostop cond.> ... duration:NUM - stop after NUM seconds filesize:NUM - stop this file after NUM KB files:NUM - stop after NUM files Capture output: -b <ringbuffer opt.> ... duration:NUM - switch to next file after NUM secs filesize:NUM - switch to next file after NUM KB files:NUM - ringbuffer: replace after NUM files Input file: -r <infile> set the filename to read from (no pipes or stdin!) Processing: -R <read filter> packet filter in Wireshark display filter syntax disable all name resolutions (def: all enabled) -n -N <name resolve flags> enable specific name resolution(s): "mntC" User interface: start with specified configuration profile -C <config profile> -d <display filter> start with the given display filter go to specified packet number after "-r" -g <packet number> -J <jump filter> jump to the first packet matching the (display) filter - i search backwards for a matching packet after "-J" -m <font> set the font name used for most text -t ad a r d dd e output format of time stamps (def: r: rel. to first) -u s|hms output format of seconds (def: s: seconds) -X <key>:<value> eXtension options, see man page for details -z <statistics> show various statistics, see man page for details Output: -w <outfile -> set the output filename (or '-' for stdout) Miscellaneous: -h display this help and exit display version info and exit -v -P <key>:<path> persconf:path - personal configuration files persdata:path - personal data files -o <name>:<value> ... override preference or recent setting -K <keytab> keytab file to use for kerberos decryption --display=DISPLAY X display to use

We will examine each of the command line options in turn.

The first thing to notice is that issuing the command **wireshark** by itself will bring up Wireshark. However, you can include as many of the command line parameters as you like. Their meanings are as follows ( in alphabetical order ): XXX - is the alphabetical order a good choice? Maybe better task based?

-a <capture autostop="" condition=""></capture>		at specifies when Wireshark is to stop writing e criterion is of the form test:value, where test					
	duration:value	Stop writing to a capture file after value of seconds have elapsed.					
	<b>filesize</b> :value	Stop writing to a capture file after it reaches a size of value kilobytes (where a kilobyte is 1000 bytes, not 1024 bytes). If this option is used together with the -b option, Wireshark will stop writing to the current capture file and switch to the next one if filesize is reached.					
	files:value	Stop writing to capture files after value number of files were written.					
-b <capture buffer="" option="" ring=""></capture>	If a maximum capture file size was specified, this option causes Wireshark to run in "ring buffer" mode, with the specified number of files. In "ring buffer" mode, Wireshark will write to several capture files. Their name is based on the number of the file and on the creation date and time.						
	When the first capture file fills up, Wireshark will switch to writing to the next file, until it fills up the last file, at which point it'll discard the data in the first file (unless 0 is specified, in which case, the number of files is unlimited) and start writing to that file and so on.						
	If the optional duration is specified, Wireshark will also switch to the next file when the specified number of seconds has elapsed even if the current file is not completely fills up.						
	duration:value	Switch to the next file after value seconds have elapsed, even if the current file is not completely filled up.					
	filesize:value	Switch to the next file after it reaches a size of value kilobytes (where a kilobyte is 1000 bytes, not 1024 bytes).					
	files:value	Begin again with the first file after value number of files were written (form a ring buffer).					
-B <capture (win32="" buffer="" only)="" size=""></capture>	is used by the capture	ture buffer size (in MB, default is 1MB). This e driver to buffer packet data until that data can you encounter packet drops while capturing, ze.					

-c <capture count="" packet=""></capture>	This option specifies the maximum number of packets to capture when capturing live data. It would be used in conjunction with the <b>-k</b> option.
-D	Print a list of the interfaces on which Wireshark can capture, and exit. For each network interface, a number and an interface name, possibly followed by a text description of the interface, is printed. The interface name or the number can be supplied to the <b>-i</b> flag to specify an interface on which to capture.
	This can be useful on systems that don't have a command to list them (e.g., Windows systems, or UNIX systems lacking <b>ifconfig</b> - <b>a</b> ); the number can be useful on Windows 2000 and later systems, where the interface name is a somewhat complex string.
	Note that "can capture" means that Wireshark was able to open that device to do a live capture; if, on your system, a program doing a network capture must be run from an account with special privileges (for example, as root), then, if Wireshark is run with the - <b>D</b> flag and is not run from such an account, it will not list any interfaces.
-f <capture filter=""></capture>	This option sets the initial capture filter expression to be used when capturing packets.
-g <packet number=""></packet>	After reading in a capture file using the -r flag, go to the given packet number.
-h	The $-h$ option requests Wireshark to print its version and usage instructions (as shown above) and exit.
-i <capture interface=""></capture>	Set the name of the network interface or pipe to use for live packet capture.
	Network interface names should match one of the names listed in <b>wireshark -D</b> (described above); a number, as reported by <b>wireshark -D</b> , can also be used. If you're using UNIX, <b>netstat -i</b> or <b>ifconfig -a</b> might also work to list interface names, although not all versions of UNIX support the <b>-a</b> flag to <b>ifconfig</b> .
	If no interface is specified, Wireshark searches the list of interfaces, choosing the first non-loopback interface if there are any non-loopback interfaces, and choosing the first loopback interface if there are no non-loopback interfaces; if there are no interfaces, Wireshark reports an error and doesn't start the capture.
	Pipe names should be either the name of a FIFO (named pipe) or ``-" to read data from the standard input. Data read from pipes must be in standard libpcap format.
-J <jump filter=""></jump>	After reading in a capture file using the <b>-r</b> flag, jump to the first packet which matches the filter expression. The filter expression is in display filter format. If an exact match cannot be found the first packet afterwards is selected.
-j	Use this option after the $-J$ option to search backwards for a first packet to go to.

-k	The <b>-k</b> option specifies that Wireshark should start capturing packets immediately. This option requires the use of the <b>-i</b> parameter to specify the interface that packet capture will occur from.
-1	This option turns on automatic scrolling if the packet list pane is being updated automatically as packets arrive during a capture ( as specified by the <b>-S</b> flag).
-L	List the data link types supported by the interface and exit.
-m <font></font>	This option sets the name of the font used for most text displayed by Wireshark. XXX - add an example!
-n	Disable network object name resolution (such as hostname, TCP and UDP port names).
-N <name flags="" resolving=""></name>	Turns on name resolving for particular types of addresses and port numbers; the argument is a string that may contain the letters $\mathbf{m}$ to enable MAC address resolution, $\mathbf{n}$ to enable network address resolution, and $\mathbf{t}$ to enable transport-layer port number resolution. This overrides - $\mathbf{n}$ if both - $\mathbf{N}$ and - $\mathbf{n}$ are present. The letter C enables concurrent (asynchronous) DNS lookups.
-o <preference recent="" settings=""></preference>	Sets a preference or recent value, overriding the default value and any value read from a preference/recent file. The argument to the flag is a string of the form prefname:value, where prefname is the name of the preference (which is the same name that would appear in the preference/recent file), and value is the value to which it should be set. Multiple instances of <b>-o <preference settings=""></preference></b> can be given on a single command line.
	An example of setting a single preference would be:
	wireshark -o mgcp.display_dissect_tree:TRUE
	An example of setting multiple preferences would be:
	wireshark -o mgcp.display_dissect_tree:TRUE -o mgcp.udp.callagent_port:2627
	👝 Tip!
	You can get a list of all available preference strings from the preferences file, see <u>Appendix A</u> , <i>Files and Folders</i> .
	User access tables can be overridden using "uat," followed by the UAT file name and a valid record for the file:
	wireshark -o ''uat:user_dlts:\''User 0 (DLT=147)\'',\''http\'', \''0\'',\''\'',\''0\'',\''\''
	The example above would dissect packets with a librcan data

The example above would dissect packets with a libpcap data link type 147 as HTTP, just as if you had configured it in the DLT\_USER protocol preferences.

-р	Don't put the interface into promiscuous mode. Note that the interface might be in promiscuous mode for some other reason; hence, -p cannot be used to ensure that the only traffic that is captured is traffic sent to or from the machine on which Wireshark is running, broadcast traffic, and multicast traffic to addresses received by that machine.					
-P <path setting=""></path>	Special path settings usually detected automatically. This is used for special cases, e.g. starting Wireshark from a known location or an USB stick.					
	The criterion is of th	e form key:path, where key is one of:				
	persconf:path	path of personal configuration files, like the preferences files.				
	persdata:path	path of personal data files, it's the folder initially opened. After the initialization, the recent file will keep the folder last used.				
-Q	This option forces Wireshark to exit when capturing is complete. It can be used with the <b>-c</b> option. It must be used in conjunction with the <b>-i</b> and <b>-w</b> options.					
-r <infile></infile>	This option provides the name of a capture file for Wireshark to read and display. This capture file can be in one of the formats Wireshark understands.					
-R <read (display)="" filter=""></read>	This option specifies a display filter to be applied when reading packets from a capture file. The syntax of this filter is that of the display filters discussed in <u>Section 6.3</u> , "Filtering packets while <u>viewing</u> ". Packets not matching the filter are discarded.					
-s <capture snaplen=""></capture>		s the snapshot length to use when capturing will only capture <b><snaplen></snaplen></b> bytes of data for				
-S	This option specifies that Wireshark will display packets as it captures them. This is done by capturing in one process and displaying them in a separate process. This is the same as "Update list of packets in real time" in the Capture Options dialog box.					
-t <time format="" stamp=""></time>	-	format of packet timestamps that are displayed adow. The format can be one of:				
	• <b>r</b> relative, which the first packet ca	specifies timestamps are displayed relative to ptured.				
	• <b>a</b> absolute, which packets.	specifies that actual times be displayed for all				
	• <b>ad</b> absolute with d be displayed for a	ate, which specifies that actual dates and times ll packets.				
	• <b>d</b> delta, which s previous packet.	pecifies that timestamps are relative to the				

	• e epoch, which specifies that timestamps are seconds since epoch (Jan 1, 1970 00:00:00)
-v	The <b>-v</b> option requests Wireshark to print out its version information and exit.
-w <savefile></savefile>	This option sets the name of the <b>savefile</b> to be used when saving a capture file.
-y <capture link="" type=""></capture>	If a capture is started from the command line with -k, set the data link type to use while capturing packets. The values reported by - L are the values that can be used.
-X <extension option=""></extension>	Specify an option to be passed to a TShark module. The eXtension option is in the form extension_key:value, where extension_key can be:
	<b>lua_script</b> :lua_script_filename; Tells Wireshark to load the given script in addition to the default Lua scripts.
-z <statistics-string></statistics-string>	Get Wireshark to collect various types of statistics and display the result in a window that updates in semi-real time. XXX - add more details here!

### **10.3.** Packet colorization

A very useful mechanism available in Wireshark is packet colorization. You can set-up Wireshark so that it will colorize packets according to a filter. This allows you to emphasize the packets you are (usually) interested in.



### Tip!

You will find a lot of Coloring Rule examples at the **Wireshark Wiki Coloring Rules page** at <u>http://wiki.wireshark.org/ColoringRules</u>.

There are two types of coloring rules in Wireshark; temporary ones that are only used until you quit the program, and permanent ones that will be saved to a preference file so that they are available on a next session.

Temporary coloring rules can be added by selecting a packet and pressing the <ctrl> key together with one of the number keys. This will create a coloring rule based on the currently selected conversation. It will try to create a conversation filter based on TCP first, then UDP, then IP and at last Ethernet. Temporary filters can also be created by selecting the "Colorize with Filter > Color X" menu items when rightclicking in the packet-detail pane.

To permanently colorize packets, select the **Coloring Rules...** menu item from the **View** menu; Wireshark will pop up the "Coloring Rules" dialog box as shown in Figure 10.1, "The "Coloring Rules" dialog box".

:dit	Filter		Order
		[List is processed in order until match is found]	
New [	Name	String	7
		-	
	tcp.analysis.fla	g: tcp.analysis.flags	🚺 🏠 Up
	cotp	cotp	
2 Edit	tpkt_long	tpkt.length > 519	
	nbss negative r	re nbss.type == 131	
	arp	arp	
	icmp	icmp	
🗑 <u>D</u> elete	smb	smb    nbss    nbns    nbipx    ipxsap    netbios	Move
	http	http    tcp.port == 80	selected filte
lanage	uninterested	ipx    stp    hsrp    eigrp    cdp	up or down
	dcerpc	dcerpc	
Export	tcp syn	tcp.flags.syn == 1    tcp.flags.fin == 1    tcp.flags.reset == 1	
	tcp	tcp	
	DNS	dns	
Import	udp	udp	
	tcp reset	tcp.flags.fin == 1    tcp.flags.reset == 1	🗣 Down
9	nbss	nbss	
‱ <u>C</u> lear	nbns	nbns	
	1		

Figure 10.1. The "Coloring Rules" dialog box

Once the Coloring Rules dialog box is up, there are a number of buttons you can use, depending on whether or not you have any color filters installed already.



### Note!

You will need to carefully select the order the coloring rules are listed as they are applied in order from top to bottom. So, more specific rules need to be listed before more general rules. For example, if you have a color rule for UDP before the one for DNS, the color rule for DNS will never be applied (as DNS uses UDP, so the UDP rule will match first).

If this is the first time you have used Coloring Rules, click on the New button which will bring up the Edit color filter dialog box as shown in Figure 10.2, "The "Edit Color Filter" dialog box".

Figure 10.2. The "Edit Color Filter" dialog box	Figure 10.	2. The	"Edit	Color	Filter"	dialog	box
---	------------	--------	-------	-------	---------	--------	-----

🛙 Wireshark: Edit Color Filter	
Filter	
Name: arp	
String: arp	Expression
Display Colors	
Foreground Color	Background Color
	QK 🗶 Cancel

In the Edit Color dialog box, simply enter a name for the color filter, and enter a filter string in the Filter text field. <u>Figure 10.2</u>, "The "Edit Color Filter" dialog box" shows the values **arp** and **arp** which means that the name of the color filter is **arp** and the filter will select protocols of type **arp**. Once you have entered these values, you can choose a foreground and background color for packets that match the filter expression. Click on **Foreground color...** or **Background color...** to achieve this and Wireshark will pop up the Choose foreground/background color for protocol dialog box as shown in Figure 10.3, "The "Choose color" dialog box".

Wireshark: Choose backgroun	nd color for	"arp"		
	Hue:		<u>R</u> ed:	
°	Saturation: <u>V</u> alue:		Green: Blue:	
	Color <u>N</u> ame:	#D6E7FF	]	
		<i>ф</i> ₽ <u>о</u> к		<u>Cancel</u>

Figure 10.3. The "Choose color" dialog box

Select the color you desire for the selected packets and click on OK.



#### Note!

You must select a color in the colorbar next to the colorwheel to load values into the RGB values. Alternatively, you can set the values to select the color you want.

Figure 10.4, "Using color filters with Wireshark" shows an example of several color filters being used in Wireshark. You may not like the color choices, however, feel free to choose your own.

If you are uncertain which coloring rule actually took place for a specific packet, have a look at the [Coloring Rule Name: ...] and [Coloring Rule String: ...] fields.

#### 🕂 test.pcap - Wireshark File Edit View Go Capture Analyze Statistics Help $\Theta_{\mathbf{Q}}$ 2 х e, ٩ ₽ D Ø ▼ 💠 Expression... 🏷 ⊆lear 🖋 Apply Filter: Time Protocol Info No. -Source Destination 0.000000 192.168.0.2 192.168.0.1 Broadcast 192.168.0.2 NBNS 4 1.025659 IGME 192.168.0.2 224.0.0.22 6 1.048652 239.255.255.250 UDP Source port: 3193 Destination po 192.168.0.2 8 1.055053 9 1.082038 192.168.0.1 192.168.0.2 192.168.0.2 192.168.0.25 UDP NBNS Source port: 1900 Destination p Registration NB NB10061D<00> 11194 (42 bytes on wire, 42 bytes captured) Arrival Time: Jun 22, 2004 20:02:48.863096000 [Time delta from previous packet: 0.000000000 seconds] [Time since reference or first frame: 0.000000000 seconds] Frame Number: 1 Packet Length: 42 bytes Capture Length: 42 bytes [Frame is marked: False] [Protocols in frame: eth:arp] [Coloring Rule Name: arp] [Coloring Rule String: arp] adrast (ff+ff+ff+ff+ff+ff+ 192 168 0 2 (00-0h TT Sm 010 Frame (frame), 42 bytes P: 120 D: 120 M: 0

#### Figure 10.4. Using color filters with Wireshark

# **10.4. Control Protocol dissection**

The user can control how protocols are dissected.

Each protocol has its own dissector, so dissecting a complete packet will typically involve several dissectors. As Wireshark tries to find the right dissector for each packet (using static "routes" and heuristics "guessing"), it might choose the wrong dissector in your specific case. For example, Wireshark won't know if you use a common protocol on an uncommon TCP port, e.g. using HTTP on TCP port 800 instead of the standard port 80.

There are two ways to control the relations between protocol dissectors: disable a protocol dissector completely or temporarily divert the way Wireshark calls the dissectors.

### 10.4.1. The "Enabled Protocols" dialog box

The Enabled Protocols dialog box lets you enable or disable specific protocols; all protocols are enabled by default. When a protocol is disabled, Wireshark stops processing a packet whenever that protocol is encountered.



### Note!

Disabling a protocol will prevent information about higher-layer protocols from being displayed. For example, suppose you disabled the IP protocol and selected a packet containing Ethernet, IP, TCP, and HTTP information. The Ethernet information would be displayed, but the IP, TCP and HTTP information would not - disabling IP would prevent it and the other protocols from being displayed.

To enable/disable protocols select the **Enabled Protocols...** item from the **Analyze** menu; Wireshark will pop up the "Enabled Protocols" dialog box as shown in Figure 10.5, "The "Enabled Protocols" dialog box".

Status	Protocol 🔹	Description
<b>V</b>	2dparityfec	Pro-MPEG Code of Practice #3 release 2 FEC
<b>*</b>	3COMXNS	3Com XNS Encapsulation
<b>*</b>	3GPP2 A11	3GPP2 A11
<b>*</b>	802.11 MGT	IEEE 802.11 wireless LAN management frame
<b>*</b>	802.11 Radiotap	IEEE 802.11 Radiotap Capture header
<b>*</b>	802.3 Slow protocols	Slow Protocols
<b>*</b>	9P	Plan 9 9P
<b>*</b>	AAL1	ATM AAL1
<b>V</b>	AAL3/4	ATM AAL3/4
<b>V</b>	AARP	Appletalk Address Resolution Protocol
<b>V</b>	ACAP	Application Configuration Access Protocol
1	ACP133	ACP133 Attribute Syntaxes
1	ACSE	ISO 8650-1 OSI Association Control Service
1	ACtrace	AudioCodes Trunk Trace
1	ADP	Aruba - Aruba Discovery Protocol
1	AFP	Apple Filing Protocol
1	AFS (RX)	Andrew File System (AFS)
<b>V</b>	AH	Authentication Header
<b>V</b>	AIM	AOL Instant Messenger
1	AIM Administration	AIM Administrative
<		
	Disabling a protocol prevents highe	r layer protocols from being displayed
		Enable All Disable All Invert

Figure 10.5. The "Enabled Protocols" dialog box

To disable or enable a protocol, simply click on it using the mouse or press the space bar when the protocol is highlighted. Note that typing the first few letters of the protocol name when the Enabled Protocols dialog box is active will temporarily open a search text box and automatically select the first matching protocol name (if it exists).



### Warning!

You have to use the Save button to save your settings. The OK or Apply buttons will not save your changes permanently, so they will be lost when Wireshark is closed.

You can choose from the following actions:

- 1. Enable All: Enable all protocols in the list.
- 2. Disable All: Disable all protocols in the list.
- 3. **Invert**: Toggle the state of all protocols in the list.
- 4. **OK**: Apply the changes and close the dialog box.
- 5. Apply: Apply the changes and keep the dialog box open.
- 6. Save: Save the settings to the disabled\_protos, see <u>Appendix A, Files and Folders</u> for details.
- 7. Cancel: Cancel the changes and close the dialog box.

### 10.4.2. User Specified Decodes

The "Decode As" functionality let you temporarily divert specific protocol dissections. This might be useful for example, if you do some uncommon experiments on your network.

Decode As is accessed by selecting the **Decode As...** item from the **Analyze** menu; Wireshark will pop up the "Decode As" dialog box as shown in Figure 10.6, "The "Decode As" dialog box".

Figure 10.6	. The	"Decode As"	dialog box
-------------	-------	-------------	------------

🛙 Wireshark: Decode As				
	Link Network Transport			
<ul> <li>Decode</li> </ul>		(default)	^	
		9P		
		ACAP AIM		
🔿 Do not decode		AJP13		
	TCP source (3196) 💙 port(s) as	AX4000		
		BEEP		
		BGP CAST		
Show Current		CIGI		
Clear		CIMD	~	
		oly 🗙 Close		

The content of this dialog box depends on the selected packet when it was opened.



### Warning!

These settings will be lost if you quit Wireshark or change profile, unless you save the entries in the **Show User Specified Decodes...** windows (<u>Section 10.4.3</u>, "<u>Show User Specified Decodes</u>").

- 1. **Decode**: Decode packets the selected way.
- 2. Do not decode: Do not decode packets the selected way.
- 3. Link/Network/Transport: Specify the network layer at which "Decode As" should take place. Which of these pages are available depends on the content of the selected packet when this dialog box is opened.
- 4. Show Current: Open a dialog box showing the current list of user specified decodes.
- 5. OK: Apply the currently selected decode and close the dialog box.
- 6. Apply: Apply the currently selected decode and keep the dialog box open.
- 7. Cancel: Cancel the changes and close the dialog box.

### 10.4.3. Show User Specified Decodes

This dialog box shows the currently active user specified decodes. These entries can be saved into current profile for later session.

🔽 Wiresha	rk: Decode /	As: Show	-OX)
Table Value In	nitial Curren	t	
TCP port 8081 (	none) HTTP		
TCP port 3196 (	none) AIM		
Help	<u>o</u> k	Save	<u>C</u> lear

Figure 10.7. The "Decode As: Show" dialog box

- 1. **OK**: Close this dialog box.
- 2. Save: Save the entries in the table into current profile.
- 3. Clear: Removes all user specified decodes without updating the profile.

## **10.5. Preferences**

There are a number of preferences you can set. Simply select the **Preferences...** menu item from the **Edit** menu; and Wireshark will pop up the Preferences dialog box as shown in Figure 10.8, "The preferences dialog box", with the "User Interface" page as default. On the left side is a tree where you can select the page to be shown.



#### Note!

Preference settings are added frequently. For a recent explanation of the preference pages and their settings have a look at the **Wireshark Wiki Preferences page** at <u>http://</u>wiki.wireshark.org/Preferences.



#### Warning!

The OK or Apply button will not save the preference settings, you'll have to save the settings by clicking the Save button.

- The **OK** button will apply the preferences settings and close the dialog.
- The Apply button will apply the preferences settings and keep the dialog open.
- The **Save** button will apply the preferences settings, save the settings on the hard disk and keep the dialog open.

• The **Cancel** button will restore all preferences settings to the last saved state.

Wireshark: Preference	es	
🗖 User Interface	User Interface	
Layout	Packet list selection mode:	Selects 🗸
Columns	Protocol tree selection mode:	Selects 🗸
Font Colors		
Capture	Save window position:	
Printing	Save window size:	
Name Resolution	Save maximized state:	
<ul> <li>Protocols</li> </ul>	Save maximized state.	
	Open a console window	Automatic (advanced user) 👻
	"File Open" dialog behavior:	Remember last directory
	Directory:	
	"File Open" preview timeout:	3
	"Open Recent" max. list entries:	20
	Ask for unsaved capture files:	
	Wrap to end/beginning of file during a find:	
🔯 <u>H</u> elp		

Figure 10.8. The preferences dialog box

### **10.5.1. Interface Options**

In the Capture preferences it is possible to configure several options for the interfaces available on your computer. Select the **Capture** pane and press the Interfaces: **Edit** button. In this window it is possible to change the default link-layer header type for the interface, add a comment or choose to hide a interface from other parts of the program.

#### Figure 10.9. The interface options dialog box

Į	1	Wireshark: Preference	s: Interfa	e Options - Profile: Defau	ılt	_ <b>-</b> ×
	Interface	S				
	Device	Description		Default link-layer	Comment	Hide?
	eth0			Ethernet	Internet	No
	any	Pseudo-device that captures on all	interfaces	Linux cooked-mode capture		No
	lo			Ethernet	Local	No
	Propertie	Device: Description: Default link-layer header type: Comment:	eth0 Ethernet		\$	]
	<u>∂ H</u> el	Hide interface?:			<b>S</b> Canc	:el <u>о</u> к

Each row contains options for each interface available on your computer.

• **Device**: the device name provided by the operating system.

- **Description**: provided by the operating system.
- **Default link-layer**: each interface may provide several link-layer header types. The default link-layer chosen here is the one used when you first start Wireshark. It is also possible to change this value in <u>Section 4.5, "The "Capture Options" dialog box"</u> when you start a capture. For a detailed description, see <u>Section 4.11, "Link-layer header type"</u>.
- **Comment**: a user provided description of the interface. This comment will be used as a description instead of the operating system description.
- Hide?: enable this option to hide the interface from other parts of the program.

# **10.6. Configuration Profiles**

Configuration Profiles can be used to configure and use more than one set of preferences and configurations. Select the **Configuration Profiles...** menu item from the **Edit** menu, or simply press Shift-Ctrl-A; and Wireshark will pop up the Configuration Profiles dialog box as shown in Figure 10.10, "The configuration profiles dialog box". It is also possible to click in the "Profile" part of the statusbar to popup a menu with available Configuration Profiles (Figure 3.22, "The Statusbar with a configuration profile menu").

Configuration files stored in the Profiles:

- Preferences (preferences) (<u>Section 10.5, "Preferences</u>")
- Capture Filters (cfilters) (Section 6.6, "Defining and saving filters")
- Display Filters (dfilters) (Section 6.6, "Defining and saving filters")
- Coloring Rules (colorfilters) (Section 10.3, "Packet colorization")
- Disabled Protocols (disabled\_protos) (Section 10.4.1, "The "Enabled Protocols" dialog box")
- User Accessible Tables:
  - Custom HTTP headers (custom\_http\_header\_fields)
  - Custom IMF headers (imf\_header\_fields)
  - Custom LDAP AttributeValue types (custom\_ldap\_attribute\_types)
  - Display Filter Macros (dfilter\_macros) (Section 10.8, "Display Filter Macros")
  - ESS Category Attributes (ess\_category\_attributes) (Section 10.9, "ESS Category Attributes")
  - GeoIP Database Paths (geoip\_db\_paths) (<u>Section 10.10, "GeoIP Database Paths</u>")
  - K12 Protocols (k12\_protos) (Section 10.19, "Tektronix K12xx/15 RF5 protocols Table")
  - Object Identifier Names and Associated Syntaxes (Section 10.12, "Object Identifiers")
  - PRES Users Context List (pres\_context\_list) (Section 10.13, "PRES Users Context List")
  - SCCP Users Table (sccp\_users) (<u>Section 10.14, "SCCP users Table</u>")
  - SNMP Enterprise Specific Trap Types (snmp\_specific\_traps) (Section 10.17, "SNMP Enterprise Specific Trap Types")

- SNMP Users (snmp\_users) (Section 10.18, "SNMP users Table")
- User DLTs Table (user\_dlts) (Section 10.20, "User DLTs protocol table")
- IKEv2 decryption table (ikev2\_decryption\_table) (Section 10.11, "IKEv2 decryption table")
- Changed dissector assignments (decode\_as\_entries), which can be set in **Decode As...** dialog box (Section 10.4.2, "User Specified Decodes"), and further saved in the User Specified Decodes... window (Section 10.4.3, "Show User Specified Decodes").
- Some recent settings (recent), such as pane sizes in the Main window (<u>Section 3.3, "The Main window</u>"), column widths in the packet list (<u>Section 3.18, "The "Packet List" pane</u>"), all selections in the "View" menu (<u>Section 3.7, "The "View" menu</u>") and the last directory navigated to in the File Open dialog.



#### **Other configurations**

All other configurations are stored in the personal configuration folder, and are common to all profiles.

#### Figure 10.10. The configuration profiles dialog box

<ul> <li>Wireshar</li> </ul>	k: Configuration Profiles - Profile: Wireless 💶 🔳 🗙
Edit	Configuration Profiles
	Default
New	Tactical analysis
	Compare traffic
	Only IP and TCP
	Wireless
Copy	No reassembly
<u>O</u> elete	
Properties	]
Profile name:	Wireless
(?) <u>H</u> elp	Apply Scancel VC

New	This button adds a new profile to the profiles list. The name of the created profile is "New profile" and can be changed in the Properties field.
Сору	This button adds a new profile to the profiles list, copying all configuration from the profile currently selected in the list. The name of the created profile is the same as the copied profile, with the text "(copy)" applied. The name can be changed in the Properties field.
Delete	This button deletes the selected profile, including all configuration files used in this profile. It is not possible to delete the "Default" profile.
Configuration Profiles	You can select a configuration profile from this list (which will fill in the profile name in the fields down at the bottom of the dialog box).

#### Profile name:

You can change the name of the currently selected profile here.



### Used as a folder name

The profile name will be used as a folder name in the configured "Personal configurations" folder. If adding multiple profiles with the same name, only one profile will be created.



### **Illegal characters**

On Windows the profile name cannot start or end with a period (.), and cannot contain any of the following characters: \/:\*?''<>|

On Unix the profile name cannot contain the '/' character.

ОК	This button saves all changes, applies the selected profile and closes the dialog.
Apply	This button saves all changes, applies the selected profile and keeps the dialog open.
Cancel	Close this dialog. This will discard unsaved settings, new profiles will not be added and deleted profiles will not be deleted.
Help	Show this help page.

## 10.7. User Table

The User Table editor is used for managing various tables in wireshark. Its main dialog works very similarly to that of <u>Section 10.3</u>, "Packet colorization".

# **10.8. Display Filter Macros**

Display Filter Macros are a mechanism to create shortcuts for complex filters. For example defining a display filter macro named **tcp\_conv** whose text is ( (**ip.src** == **\$1** and **ip.dst** == **\$2** and **tcp.srcport** == **\$3** and **tcp.dstport** == **\$4** or (**ip.src** == **\$2** and **ip.dst** == **\$1** and **tcp.srcport** == **\$4** and **tcp.dstport** == **\$3**) would allow to use a display filter like **\${tcp\_conv:10.1.1.2;10.1.1.3;1200;1400}** instead of typing the whole filter.

Display Filter Macros can be managed with a Section 10.7, "User Table" by selecting Analyze  $\rightarrow$  Display Filter Macros from the menu. The User Table has the following fields

Name The name of the macro.

**Text** The replacement text for the macro it uses \$1, \$2, \$3, ... as the input arguments.

# **10.9. ESS Category Attributes**

Wireshark uses this table to map ESS Security Category attributes to textual representations. The values to put in this table are usually found in a <u>XML SPIF</u>, which is used for defining security labels.

This table is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

Value The value (Label And Cert Value) representing the Category.

**Name** The textual representation for the value.

## **10.10. GeoIP Database Paths**

If your copy of Wireshark supports <u>MaxMind's</u> GeoIP library, you can use their databases to match IP addresses to countries, cites, autonomous system numbers, ISPs, and other bits of information. Some databases are <u>available at no cost</u>, while others require a licensing fee. See <u>the MaxMind web site</u> for more information.

This table is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

**Database pathname** This specifies a directory containing GeoIP data files. Any files beginning with Geo and ending with .dat will be automatically loaded. A total of 8 files can be loaded.

The locations for your data files are up to you, but /usr/share/GeoIP (Linux), C:\GeoIP (Windows), C:\Program Files\Wireshark \GeoIP (Windows) might be good choices.

# **10.11. IKEv2 decryption table**

Wireshark can decrypt Encrypted Payloads of IKEv2 (Internet Key Exchange version 2) packets if necessary information is provided. Note that you can decrypt only IKEv2 packets with this feature. If you want to decrypt IKEv1 packets or ESP packets, use Log Filename setting under ISAKMP protocol preference or settings under ESP protocol preference respectively.

This table is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

Initiator's SPI	Initiator's SPI of the IKE_SA. This field takes hexadecimal string without "0x" prefix and the length must be 16 hex chars (represents 8 octets).
Responder's SPI	Responder's SPI of the IKE_SA. This field takes hexadecimal string without "0x" prefix and the length must be 16 hex chars (represents 8 octets).
SK_ei	Key used to encrypt/decrypt IKEv2 packets from initiator to responder. This field takes hexadecimal string without "0x" prefix and its length must meet the requirement of the encryption algorithm selected.
SK_er	Key used to encrypt/decrypt IKEv2 packets from responder to initiator. This field takes hexadecimal string without "0x" prefix and its length must meet the requirement of the encryption algorithm selected.
Encryption Algorithm	Encryption algorithm of the IKE_SA.
SK_ai	Key used to calculate Integrity Checksum Data for IKEv2 packets from responder to initiator. This field takes hexadecimal string without "0x" prefix and its length must meet the requirement of the integrity algorithm selected.

SK\_ar

Key used to calculate Integrity Checksum Data for IKEv2 packets from initiator to responder. This field takes hexadecimal string without "0x" prefix and its length must meet the requirement of the integrity algorithm selected.

**Integrity Algorithm** Integrity algorithm of the IKE\_SA.

# **10.12. Object Identifiers**

Many protocols that use ASN.1 use Object Identifiers (OIDs) to uniquely identify certain pieces of information. In many cases, they are used in an extension mechanism so that new object identifiers (and associated values) may be defined without needing to change the base standard.

Whilst Wireshark has knowledge about many of the OIDs and the syntax of their associated values, the extensibility means that other values may be encountered.

Wireshark uses this table to allow the user to define the name and syntax of Object Identifiers that Wireshark does not know about (for example, a privately defined X.400 extension). It also allows the user to override the name and syntax of Object Identifiers that Wireshark does know about (e.g. changing the name "id-at-countryName" to just "c").

This table is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

- **OID** The string representation of the Object Identifier e.g. "2.5.4.6".
- Name The name that should be displayed by Wireshark when the Object Identifier is dissected e.g. ("c");
- **Syntax** The syntax of the value associated with the Object Identifier. This must be one of the syntaxes that Wireshark already knows about (e.g. "PrintableString").

# **10.13. PRES Users Context List**

Wireshark uses this table to map a presentation context identifier to a given object identifier when the capture does not contain a PRES package with a presentation context definition list for the conversation.

This table is handled by an Section 10.7, "User Table" with the following fields.

- **Context Id** An Integer representing the presentation context identifier for which this association is valid.
- **Syntax Name OID** The object identifier representing the abstract syntax name, which defines the protocol that is carried over this association.

### 10.14. SCCP users Table

Wireshark uses this table to map specific protocols to a certain DPC/SSN combination for SCCP.

This table is handled by an Section 10.7, "User Table" with the following fields.

Network Indicator	An Integer representing the network indicator for which this association is valid.
Called DPCs	An range of integers representing the dpcs for which this association is valid.

Called SSNs An range of integers representing the ssns for which this association is valid.

**User protocol** The protocol that is carried over this association

# 10.15. SMI (MIB and PIB) Modules

If your copy of Wireshark supports libSMI, you can specify a list of MIB and PIB modules here. The COPS and SNMP dissectors can use them to resolve OIDs.

Module name The name of the module, e.g. IF-MIB.

# 10.16. SMI (MIB and PIB) Paths

If your copy of Wireshark supports libSMI, you can specify one or more paths to MIB and PIB modules here.

Directory name

A module directory, e.g. /usr/local/snmp/mibs. Wireshark automatically uses the standard SMI path for your system, so you usually don't have to add anything here.

# **10.17. SNMP Enterprise Specific Trap Types**

Wireshark uses this table to map specific-trap values to user defined descriptions in a Trap PDU. The description is shown in the packet details specific-trap element.

This table is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

Enterprise OID	The object identifier representing the object generating the trap.
Trap Id	An Integer representing the specific-trap code.
Description	The description to show in the packet details.

## **10.18. SNMP** users Table

Wireshark uses this table to verify authentication and to decrypt encrypted SNMPv3 packets.

This table is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

Engine ID	If given this entry will be used only for packets whose engine id is this. This field takes an hexadecimal string in the form 0102030405.
Username	This is the userName. When a single user has more than one password for different SNMP-engines the first entry to match both is taken, if you need a catch all engine-id (empty) that entry should be the last one.
Authentication model	Which auth model to use (either "MD5" or "SHA1").
Password	The authentication password. Use '\xDD' for unprintable characters. An hexadecimal password must be entered as a sequence of '\xDD' characters. For example the hex password 010203040506 must be entered as '\x01\x02\x03\x04\x05\x06'.
Privacy protocol	Which encryption algorithm to use (either "DES" or "AES").

**Privacy password** 

The privacy password. Use '\xDD' for unprintable characters. An hexadecimal password must be entered as a sequence of '\xDD' characters. For example the hex password 010203040506 must be entered as '\x01\x02\x03\x04\x05\x06'.

# 10.19. Tektronix K12xx/15 RF5 protocols Table

The Tektronix K12xx/15 rf5 file format uses helper files (\*.stk) to identify the various protocols that are used by a certain interface. Wireshark doesn't read these stk files, it uses a table that helps it identify which lowest layer protocol to use.

Stk file to protocol matching is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

- Match stringA partial match for an stk filename, the first match wins, so if you have a specific case<br/>and a general one the specific one must appear first in the list.
- **Protocol** This is the name of the encapsulating protocol (the lowest layer in the packet data) it can be either just the name of the protocol (e.g. mtp2, eth\_witoutfcs, sscf-nni) or the name of the encapsulation protocol and the "application" protocol over it separated by a colon (e.g sscop:sscf-nni, sscop:alcap, sscop:nbap, ...)

## **10.20. User DLTs protocol table**

When a pcap file uses one of the user DLTs (147 to 162) wireshark uses this table to know which protocol(s) to use for each user DLT.

This table is handled by an <u>Section 10.7, "User Table"</u> with the following fields.

DLT	One of the user dlts.
Payload protocol	This is the name of the payload protocol (the lowest layer in the packet data). (e.g. "eth" for ethernet, "ip" for IPv4)
Header size	If there is a header protocol (before the payload protocol) this tells which size this header is. A value of 0 disables the header protocol.
Header protocol	The name of the header protocol to be used (uses "data" as default).
Trailer size	If there is a trailer protocol (after the payload protocol) this tells which size this trailer is. A value of 0 disables the trailer protocol.
Trailer protocol	The name of the trailer protocol to be used (uses "data" as default).

# Chapter 11. Lua Support in Wireshark

# 11.1. Introduction

Wireshark has an embedded Lua interpreter. Lua is a powerful light-weight programming language designed for extending applications. Lua is designed and implemented by a team at PUC-Rio, the Pontifical Catholic University of Rio de Janeiro in Brazil. Lua was born and raised at Tecgraf, the Computer Graphics Technology Group of PUC-Rio, and is now housed at Lua.org. Both Tecgraf and Lua.org are laboratories of the Department of Computer Science.

In Wireshark Lua can be used to write dissectors and taps.

Wireshark's Lua interpreter starts by loading **init.lua** that is located in the global configuration directory of Wireshark. Lua is enabled by default. To disable Lua the line variable **disable\_lua** should be set to **true** in **init.lua**.

After loading **init.lua** from the data directory if Lua is enabled Wireshark will try to load a file named **init.lua** in the user's directory.

Wireshark will also load all files with **.lua** suffix from both the global and the personal plugins directory.

The command line option -X lua\_script:<file.lua> can be used to load Lua scripts as well.

The Lua code will be executed once after all the protocol dissectors have being initialized and before reading any file.

# 11.2. Example of Dissector written in Lua

```
do
        local p_multi = Proto("multi","MultiProto");
        local vs_protos = {
                [2] = "mtp2",
                [3] = "mtp3",
                [4] = "alcap"
                [5] = "h248",
                [6] = "ranap"
                [7] = "rnsap",
                [8] = "nbap"
        }
        local f_proto = ProtoField.uint8("multi.protocol", "Protocol", base.DEC, vs_protos)
        local f_dir = ProtoField.uint8("multi.direction","Direction",base.DEC, { [1] = "incoming", [0] =
        local f_text = ProtoField.string("multi.text","Text")
        p_multi.fields = { f_proto, f_dir, f_text }
        local data_dis = Dissector.get("data")
        local protos = {
                [2] = Dissector.get("mtp2"),
                [3] = Dissector.get("mtp3"),
                [4] = Dissector.get("alcap"),
                [5] = Dissector.get("h248"),
                [6] = Dissector.get("ranap"),
                [7] = Dissector.get("rnsap"),
                [8] = Dissector.get("nbap"),
```

```
[9] = Dissector.get("rrc"),
        [10] = DissectorTable.get("sctp.ppi"):get_dissector(3), -- m3ua
        [11] = DissectorTable.get("ip.proto"):get_dissector(132), -- sctp
}
function p_multi.dissector(buf,pkt,root)
        local t = root:add(p_multi,buf(0,2))
        t:add(f_proto,buf(0,1))
        t:add(f_dir,buf(1,1))
        local proto_id = buf(0,1):uint()
        local dissector = protos[proto_id]
        if dissector ~= nil then
                dissector:call(buf(2):tvb(),pkt,root)
        elseif proto_id < 2 then
                t:add(f_text,buf(2))
                -- pkt.cols.info:set(buf(2,buf:len() - 3):string())
        else
                data_dis:call(buf(2):tvb(),pkt,root)
        end
```

end

local wtap\_encap\_table = DissectorTable.get("wtap\_encap")
local udp\_encap\_table = DissectorTable.get("udp.port")

```
wtap_encap_table:add(wtap.USER15,p_multi)
wtap_encap_table:add(wtap.USER12,p_multi)
udp_encap_table:add(7555,p_multi)
```

end

### 11.3. Example of Listener written in Lua

```
-- This program will register a menu that will open a window with a count of occurrences
-- of every address in the capture
do
local function menuable_tap()
  -- Declare the window we will use
 local tw = TextWindow.new("Address Counter")
  -- This will contain a hash of counters of appearances of a certain address
 local ips = {}
  -- this is our tap
 local tap = Listener.new();
  function remove()
   -- this way we remove the listener that otherwise will remain running indefinitely
  tap:remove();
 end
  -- we tell the window to call the remove() function when closed
 tw:set atclose(remove)
  -- this function will be called once for each packet
  function tap.packet(pinfo,tvb)
   local src = ips[tostring(pinfo.src)] or 0
  local dst = ips[tostring(pinfo.dst)] or 0
   ips[tostring(pinfo.src)] = src + 1
```

```
ips[tostring(pinfo.dst)] = dst + 1
 end
  -- this function will be called once every few seconds to update our window
 function tap.draw(t)
  tw:clear()
  for ip,num in pairs(ips) do
   tw:append(ip .. "\t" .. num .. "\n");
  end
 end
 -- this function will be called whenever a reset is needed
 -- e.g. when reloading the capture file
 function tap.reset()
  tw:clear()
  ips = {}
 end
end
-- using this function we register our function
-- to be called when the user selects the Tools->Test->Packets menu
register_menu("Test/Packets", menuable_tap, MENU_TOOLS)
end
```

# 11.4. Wireshark's Lua API Reference Manual

This Part of the User Guide describes the Wireshark specific functions in the embedded Lua.

# 11.5. Saving capture files

### 11.5.1. Dumper

### 11.5.1.1. Dumper.new(filename, [filetype], [encap])

Creates a file to write packets. Dumper:new\_for\_current() will probably be a better choice.

#### 11.5.1.1.1. Arguments

filename	The name of the capture file to be created
filetype (optional)	The type of the file to be created
encap (optional)	The encapsulation to be used in the file to be created

#### 11.5.1.1.2. Returns

The newly created Dumper object

#### 11.5.1.1.3. Errors

• Not every filetype handles every encap

### 11.5.1.2. dumper:close()

Closes a dumper

### 11.5.1.2.1. Errors

• Cannot operate on a closed dumper

### 11.5.1.3. dumper:flush()

Writes all unsaved data of a dumper to the disk.

### 11.5.1.4. dumper:dump(timestamp, pseudoheader, bytearray)

Dumps an arbitrary packet. Note: Dumper:dump\_current() will fit best in most cases.

#### 11.5.1.4.1. Arguments

timestamp	The absolute timestamp the packet will have
pseudoheader	The Pseudoheader to use.
bytearray	the data to be saved

### 11.5.1.5. dumper:new\_for\_current([filetype])

Creates a capture file using the same encapsulation as the one of the cuurrent packet

#### 11.5.1.5.1. Arguments

filetype (optional) The file type. Defaults to pcap.

#### 11.5.1.5.2. Returns

The newly created Dumper Object

#### 11.5.1.5.3. Errors

• Cannot be used outside a tap or a dissector

### 11.5.1.6. dumper:dump\_current()

Dumps the current packet as it is.

### 11.5.1.6.1. Errors

• Cannot be used outside a tap or a dissector

### 11.5.2. PseudoHeader

A pseudoheader to be used to save captured frames.

### 11.5.2.1. PseudoHeader.none()

Creates a "no" pseudoheader.

#### 11.5.2.1.1. Returns

A null pseudoheader

### 11.5.2.2. PseudoHeader.eth([fcslen])

Creates an ethernet pseudoheader

#### 11.5.2.2.1. Arguments

fcslen (optional) The fcs length

### 11.5.2.2.2. Returns

The ethernet pseudoheader

# 11.5.2.3. PseudoHeader.atm([aal], [vpi], [vci], [channel], [cells], [aal5u2u], [aal5len])

Creates an ATM pseudoheader

### 11.5.2.3.1. Arguments

aal (optional)	AAL number
vpi (optional)	VPI
vci (optional)	VCI
channel (optional)	Channel
cells (optional)	Number of cells in the PDU
aal5u2u (optional)	AAL5 User to User indicator
aal5len (optional)	AAL5 Len

### 11.5.2.3.2. Returns

The ATM pseudoheader

### 11.5.2.4. PseudoHeader.mtp2()

Creates an MTP2 PseudoHeader

### 11.5.2.4.1. Returns

The MTP2 pseudoheader

# 11.6. Obtaining dissection data

### 11.6.1. Field

A Field extractor to to obtain field values.

### 11.6.1.1. Field.new(fieldname)

Create a Field extractor

#### 11.6.1.1.1. Arguments

fieldname The filter name of the field (e.g. ip.addr)

#### 11.6.1.1.2. Returns

The field extractor

#### 11.6.1.1.3. Errors

• A Field extractor must be defined before Taps or Dissectors get called

### 11.6.1.2. field:\_\_\_call()

Obtain all values (see FieldInfo) for this field.

### 11.6.1.2.1. Returns

All the values of this field

### 11.6.1.2.2. Errors

• Fields cannot be used outside dissectors or taps

### 11.6.2. FieldInfo

An extracted Field

### 11.6.2.1. fieldinfo:\_\_len()

Obtain the Length of the field

### 11.6.2.2. fieldinfo:\_\_unm()

Obtain the Offset of the field

### 11.6.2.3. fieldinfo: \_\_call()

Obtain the Value of the field

### 11.6.2.4. fieldinfo:\_\_tostring()

The string representation of the field

### 11.6.2.5. fieldinfo:\_\_\_eq()

Checks whether lhs is within rhs

### 11.6.2.5.1. Errors

• Data source must be the same for both fields

### 11.6.2.6. fieldinfo:\_\_le()

Checks whether the end byte of lhs is before the end of rhs

## 11.6.2.7. fieldinfo:\_\_lt()

Checks whether the end byte of rhs is before the beginning of rhs

### 11.6.2.7.1. Errors

• Data source must be the same for both fields

## 11.6.2.8. fieldinfo.name

The name of this field

## 11.6.2.9. fieldinfo.label

The string representing this field

## 11.6.2.10. fieldinfo.value

The value of this field

## 11.6.2.11. fieldinfo.len

The length of this field

## 11.6.2.12. fieldinfo.offset

The offset of this field

# **11.6.3. Non Method Functions**

## 11.6.3.1. all\_field\_infos()

Obtain all fields from the current tree

### 11.6.3.1.1. Errors

• Cannot be called outside a listener or dissector

# 11.7. GUI support

# 11.7.1. ProgDlg

Manages a progress bar dialog.

## 11.7.1.1. ProgDlg.new([title], [task])

Creates a new TextWindow.

### 11.7.1.1.1. Arguments

title (optional)	Title of the new window, defaults to "Progress".
task (optional)	Current task, defaults to "".

### 11.7.1.1.2. Returns

The newly created TextWindow object.

## 11.7.1.2. progdlg:update(progress, [task])

Appends text

### 11.7.1.2.1. Arguments

progress	Part done ( e.g. 0.75 ).
task (optional)	Current task, defaults to "".

### 11.7.1.2.2. Errors

- GUI not available
- Cannot be called for something not a ProgDlg
- Progress value out of range (must be between 0.0 and 1.0)

## 11.7.1.3. progdlg:stopped()

Checks wheher the user has pressed the stop button.

### 11.7.1.3.1. Returns

true if the user has asked to stop the progress.

### 11.7.1.3.2. Errors

• Cannot be called for something not a ProgDlg

## 11.7.1.4. progdlg:close()

Appends text

### 11.7.1.4.1. Errors

- GUI not available
- Cannot be called for something not a ProgDlg

# 11.7.2. TextWindow

Manages a text window.

## 11.7.2.1. TextWindow.new([title])

Creates a new TextWindow.

### 11.7.2.1.1. Arguments

title (optional)

Title of the new window.

### 11.7.2.1.2. Returns

The newly created TextWindow object.

### 11.7.2.1.3. Errors

• GUI not available

## 11.7.2.2. textwindow:set\_atclose(action)

Set the function that will be called when the window closes

### 11.7.2.2.1. Arguments

action A function to be executed when the user closes the window

### 11.7.2.2.2. Returns

The TextWindow object.

### 11.7.2.2.3. Errors

- GUI not available
- Cannot be called for something not a TextWindow

## 11.7.2.3. textwindow:set(text)

Sets the text.

### 11.7.2.3.1. Arguments

text The text to be used.

### 11.7.2.3.2. Returns

The TextWindow object.

### 11.7.2.3.3. Errors

- GUI not available
- Cannot be called for something not a TextWindow
- Expired TextWindow

## 11.7.2.4. textwindow:append(text)

Appends text

### 11.7.2.4.1. Arguments

text The text to be appended

### 11.7.2.4.2. Returns

The TextWindow object.

### 11.7.2.4.3. Errors

- GUI not available
- Cannot be called for something not a TextWindow
- Expired TextWindow

## 11.7.2.5. textwindow:prepend(text)

Prepends text

### 11.7.2.5.1. Arguments

text The text to be appended

### 11.7.2.5.2. Returns

The TextWindow object.

### 11.7.2.5.3. Errors

- GUI not available
- Cannot be called for something not a TextWindow
- Expired TextWindow

## 11.7.2.6. textwindow:clear()

Erases all text in the window.

### 11.7.2.6.1. Returns

The TextWindow object.

### 11.7.2.6.2. Errors

- GUI not available
- Cannot be called for something not a TextWindow
- Expired TextWindow

## 11.7.2.7. textwindow:get\_text()

Get the text of the window

### 11.7.2.7.1. Returns

The TextWindow's text.

### 11.7.2.7.2. Errors

• GUI not available

- Cannot be called for something not a TextWindow
- Expired TextWindow

## 11.7.2.8. textwindow:set\_editable([editable])

Make this window editable

### 11.7.2.8.1. Arguments

editable (optional) A boolean flag, defaults to true

### 11.7.2.8.2. Returns

The TextWindow object.

### 11.7.2.8.3. Errors

- GUI not available
- Cannot be called for something not a TextWindow
- Expired TextWindow

## 11.7.2.9. textwindow:add\_button(label, function)

### 11.7.2.9.1. Arguments

labelThe label of the button

function The function to be called when clicked

### 11.7.2.9.2. Returns

The TextWindow object.

### 11.7.2.9.3. Errors

- GUI not available
- Cannot be called for something not a TextWindow
- Expired TextWindow

# **11.7.3. Non Method Functions**

## 11.7.3.1. gui\_enabled()

Checks whether the GUI facility is enabled.

### 11.7.3.1.1. Returns

A boolean: true if it is enabled, false if it isn't.

## 11.7.3.2. register\_menu(name, action, [group])

Register a menu item in one of the main menus.

### 11.7.3.2.1. Arguments

name	The name of the menu item. The submenus are to be separated by '/'s. (string)
action	The function to be called when the menu item is invoked. (function taking no arguments and returning nothing)
group (optional)	The menu group into which the menu item is to be inserted. If omitted, defaults to MENU_STAT_GENERIC. One of: MENU_STAT_UNSORTED (Statistics), MENU_STAT_GENERIC (Statistics, first section), MENU_STAT_CONVERSATION (Statistics/ Conversation List), MENU_STAT_ENDPOINT (Statistics/Endpoint List), MENU_STAT_RESPONSE (Statistics/Service Response Time), MENU_STAT_TELEPHONY (Telephony), MENU_ANALYZE (Analyze), MENU_ANALYZE_CONVERSATION (Analyze/Conversation Filter), MENU_TOOLS_UNSORTED (Tools). (number)

## 11.7.3.3. new\_dialog(title, action, ...)

Pops up a new dialog

### 11.7.3.3.1. Arguments

title Title of the dialog's window.
-------------------------------------

- action Action to be performed when OKd.
  - A series of strings to be used as labels of the dialog's fields

### 11.7.3.3.2. Errors

- GUI not available
- At least one field required
- All fields must be strings

## 11.7.3.4. retap\_packets()

Rescan all packets and just run taps - don't reconstruct the display.

## 11.7.3.5. copy\_to\_clipboard(text)

Copy a string into the clipboard

### 11.7.3.5.1. Arguments

text The string to be copied into the clipboard.

## 11.7.3.6. open\_capture\_file(filename, filter)

Open and display a capture file

### 11.7.3.6.1. Arguments

filename The name of the file to be opened.

filter A filter to be applied as the file gets opened.

## 11.7.3.7. set\_filter(text)

Set the main filter text

### 11.7.3.7.1. Arguments

text The filter's text.

## 11.7.3.8. set\_color\_filter\_slot(row, text)

Set packet-coloring rule for the current session

### 11.7.3.8.1. Arguments

row The index of the desired color in the temporary coloring rules list

text Display filter for selecting packets to be colorized

## 11.7.3.9. apply\_filter()

Apply the filter in the main filter box

## 11.7.3.10. reload()

Reload the current capture file

### 11.7.3.11. browser\_open\_url(url)

Open an url in a browser

### 11.7.3.11.1. Arguments

url The url.

## 11.7.3.12. browser\_open\_data\_file(filename)

Open an file in a browser

### 11.7.3.12.1. Arguments

filename The url.

# **11.8.** Post-dissection packet analysis

## 11.8.1. Listener

A Listener, is called once for every packet that matches a certain filter or has a certain tap. It can read the tree, the packet's Tvb eventually the tapped data but it cannot add elements to the tree.

## 11.8.1.1. Listener.new([tap], [filter])

Creates a new Listener listener

### 11.8.1.1.1. Arguments

tap (optional)	The name of this tap
filter (optional)	A filter that when matches the tap.packet function gets called (use nil to be called for every packet)

### 11.8.1.1.2. Returns

The newly created Listener listener object

### 11.8.1.1.3. Errors

• tap registration error

## 11.8.1.2. listener:remove()

Removes a tap listener

## 11.8.1.3. listener.packet

A function that will be called once every packet matches the Listener listener filter. function tap.packet(pinfo,tvb,userdata) ... end

### 11.8.1.4. listener.draw

A function that will be called once every few seconds to redraw the gui objects in tshark this funtion is called oly at the very end of the capture file. function tap.draw(userdata) ... end

### 11.8.1.5. listener.reset

A function that will be called at the end of the capture run. function tap.reset(userdata) ... end

# 11.9. Obtaining packet information

## 11.9.1. Address

Represents an address

## 11.9.1.1. Address.ip(hostname)

Creates an Address Object representing an IP address.

### 11.9.1.1.1. Arguments

hostname The address or name of the IP host.

### 11.9.1.1.2. Returns

The Address object

## 11.9.1.2. address:\_\_tostring()

### 11.9.1.2.1. Returns

The string representing the address.

## 11.9.1.3. address:\_\_\_eq()

Compares two Addresses

## 11.9.1.4. address:\_\_le()

Compares two Addresses

## 11.9.1.5. address:\_\_\_lt()

Compares two Addresses

# 11.9.2. Column

A Column in the packet list

## 11.9.2.1. column:\_\_tostring()

### 11.9.2.1.1. Returns

A string representing the column

## 11.9.2.2. column:clear()

Clears a Column

## 11.9.2.3. column:set(text)

Sets the text of a Column

### 11.9.2.3.1. Arguments

text The text to which to set the Column

## 11.9.2.4. column:append(text)

Appends text to a Column

### 11.9.2.4.1. Arguments

text The text to append to the Column

## 11.9.2.5. column:preppend(text)

Prepends text to a Column

### 11.9.2.5.1. Arguments

text The text to prepend to the Column

## 11.9.3. Columns

The Columns of the packet list.

## 11.9.3.1. columns:\_\_tostring()

### 11.9.3.1.1. Returns

The string "Columns", no real use, just for debugging purposes.

## 11.9.3.2. columns: \_\_newindex(column, text)

Sets the text of a specific column

### 11.9.3.2.1. Arguments

column The name of the column to set

text The text for the column

## 11.9.4. NSTime

NSTime represents a nstime\_t. This is an object with seconds and nano seconds.

## 11.9.4.1. NSTime.new([seconds], [nseconds])

Creates a new NSTime object

### 11.9.4.1.1. Arguments

seconds (optional)	Seconds
--------------------	---------

nseconds (optional) Nano seconds

### 11.9.4.1.2. Returns

The new NSTime object.

## 11.9.4.2. nstime: \_\_tostring()

### 11.9.4.2.1. Returns

The string representing the nstime.

## 11.9.4.3. nstime: \_\_add()

Calculates the sum of two NSTimes

## 11.9.4.4. nstime:\_\_sub()

Calculates the diff of two NSTimes

## 11.9.4.5. nstime:\_\_unm()

Calculates the negative NSTime

## 11.9.4.6. nstime:\_\_\_eq()

Compares two NSTimes

### 11.9.4.6.1. Errors

• Data source must be the same for both fields

## 11.9.4.7. nstime:\_\_le()

Compares two NSTimes

### 11.9.4.7.1. Errors

• Data source must be the same for both fields

## 11.9.4.8. nstime:\_\_lt()

Compares two NSTimes

### 11.9.4.8.1. Errors

• Data source must be the same for both fields

## 11.9.4.9. nstime.secs

The NSTime seconds

## 11.9.4.10. nstime.nsecs

The NSTime nano seconds

# 11.9.5. Pinfo

Packet information

## 11.9.5.1. pinfo.number

The number of this packet in the current file

## 11.9.5.2. pinfo.len

The length of the frame

## 11.9.5.3. pinfo.caplen

The captured length of the frame

## 11.9.5.4. pinfo.abs\_ts

When the packet was captured

## 11.9.5.5. pinfo.rel\_ts

Number of seconds passed since beginning of capture

## 11.9.5.6. pinfo.delta\_ts

Number of seconds passed since the last captured packet

## 11.9.5.7. pinfo.delta\_dis\_ts

Number of seconds passed since the last displayed packet

## 11.9.5.8. pinfo.visited

Whether this packet hass been already visited

## 11.9.5.9. pinfo.src

Source Address of this Packet

## 11.9.5.10. pinfo.dst

Destination Address of this Packet

## 11.9.5.11. pinfo.lo

lower Address of this Packet

## 11.9.5.12. pinfo.hi

higher Address of this Packet

## 11.9.5.13. pinfo.dl\_src

Data Link Source Address of this Packet

## 11.9.5.14. pinfo.dl\_dst

Data Link Destination Address of this Packet

## 11.9.5.15. pinfo.net\_src

Network Layer Source Address of this Packet

## 11.9.5.16. pinfo.net\_dst

Network Layer Destination Address of this Packet

## 11.9.5.17. pinfo.ptype

Type of Port of .src\_port and .dst\_port

## 11.9.5.18. pinfo.src\_port

Source Port of this Packet

## 11.9.5.19. pinfo.dst\_port

Source Address of this Packet

## 11.9.5.20. pinfo.ipproto

IP Protocol id

## 11.9.5.21. pinfo.circuit\_id

For circuit based protocols

## 11.9.5.22. pinfo.match

Port/Data we are matching

## 11.9.5.23. pinfo.curr\_proto

Which Protocol are we dissecting

## 11.9.5.24. pinfo.columns

Accesss to the packet list columns

## 11.9.5.25. pinfo.cols

Accesss to the packet list columns (equivalent to pinfo.columns)

## 11.9.5.26. pinfo.desegment\_len

Estimated number of additional bytes required for completing the PDU

## 11.9.5.27. pinfo.desegment\_offset

Offset in the tvbuff at which the dissector will continue processing when next called

## 11.9.5.28. pinfo.private\_data

Access to private data

## 11.9.5.29. pinfo.private

Access to the private table entries

## 11.9.5.30. pinfo.ethertype

Ethernet Type Code, if this is an Ethernet packet

## 11.9.5.31. pinfo.fragmented

If the protocol is only a fragment

## 11.9.5.32. pinfo.in\_error\_pkt

If we're inside an error packet

## 11.9.5.33. pinfo.match\_uint

Matched uint for calling subdissector from table

## 11.9.5.34. pinfo.match\_string

Matched string for calling subdissector from table

# 11.9.6. PrivateTable

PrivateTable represents the pinfo->private\_table.

## 11.9.6.1. privatetable:\_\_tostring()

### 11.9.6.1.1. Returns

A string with all keys in the table, mostly for debugging.

# **11.10. Functions for writing dissectors**

# 11.10.1. Dissector

A refererence to a dissector, used to call a dissector against a packet or a part of it.

## 11.10.1.1. Dissector.get(name)

Obtains a dissector reference by name

### 11.10.1.1.1. Arguments

name The name of the dissector

### 11.10.1.1.2. Returns

The Dissector reference

## 11.10.1.2. dissector:call(tvb, pinfo, tree)

Calls a dissector against a given packet (or part of it)

### 11.10.1.2.1. Arguments

tvb The buffer to dissect

pinfo The packet info

tree The tree on which to add the protocol items

## 11.10.2. DissectorTable

A table of subdissectors of a particular protocol (e.g. TCP subdissectors like http, smtp, sip are added to table "tcp.port"). Useful to add more dissectors to a table so that they appear in the Decode As... dialog.

## 11.10.2.1. DissectorTable.new(tablename, [uiname], [type], [base])

Creates a new DissectorTable for your dissector's use.

### 11.10.2.1.1. Arguments

tablename	The short name of the table.	
uiname (optional)	The name of the table in the User Interface (defaults to the name given).	
type (optional)	Either ftypes.UINT{8,16,24,32} or ftypes.STRING (defaults to ftypes.UINT32)	
base (optional)	Either base.NONE, base.DEC, base.HEX, base.OCT, base.DEC_HEX or base.HEX_DEC (defaults to base.DEC)	

### 11.10.2.1.2. Returns

The newly created DissectorTable

## 11.10.2.2. DissectorTable.get(tablename)

Obtain a reference to an existing dissector table.

### 11.10.2.2.1. Arguments

tablename The short name of the table.

### 11.10.2.2.2. Returns

The DissectorTable

### 11.10.2.3. dissectortable:add(pattern, dissector)

Add a dissector to a table.

### 11.10.2.3.1. Arguments

on the table's type).
•

dissector The dissector to add (either an Proto or a Dissector).

## 11.10.2.4. dissectortable:remove(pattern, dissector)

Remove a dissector from a table

### 11.10.2.4.1. Arguments

pattern The pattern to match	(either an integer or a string	depending on the table's type).
------------------------------	--------------------------------	---------------------------------

dissector The dissector to add (either an Proto or a Dissector).

## 11.10.2.5. dissectortable:try(pattern, tvb, pinfo, tree)

Try to call a dissector from a table

### 11.10.2.5.1. Arguments

pattern	The pattern to be matched (either an integer or a string depending on the table's type).
tvb	The buffer to dissect
pinfo	The packet info
tree	The tree on which to add the protocol items

## 11.10.2.6. dissectortable:get\_dissector(pattern)

Try to obtain a dissector from a table.

### 11.10.2.6.1. Arguments

pattern The pattern to be matched (either an integer or a string depending on the table's type).

### 11.10.2.6.2. Returns

The dissector handle if found

nil if not found

## 11.10.3. Pref

A preference of a Protocol.

## 11.10.3.1. Pref.bool(label, default, descr)

Creates a boolean preference to be added to a Protocol's prefs table.

### 11.10.3.1.1. Arguments

label	The Label (text in the right side of the preference input) for this preference
default	The default value for this preference
descr	A description of what this preference is

## 11.10.3.2. Pref.uint(label, default, descr)

Creates an (unsigned) integer preference to be added to a Protocol's prefs table.

### 11.10.3.2.1. Arguments

label	The Label (text in the right side of the preference input) for this preference

default The default value for this preference

descr A description of what this preference is

## 11.10.3.3. Pref.string(label, default, descr)

Creates a string preference to be added to a Protocol's prefs table.

### 11.10.3.3.1. Arguments

label	The Label	(text in the	right side	of the preference	input) for this	preference
		(			r	r

default The default value for this preference

descr A description of what this preference is

## 11.10.3.4. Pref.enum(label, default, descr, enum, radio)

Creates an enum preference to be added to a Protocol's prefs table.

### 11.10.3.4.1. Arguments

label	The Label (text in the right side of the preference input) for this preference
default	The default value for this preference
descr	A description of what this preference is
enum	A enum table
radio	Radio button (true) or Combobox (false)

## 11.10.3.5. Pref.range(label, default, descr, max)

Creates a range preference to be added to a Protocol's prefs table.

### 11.10.3.5.1. Arguments

label	The Label (text in the	e right side of the	preference inp	out) for this preference
-------	------------------------	---------------------	----------------	--------------------------

- default The default value for this preference, e.g., "53", "10-30", or "10-30,53,55,100-120"
- descr A description of what this preference is
- max The maximum value

## 11.10.3.6. Pref.statictext(label, descr)

Creates a static text preference to be added to a Protocol's prefs table.

### 11.10.3.6.1. Arguments

label The static text

descr The static text description

## 11.10.4. Prefs

The table of preferences of a protocol

## 11.10.4.1. prefs:\_\_\_newindex(name, pref)

Creates a new preference

### 11.10.4.1.1. Arguments

- name The abbreviation of this preference
- pref A valid but still unassigned Pref object

### 11.10.4.1.2. Errors

• Unknow Pref type

## 11.10.4.2. prefs:\_\_index(name)

Get the value of a preference setting

### 11.10.4.2.1. Arguments

name The abbreviation of this preference

### 11.10.4.2.2. Returns

The current value of the preference

### 11.10.4.2.3. Errors

• Unknow Pref type

## 11.10.5. Proto

A new protocol in wireshark. Protocols have more uses, the main one is to dissect a protocol. But they can be just dummies used to register preferences for other purposes.

## 11.10.5.1. Proto.new(name, desc)

### 11.10.5.1.1. Arguments

name The name of the protocol

desc A Long Text description of the protocol (usually lowercase)

### 11.10.5.1.2. Returns

The newly created protocol

## 11.10.5.2. proto.dissector

The protocol's dissector, a function you define

## 11.10.5.3. proto.fields

The Fields Table of this dissector

## 11.10.5.4. proto.prefs

The preferences of this dissector

## 11.10.5.5. proto.init

The init routine of this dissector, a function you define

### 11.10.5.6. proto.name

The name given to this dissector

## 11.10.5.7. proto.description

The description given to this dissector

## 11.10.6. ProtoField

A Protocol field (to be used when adding items to the dissection tree)

# 11.10.6.1. ProtoField.new(name, abbr, type, [voidstring], [base], [mask], [descr])

Creates a new field to be used in a protocol.

### 11.10.6.1.1. Arguments

name	Actual name of the field (the string that appears in the tree).
abbr	Filter name of the field (the string that is used in filters).
type	Field Type: one of ftypes.NONE, ftypes.PROTOCOL, ftypes.BOOLEAN, ftypes.UINT8, ftypes.UINT16, ftypes.UINT24, ftypes.UINT32, ftypes.UINT64, ftypes.INT8, ftypes.INT16 ftypes.INT24, ftypes.INT32, ftypes.INT64, ftypes.FLOAT, ftypes.DOUBLE, ftypes.ABSOLUTE_TIME ftypes.RELATIVE_TIME, ftypes.STRING, ftypes.STRINGZ, ftypes.UINT_STRING, ftypes.ETHER, ftypes.BYTES ftypes.UINT_BYTES, ftypes.IPv4, ftypes.IPv6, ftypes.IPXNET, ftypes.FRAMENUM, ftypes.PCRE, ftypes.GUID ftypes.OID, ftypes.EUI64
voidstring (optional)	A VoidString object.
base (optional)	The representation: one of base.NONE, base.DEC, base.HEX, base.OCT, base.DEC_HEX, base.HEX_DEC

mask (optional)	The bitmask to be used.
descr (optional)	The description of the field.

### 11.10.6.1.2. Returns

The newly created ProtoField object

# 11.10.6.2. ProtoField.uint8(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.2.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.2.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.3. ProtoField.uint16(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.3.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.3.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.4. ProtoField.uint24(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.4.1. Arguments

abbr

Abbreviated name of the field (the string used in filters)

name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.4.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.5. ProtoField.uint32(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.5.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.5.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.6. ProtoField.uint64(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.6.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.6.2. Returns

# 11.10.6.7. ProtoField.int8(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.7.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.7.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.8. ProtoField.int16(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.8.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.8.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.9. ProtoField.int24(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.9.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values

mask (optional)	Integer mask of this field

desc (optional) Description of the field

### 11.10.6.9.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.10. ProtoField.int32(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.10.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.10.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.11. ProtoField.int64(abbr, [name], [base], [valuestring], [mask], [desc])

### 11.10.6.11.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.11.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.12. ProtoField.framenum(abbr, [name], [base], [valuestring], [mask], [desc])

A frame number (for hyperlinks between frames)

### 11.10.6.12.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.DEC, base.HEX or base.OCT
valuestring (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.12.2. Returns

A protofield item to be added to a ProtoFieldArray

# 11.10.6.13. ProtoField.bool(abbr, [name], [display], [string], [mask], [desc])

### 11.10.6.13.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
display (optional)	how wide the parent bitfield is (base.NONE is used for NULL-value)
string (optional)	A table containing the text that corresponds to the values
mask (optional)	Integer mask of this field
desc (optional)	Description of the field

### 11.10.6.13.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.14. ProtoField.absolute\_time(abbr, [name], [base], [desc])

### 11.10.6.14.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
base (optional)	One of base.LOCAL, base.UTC or base.DOY_UTC
desc (optional)	Description of the field

### 11.10.6.14.2. Returns

## 11.10.6.15. ProtoField.relative\_time(abbr, [name], [desc])

### 11.10.6.15.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.15.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.16. ProtoField.ipv4(abbr, [name], [desc])

### 11.10.6.16.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.16.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.17. ProtoField.ipv6(abbr, [name], [desc])

### 11.10.6.17.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.17.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.18. ProtoField.ether(abbr, [name], [desc])

### 11.10.6.18.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.18.2. Returns

## 11.10.6.19. ProtoField.float(abbr, [name], [desc])

### 11.10.6.19.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.19.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.20. ProtoField.double(abbr, [name], [desc])

### 11.10.6.20.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.20.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.21. ProtoField.string(abbr, [name], [desc])

### 11.10.6.21.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.21.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.22. ProtoField.stringz(abbr, [name], [desc])

### 11.10.6.22.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.22.2. Returns

## 11.10.6.23. ProtoField.bytes(abbr, [name], [desc])

### 11.10.6.23.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.23.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.24. ProtoField.ubytes(abbr, [name], [desc])

### 11.10.6.24.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.24.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.25. ProtoField.guid(abbr, [name], [desc])

### 11.10.6.25.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.25.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.26. ProtoField.oid(abbr, [name], [desc])

### 11.10.6.26.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.26.2. Returns

## 11.10.6.27. ProtoField.bool(abbr, [name], [desc])

### 11.10.6.27.1. Arguments

abbr	Abbreviated name of the field (the string used in filters)
name (optional)	Actual name of the field (the string that appears in the tree)
desc (optional)	Description of the field

### 11.10.6.27.2. Returns

A protofield item to be added to a ProtoFieldArray

## 11.10.6.28. protofield:\_\_tostring()

Returns a string with info about a protofield (for debugging purposes)

# 11.10.7. Non Method Functions

## 11.10.7.1. register\_postdissector(proto)

Make a protocol (with a dissector) a postdissector. It will be called for every frame after dissection

### 11.10.7.1.1. Arguments

proto the protocol to be used as postdissector

# 11.11. Adding information to the dissection tree

# 11.11.1. Treeltem

TreeItems represent information in the packet-details pane. A root TreeItem is passed to dissectors as first argument.

## 11.11.1.1. treeitem:add\_packet\_field()

Adds an child item to a given item, returning the child. tree\_item:add\_packet\_field([proto\_field], [tvbrange], [encoding], ...)

## 11.11.1.2. treeitem:add()

Adds an child item to a given item, returning the child. tree\_item:add([proto\_field | proto], [tvbrange], [label], ...) if the proto\_field represents a numeric value (int, uint or float) is to be treated as a Big Endian (network order) Value.

### 11.11.1.2.1. Returns

The child item

## 11.11.1.3. treeitem:add\_le()

Adds (and returns) an child item to a given item, returning the child. tree\_item:add([proto\_field | proto], [tvbrange], [label], ...) if the proto\_field represents a numeric value (int, uint or float) is to be treated as a Little Endian Value.

### 11.11.1.3.1. Returns

The child item

### 11.11.1.4. treeitem:set\_text(text)

Sets the text of the label

### 11.11.1.4.1. Arguments

text The text to be used.

## 11.11.1.5. treeitem:append\_text(text)

Appends text to the label

### 11.11.1.5.1. Arguments

text The text to be appended.

## 11.11.1.6. treeitem:set\_expert\_flags([group], [severity])

Sets the expert flags of the item.

### 11.11.1.6.1. Arguments

group (optional)	One of PI_CHECKSUM, PI_SEQUENCE, PI_RESPONSE_CODE, PI_REQUEST_CODE, PI_UNDECODED, PI_REASSEMBLE, PI_MALFORMED or PI_DEBUG
severity (optional)	One of PI_CHAT, PI_NOTE, PI_WARN, PI_ERROR

## 11.11.1.7. treeitem:add\_expert\_info([group], [severity], [text])

Sets the expert flags of the item and adds expert info to the packet.

### 11.11.1.7.1. Arguments

group (optional)	One of PI_CHECKSUM, PI_SEQUENCE, PI_RESPONSE_CODE, PI_REQUEST_CODE, PI_UNDECODED, PI_REASSEMBLE, PI_MALFORMED or PI_DEBUG
severity (optional)	One of PI_CHAT, PI_NOTE, PI_WARN, PI_ERROR
text (optional)	The text for the expert info

## 11.11.1.8. treeitem:set\_generated()

Marks the TreeItem as a generated field (with data infered but not contained in the packet).

## 11.11.1.9. treeitem:set\_hidden()

Should not be used

## 11.11.1.10. treeitem:set\_len(len)

Set TreeItem's length inside tvb, after it has already been created.

### 11.11.1.10.1. Arguments

len The length to be used.

# 11.12. Functions for handling packet data

# 11.12.1. ByteArray

## 11.12.1.1. ByteArray.new([hexbytes])

Creates a ByteArray Object

### 11.12.1.1.1. Arguments

hexbytes (optional) A string consisting of hexadecimal bytes like "00 B1 A2" or "1a2b3c4d"

### 11.12.1.1.2. Returns

The new ByteArray object.

## 11.12.1.2. bytearray: \_\_\_concat(first, second)

Concatenate two ByteArrays

### 11.12.1.2.1. Arguments

first First array

second Second array

### 11.12.1.2.2. Returns

The new composite ByteArray.

### 11.12.1.2.3. Errors

• Both arguments must be ByteArrays

## 11.12.1.3. bytearray:prepend(prepended)

Prepend a ByteArray to this ByteArray

### 11.12.1.3.1. Arguments

prepended Array to be prepended

### 11.12.1.3.2. Errors

• Both arguments must be ByteArrays

## 11.12.1.4. bytearray:append(appended)

Append a ByteArray to this ByteArray

### 11.12.1.4.1. Arguments

appended Array to be appended

### 11.12.1.4.2. Errors

• Both arguments must be ByteArrays

## 11.12.1.5. bytearray:set\_size(size)

Sets the size of a ByteArray, either truncating it or filling it with zeros.

### 11.12.1.5.1. Arguments

size New size of the array

### 11.12.1.5.2. Errors

• ByteArray size must be non-negative

## 11.12.1.6. bytearray:set\_index(index, value)

Sets the value of an index of a ByteArray.

### 11.12.1.6.1. Arguments

index The position of the byte to be set

value The char value to set [0-255]

## 11.12.1.7. bytearray:get\_index(index)

Get the value of a byte in a ByteArray

### 11.12.1.7.1. Arguments

index The position of the byte to get

### 11.12.1.7.2. Returns

The value [0-255] of the byte.

## 11.12.1.8. bytearray:len()

Obtain the length of a ByteArray

### 11.12.1.8.1. Returns

The length of the ByteArray.

## 11.12.1.9. bytearray:subset(offset, length)

Obtain a segment of a ByteArray

### 11.12.1.9.1. Arguments

offset The position of the first byte

length The length of the segment

### 11.12.1.9.2. Returns

A ByteArray contaiing the requested segment.

A string contaning a representaion of the ByteArray.

## 11.12.2. Int

Int64 represents a 64 bit integer. Lua uses one single number representation which can be chosen at compile time and since it is often set to IEEE 754 double precision floating point, we cannot store a 64 bit integer with full precision. For details, see: http://lua-users.org/wiki/FloatingPoint

## 11.12.3. Tvb

A Tvb represents the packet's buffer. It is passed as an argument to listeners and dissectors, and can be used to extract information (via TvbRange) from the packet's data. Beware that Tvbs are usable only by the current listener or dissector call and are destroyed as soon as the listener/dissector returns, so references to them are unusable once the function has returned. To create a tvbrange the tvb must be called with offset and length as optional arguments ( the offset defaults to 0 and the length to tvb:len() )

## 11.12.3.1. ByteArray.tvb(name)

Creates a new Tvb from a bytearray (it gets added to the current frame too)

### 11.12.3.1.1. Arguments

name The name to be given to the new data-source.

### 11.12.3.1.2. Returns

The created Tvb.

## 11.12.3.2. TvbRange.tvb(range)

Creates a (sub)Tvb from using a TvbRange

### 11.12.3.2.1. Arguments

range The TvbRange from which to create the new Tvb.

## 11.12.3.3. tvb:\_\_\_tostring()

Convert the bytes of a Tvb into a string, to be used for debugging purposes as '...' will be appended in case the string is too long.

### 11.12.3.3.1. Returns

The string.

## 11.12.3.4. tvb:reported\_len()

Obtain the reported length of a TVB

### 11.12.3.4.1. Returns

The length of the Tvb.

## 11.12.3.5. tvb:len()

Obtain the length of a TVB

### 11.12.3.5.1. Returns

The length of the Tvb.

## 11.12.3.6. tvb:reported\_length\_remaining()

Obtain the reported length of packet data to end of a TVB or -1 if the offset is beyond the end of the TVB

### 11.12.3.6.1. Returns

The length of the Tvb.

## 11.12.3.7. tvb:offset()

Returns the raw offset (from the beginning of the source Tvb) of a sub Tvb.

### 11.12.3.7.1. Returns

The raw offset of the Tvb.

## 11.12.3.8. tvb:\_\_call()

Equivalent to tvb:range(...)

## 11.12.3.9. wslua:\_\_\_concat()

Concatenate two objects to a string

## 11.12.4. TvbRange

A TvbRange represents an usable range of a Tvb and is used to extract data from the Tvb that generated it TvbRanges are created by calling a tvb (e.g. tvb(offset,length)). If the TvbRange span is outside the Tvb's range the creation will cause a runtime error.

## 11.12.4.1. tvb:range([offset], [length])

Creates a tvbr from this Tvb. This is used also as the Tvb:\_\_call() metamethod.

### 11.12.4.1.1. Arguments

offset (optional)	The offset (in octets) from the begining of the Tvb. Defaults to 0.
length (optional)	The length (in octets) of the range. Defaults to until the end of the Tvb.

### 11.12.4.1.2. Returns

The TvbRange

## 11.12.4.2. tvbrange:uint()

Get a Big Endian (network order) unsigned integer from a TvbRange. The range must be 1, 2, 3 or 4 octets long.

### 11.12.4.2.1. Returns

The unsigned integer value

## 11.12.4.3. tvbrange:le\_uint()

Get a Little Endian unsigned integer from a TvbRange. The range must be 1, 2, 3 or 4 octets long.

### 11.12.4.3.1. Returns

The unsigned integer value

## 11.12.4.4. tvbrange:uint64()

Get a Big Endian (network order) unsigned 64 bit integer from a TvbRange. The range must be 1-8 octets long.

## 11.12.4.5. tvbrange:le\_uint64()

Get a Little Endian unsigned 64 bit integer from a TvbRange. The range must be 1-8 octets long.

## 11.12.4.6. tvbrange:int()

Get a Big Endian (network order) signed integer from a TvbRange. The range must be 1, 2 or 4 octets long.

### 11.12.4.6.1. Returns

The signed integer value

## 11.12.4.7. tvbrange:le\_int()

Get a Little Endian signed integer from a TvbRange. The range must be 1, 2 or 4 octets long.

### 11.12.4.7.1. Returns

The signed integer value

## 11.12.4.8. tvbrange:int64()

Get a Big Endian (network order) signed 64 bit integer from a TvbRange. The range must be 1-8 octets long.

## 11.12.4.9. tvbrange:le\_int64()

Get a Little Endian signed 64 bit integer from a TvbRange. The range must be 1-8 octets long.

## 11.12.4.10. tvbrange:float()

Get a Big Endian (network order) floating point number from a TvbRange. The range must be 4 or 8 octets long.

### 11.12.4.10.1. Returns

The floating point value

## 11.12.4.11. tvbrange:le\_float()

Get a Little Endian floating point number from a TvbRange. The range must be 4 or 8 octets long.

### 11.12.4.11.1. Returns

The floating point value

## 11.12.4.12. tvbrange:ipv4()

Get an IPv4 Address from a TvbRange.

### 11.12.4.12.1. Returns

The IPv4 Address

## 11.12.4.13. tvbrange:le\_ipv4()

Get an Little Endian IPv4 Address from a TvbRange.

### 11.12.4.13.1. Returns

The IPv4 Address

## 11.12.4.14. tvbrange:ether()

Get an Ethernet Address from a TvbRange.

### 11.12.4.14.1. Returns

The Ethernet Address

### 11.12.4.14.2. Errors

• The range must be 6 bytes long

## 11.12.4.15. tvbrange:nstime()

Obtain a nstime from a TvbRange

### 11.12.4.15.1. Returns

The NSTime

### 11.12.4.15.2. Errors

• The range must be 4 or 8 bytes long

## 11.12.4.16. tvbrange:le\_nstime()

Obtain a nstime from a TvbRange

### 11.12.4.16.1. Returns

The NSTime

### 11.12.4.16.2. Errors

• The range must be 4 or 8 bytes long

## 11.12.4.17. tvbrange:string()

Obtain a string from a TvbRange

### 11.12.4.17.1. Returns

The string

## 11.12.4.18. tvbrange:ustring()

Obtain a Big Endian (network order) UTF-16 encoded string from a TvbRange

### 11.12.4.18.1. Returns

The string

## 11.12.4.19. tvbrange:le\_ustring()

Obtain a Little Endian UTF-16 encoded string from a TvbRange

### 11.12.4.19.1. Returns

The string

## 11.12.4.20. tvbrange:stringz()

Obtain a zero terminated string from a TvbRange

### 11.12.4.20.1. Returns

The zero terminated string

#### 11.12.4.21. tvbrange:ustringz()

Obtain a Big Endian (network order) UTF-16 encoded zero terminated string from a TvbRange

#### 11.12.4.21.1. Returns

The zero terminated string, the length found in tvbr

### 11.12.4.22. tvbrange:le\_ustringz()

Obtain a Little Endian UTF-16 encoded zero terminated string from a TvbRange

#### 11.12.4.22.1. Returns

The zero terminated string, the length found in tvbr

#### 11.12.4.23. tvbrange:bytes()

Obtain a ByteArray

#### 11.12.4.23.1. Returns

The ByteArray

## 11.12.4.24. tvbrange:bitfield([position], [length])

Get a bitfield from a TvbRange.

#### 11.12.4.24.1. Arguments

position (optional)	The bit offset from the begining of the TvbRange. Defaults to 0.
length (optional)	The length (in bits) of the field. Defaults to 1.

#### 11.12.4.24.2. Returns

The bitfield value

#### 11.12.4.25. tvbrange:range([offset], [length])

Creates a sub-TvbRange from this TvbRange. This is used also as the TvbRange:\_\_call() metamethod.

#### 11.12.4.25.1. Arguments

offset (optional)	The offset (in octets) from the begining of the TvbRange. Defaults to 0.
length (optional)	The length (in octets) of the range. Defaults to until the end of the TvbRange.

#### 11.12.4.25.2. Returns

The TvbRange

### 11.12.4.26. tvbrange:len()

Obtain the length of a TvbRange

## 11.12.4.27. tvbrange:offset()

Obtain the offset in a TvbRange

## 11.12.4.28. tvbrange:\_\_tostring()

Converts the TvbRange into a string. As the string gets truncated you should use this only for debugging purposes or if what you want is to have a truncated string in the format 67:89:AB:...

## 11.12.5. UInt

UInt64 represents a 64 bit unsigned integer.

## 11.13. Utility Functions

## 11.13.1. Dir

A Directory

## 11.13.1.1. Dir.open(pathname, [extension])

Usage: for filename in Dir.open(path) do ... end

#### 11.13.1.1.1. Arguments

pathname	The pathname of the directory
extension (optional)	If given, only file with this extension will be returned

#### 11.13.1.1.2. Returns

the Dir object

### 11.13.1.2. dir:\_\_call()

At every invocation will return one file (nil when done)

### 11.13.1.3. dir:close()

Closes the directory

## **11.13.2. Non Method Functions**

### 11.13.2.1. get\_version()

Get Wireshark version

#### 11.13.2.1.1. Returns

version string

## 11.13.2.2. format\_date(timestamp)

Formats an absolute timestamp into a human readable date

#### 11.13.2.2.1. Arguments

timestamp A timestamp value to convert.

#### 11.13.2.2.2. Returns

A string with the formated date

#### 11.13.2.3. format\_time(timestamp)

Formats a relative timestamp in a human readable form

#### 11.13.2.3.1. Arguments

timestamp A timestamp value to convert

#### 11.13.2.3.2. Returns

A string with the formated time

#### 11.13.2.4. report\_failure(text)

Reports a failure to the user

#### 11.13.2.4.1. Arguments

text Message

#### 11.13.2.5. critical(...)

Will add a log entry with critical severity

#### 11.13.2.5.1. Arguments

. objects to be printed

### 11.13.2.6. warn(...)

Will add a log entry with warn severity

#### 11.13.2.6.1. Arguments

.. objects to be printed

#### 11.13.2.7. message(...)

Will add a log entry with message severity

#### 11.13.2.7.1. Arguments

... objects to be printed

#### 11.13.2.8. info(...)

Will add a log entry with info severity

#### 11.13.2.8.1. Arguments

... objects to be printed

### 11.13.2.9. debug(...)

Will add a log entry with debug severity

#### 11.13.2.9.1. Arguments

... objects to be printed

## 11.13.2.10. loadfile(filename)

Lua's loadfile() has been modified so that if a file does not exist in the current directory it will look for it in wireshark's user and system directories

#### 11.13.2.10.1. Arguments

filename Name of the file to be loaded

## 11.13.2.11. dofile(filename)

Lua's dofile() has been modified so that if a file does not exist in the current directory it will look for it in wireshark's user and system directories

#### 11.13.2.11.1. Arguments

filename Name of the file to be run

## 11.13.2.12. persconffile\_path([filename])

#### 11.13.2.12.1. Arguments

filename (optional) A filename

#### 11.13.2.12.2. Returns

The full pathname for a file in the personal configuration directory

## 11.13.2.13. datafile\_path([filename])

#### 11.13.2.13.1. Arguments

filename (optional) A filename

#### 11.13.2.13.2. Returns

The full pathname for a file in wireshark's configuration directory

## 11.13.2.14. register\_stat\_cmd\_arg(argument, [action])

Register a function to handle a -z option

#### 11.13.2.14.1. Arguments

argument

Argument

action (optional) Action

## **Appendix A. Files and Folders**

## A.1. Capture Files

To understand which information will remain available after the captured packets are saved to a capture file, it's helpful to know a bit about the capture file contents.

Wireshark uses the libpcap file format as the default format to save captured packets; this format has existed for a long time and it's pretty simple. However, it has some drawbacks: it's not extensible and lacks some information that would be really helpful (e.g. being able to add a comment to a packet such as "the problems start here" would be really nice).

In addition to the libpcap format, Wireshark supports several different capture file formats. However, the problems described above also applies for these formats.

A new capture file format "PCAP Next Generation Dump File Format" is currently under development, which will fix these drawbacks. However, it still might take a while until the new file format is ready and Wireshark can use it.

## A.1.1. Libpcap File Contents

At the start of each libpcap capture file some basic information is stored like a magic number to identify the libpcap file format. The most interesting information of this file start is the link layer type (Ethernet, Token Ring, ...).

The following data is saved for each packet:

- the timestamp with millisecond resolution
- the packet length as it was "on the wire"
- the packet length as it's saved in the file
- the packet's raw bytes

A detailed description of the libpcap file format can be found at: <u>http://wiki.wireshark.org/Development/</u> <u>LibpcapFileFormat</u>

## A.1.2. Not Saved in the Capture File

Probably even more interesting for everyday Wireshark usage is to know the things that are **not saved** in the capture file:

- current selections (selected packet, ...)
- name resolution information, see Section 7.7, "Name Resolution" for details



#### Warning!

The name resolution information is rebuilt each time Wireshark is restarted so this information might even change when the capture file is reopened on the same machine later!

- the number of packets dropped while capturing
- packet marks set with "Edit/Mark Packet"

- time references set with "Edit/Time Reference"
- the current display filter
- ...

## A.2. Configuration Files and Folders

Wireshark uses a number of files and folders while it is running. Some of these reside in the personal configuration folder and are used to maintain information between runs of Wireshark, while some of them are maintained in system areas.

#### Tip



A list of the folders Wireshark actually uses can be found under the **Folders** tab in the dialog box shown when you select **About Wireshark** from the **Help** menu.

The content format of the configuration files is the same on all platforms. However, to match the different policies for Unix and Windows platforms, different folders are used for these files.

Table A.1. Configuration files and folders overview

File/Folder	Description	Unix/Linux folders	Windows folders	
preferences	Settings from the Preferences dialog box.		%WIRESHARK%\wireshark.com %APPDATA%\Wireshark\prefere	
recent		\$HOME/.wireshark recent	%APPDATA%\Wireshark\recent	
cfilters	Capture filters.	\$HOME/.wireshark cfilters	%WIRESHARK%\cfilters, %A \Wireshark\cfilters	PPDATA%
dfilters	Display filters.	\$HOME/.wireshark dfilters	%WIRESHARK%\dfilters, %A \Wireshark\dfilters	PPDATA%
colorfilters	Coloring rules.	\$HOME/.wireshark colorfilters	%WIRESHARK%\colorfilters, % %\Wireshark\colorfilters	APPDATA
disabled_protos	Disabled protocols.	\$HOME/.wireshark disabled_protos	%WIRESHARK%\disabled_proto %APPDATA%\Wireshark\disable	
ethers	Ethernet name resolution.	/etc/ethers, \$HOME/.wireshark ethers		PPDATA%
manuf	Ethernet name resolution.	/etc/manuf, \$HOME/.wireshark manuf	····· ··· ··· ··· ··· ··· ··· ··· ···	PPDATA%
hosts	IPv4 and IPv6 name resolution.	/etc/hosts, \$HOME/.wireshark hosts	·····, ·····	PPDATA%
services	Network services.	/etc/services, \$HOME/.wireshark services	%WIRESHARK%\services, %A {Wireshark\services	PPDATA%

File/Folder	Description	Unix/Linux folders	Windows folders
subnets	IPv4 subnet name resolution.	,	%WIRESHARK%\subnets, %APPDATA% \Wireshark\subnets
ipxnets	IPX name resolution.	1 /	%WIRESHARK%\ipxnets, %APPDATA% \Wireshark\ipxnets
plugins	Plugin directories.	/usr/share/ wireshark/ plugins, /usr/local/ share/wireshark/ plugins, \$HOME/.wireshark plugins	%WIRESHARK%\plugins\ <version>, %APPDATA%\Wireshark\plugins</version>
temp	Temporary files.	Environment: TMPDIR	Environment: TMPDIR or TEMP



#### Windows folders

%APPDATA% points to the personal configuration folder, e.g.: C:\Documents and Settings\<username>\Application Data (details can be found at: Section A.3.1, "Windows profiles"),

%WIRESHARK% points to the Wireshark program folder, e.g.: C:\Program Files \Wireshark



#### **Unix/Linux folders**

The /etc folder is the global Wireshark configuration folder. The folder actually used on your system may vary, maybe something like: /usr/local/etc.

\$HOME is usually something like: /home/<username>

preferences/wireshark.confThis file contains your Wireshark preferences, including defaults<br/>for capturing and displaying packets. It is a simple text file<br/>containing statements of the form:variable:valueThe settings from this file are read in at program start and written<br/>to disk when you press the Save button in the "Preferences" dialog<br/>box.recentThis file contains various GUI related settings like the main window<br/>position and size, the recent files list and such. It is a simple text<br/>file containing statements of the form:variable:value

It is read at program start and written at program exit.

cfilters	This file contains all the capture filters that you have defined and saved. It consists of one or more lines, where each line has the following format:
	" <filter name="">" <filter string=""></filter></filter>
	The settings from this file are read in at program start and written to disk when you press the Save button in the "Capture Filters" dialog box.
dfilters	This file contains all the display filters that you have defined and saved. It consists of one or more lines, where each line has the following format:
	" <filter name="">" <filter string=""></filter></filter>
	The settings from this file are read in at program start and written to disk when you press the Save button in the "Display Filters" dialog box.
colorfilters	This file contains all the color filters that you have defined and saved. It consists of one or more lines, where each line has the following format:
	<pre>@<filter name="">@<filter string="">@[<bg rgb(16-bit)="">][<fg rgb(16-bit)="">]</fg></bg></filter></filter></pre>
	The settings from this file are read in at program start and written to disk when you press the Save button in the "Coloring Rules" dialog box.
disabled_protos	Each line in this file specifies a disabled protocol name. The following are some examples:
	tcp udp
	The settings from this file are read in at program start and written to disk when you press the Save button in the "Enabled Protocols" dialog box.
ethers	When Wireshark is trying to translate Ethernet hardware addresses to names, it consults the files listed in <u>Table A.1, "Configuration</u> <u>files and folders overview</u> ". If an address is not found in /etc/ethers, Wireshark looks in \$HOME/.wireshark/ethers
	Each line in these files consists of one hardware address and name separated by whitespace. The digits of hardware addresses are separated by colons (:), dashes (-) or periods(.). The following are some examples:
	ff-ff-ff-ff-ff Broadcast

	c0-00-ff-ff-ff TR_broadcast 00.2b.08.93.4b.a1 Freds_machine
	The settings from this file are read in at program start and never written by Wireshark.
manuf	Wireshark uses the files listed in <u>Table A.1, "Configuration files</u> and folders overview" to translate the first three bytes of an Ethernet address into a manufacturers name. This file has the same format as the ethers file, except addresses are three bytes long.
	An example is:
	00:00:01 Xerox # XEROX CORPORATION
	The settings from this file are read in at program start and never written by Wireshark.
hosts	Wireshark uses the files listed in <u>Table A.1, "Configuration files</u> and folders overview" to translate IPv4 and IPv6 addresses into names.
	This file has the same format as the usual /etc/hosts file on Unix systems.
	An example is:
	# Comments must be prepended by the # sign! 192.168.0.1 homeserver
	The settings from this file are read in at program start and never written by Wireshark.
services	Wireshark uses the files listed in <u>Table A.1, "Configuration files</u> and folders overview" to translate port numbers into names.
	An example is:
	mydns 5045/udp # My own Domain Name Server mydns 5045/tcp # My own Domain Name Server
	The settings from this file are read in at program start and never written by Wireshark.
subnets	Wireshark uses the files listed in <u>Table A.1, "Configuration files</u> and folders overview" to translate an IPv4 address into a subnet name. If no exact match from the hosts file or from DNS is found, Wireshark will attempt a partial match for the subnet of the address.
	Each line of this file consists of an IPv4 address, a subnet mask length separated only by a '/' and a name separated by whitespace. While the address must be a full IPv4 address, any values beyond the mask length are subsequently ignored.

An example is:

# Comments must be prepended by the # sign!
192.168.0.0/24 ws\_test\_network

A partially matched name will be printed as "subnetname.remaining-address". For example, "192.168.0.1" under the subnet above would be printed as "ws\_test\_network.1"; if the mask length above had been 16 rather than 24, the printed address would be "ws\_test\_network.0.1".

The settings from this file are read in at program start and never written by Wireshark.

ipxnets Wireshark uses the files listed in <u>Table A.1, "Configuration files</u> and folders overview" to translate IPX network numbers into names.

An example is:

C0.A8.2C.00 HR c0-a8-1c-00 CEO 00:00:BE:EF IT\_Server1 110f FileServer3

The settings from this file are read in at program start and never written by Wireshark.

plugins folderWireshark searches for plugins in the directories listed in Table A.1,<br/>"Configuration files and folders overview". They are searched in<br/>the order listed.temp folderIf you start a new capture and don't specify a filename for it,<br/>Wireshark uses this directory to store that file; see Section 4.10,

"Capture files and file modes".

## A.2.1. Protocol help configuration

Wireshark can use configuration files to create context-sensitive menu items for protocol detail items which will load help URLs in your web browser.

To create a protocol help file, create a folder named "protocol\_help" in either the personal or global configuration folders. Then create a text file with the extension ".ini" in the "protocol\_help" folder. The file must contain key-value pairs with the following sections:

[database] Mandatory. This contains initialization information for the help file. The following keys must be defined:

sourceSource name, e.g. "HyperGlobalMegaMart".versionMust be "1".locationGeneral URL for help items. Variables can be substituted using<br/>the [location data] section below.

[location data] Optional. Contains keys that will be used for variable substitution in the "location" value. For example, if the database section contains

location = http://www.example.com/proto?cookie=\${cookie}&path=\${PATH}

then setting

cookie = anonymous-user-1138

will result in the URL "http://www.example.com/proto?cookie=anonymoususer-1138&path=\${PATH}". PATH is used for help path substitution, and shouldn't be defined in this section.

[map] Maps Wireshark protocol names to section names below. Each key MUST match a valid protocol name such as "ip". Each value MUST have a matching section defined in the configuration file.

Each protocol section must contain an "\_OVERVIEW" key which will be used as the first menu item for the help source. Subsequent keys must match descriptions in the protocol detail. Values will be used as the \${PATH} variable in the location template. If \${PATH} isn't present in the location template the value will be appended to the location.

Suppose the file C:\Users\sam.clemens\AppData\Roaming\Wireshark \protocol\_help\wikipedia.ini contains the following:

```
# Wikipedia (en) protocol help file.
# Help file initialization
# source: The source of the help information, e.q. "Inacon" or "Wikipedia"
# version: Currently unused. Must be "1".
# url_template: Template for generated URLs. See "URL Data" below.
[database]
source=Wikipedia
version=1
url_template=http://${language}.wikipedia.org/wiki/${PATH}
# Substitution data for the location template.
# Each occurence of the keys below in the location template will be
# substituted with their corresponding values. For example, "${license}"
# in the URL template above will be replaced with the value of "license"
# below.
±
# PATH is reserved for the help paths below; do not specify it here.
[location data]
language = en
# Maps Wireshark protocol names to section names below. Each key MUST match
# a valid protocol name. Each value MUST have a matching section below.
[map]
tcp=TCP
# Mapped protocol sections.
# Keys must match protocol detail items descriptions.
[TCP]
_OVERVIEW=Transmission_Control_Protocol
Destination port=Transmission_Control_Protocol#TCP_ports
Source port=Transmission_Control_Protocol#TCP_ports
```

Right-clicking on a TCP protocol detail item will display a help menu item that displays the Wikipedia page for TCP. Right-clicking on the TCP destination or source ports will display additional help menu items that take you to the "TCP ports" section of the page.

The [location data] and \${PATH} can be omitted if they are not needed. For example, the following configuration is functionally equivalent to the previous configuration:

```
[database]
source=Wikipedia
version=1
location=http://en.wikipedia.org/wiki/
[map]
tcp=TCP
[TCP]
_OVERVIEW=Transmission_Control_Protocol
Destination port=Transmission_Control_Protocol#TCP_ports
Source port=Transmission_Control_Protocol#TCP_ports
```

## A.3. Windows folders

Here you will find some details about the folders used in Wireshark on different Windows versions.

As already mentioned, you can find the currently used folders in the About Wireshark dialog.

## A.3.1. Windows profiles

Windows uses some special directories to store user configuration files which define the "user profile". This can be confusing, as the default directory location changed from Windows version to version and might also be different for English and internationalized versions of Windows.



#### Note!

If you've upgraded to a new Windows version, your profile might be kept in the former location, so the defaults mentioned here might not apply.

The following guides you to the right place where to look for Wireshark's profile data.

Windows 7, Windows Vista	C:\Users\ <username>\AppData\Roaming \Wireshark</username>	
Windows XP	C:\Documents and Settings\ <username> \Application Data, "Documents and Settings" and "Application Data" might be internationalized.</username>	
Windows 2000 (no longer supported by Wireshark, for historical reference only)	C:\Documents and Settings\ <username> \Application Data, "Documents and Settings" and "Application Data" might be internationalized.</username>	
Windows NT 4 (no longer supported, for historical reference only)	C:\WINNT\Profiles\ <username>\Application Data\Wireshark</username>	
Windows ME, Windows 98 with user profiles (no longer supported, for historical reference only)	In Windows ME and 98 you can enable separate user profiles. In that case, something like C:\windows\Profiles \ <username>\Application Data\Wireshark is used.</username>	

Windows ME, Windows 98 without user profiles (no longer supported, for historical reference only) Without user profiles enabled the default location for all users is C: \windows\Application Data\Wireshark

## A.3.2. Windows 7, Vista, XP, 2000, and NT roaming profiles

The following will only be applicable if you are using roaming profiles. This might be the case, if you work in a Windows domain environment (used in company networks). The configurations of all programs you use won't be saved on the local hard drive of the computer you are currently working on, but on the domain server.

As Wireshark is using the correct places to store its profile data, your settings will travel with you, if you logon to a different computer the next time.

There is an exception to this: The "Local Settings" folder in your profile data (typically something like: C:\Documents and Settings\<username>\Local Settings) will not be transferred to the domain server. This is the default for temporary capture files.

## A.3.3. Windows temporary folder

Wireshark uses the folder which is set by the TMPDIR or TEMP environment variable. This variable will be set by the Windows installer.

Windows 7, Windows Vista	C:\Users\ <username>\AppData\Local\Temp</username>	
Windows XP, Windows 2000	C:\Documents and Setting Settings\Temp	gs\ <username>\Local</username>
Windows NT	C:\TEMP	

# Appendix B. Protocols and Protocol Fields

Wireshark distinguishes between protocols (e.g. tcp) and protocol fields (e.g. tcp.port).

A comprehensive list of all protocols and protocol fields can be found at: <u>http://www.wireshark.org/docs/</u><u>dfref/</u>

## **Appendix C. Wireshark Messages**

Wireshark provides you with additional information generated out of the plain packet data or it may need to indicate dissection problems. Messages generated by Wireshark are usually placed in [] parentheses.

## C.1. Packet List Messages

These messages might appear in the packet list.

## C.1.1. [Malformed Packet]

Malformed packet means that the protocol dissector can't dissect the contents of the packet any further. There can be various reasons:

- Wrong dissector: Wireshark erroneously has chosen the wrong protocol dissector for this packet. This will happen e.g. if you are using a protocol not on its well known TCP or UDP port. You may try Analyze|Decode As to circumvent this problem.
- **Packet not reassembled**: The packet is longer than a single frame and it is not reassembled, see <u>Section 7.6, "Packet Reassembling"</u> for further details.
- **Packet is malformed**: The packet is actually wrong (malformed), meaning that a part of the packet is just not as expected (not following the protocol specifications).
- Dissector is buggy: The corresponding protocol dissector is simply buggy or still incomplete.

Any of the above is possible. You'll have to look into the specific situation to determine the reason. You could disable the dissector by disabling the protocol on the Analyze menu and check how Wireshark displays the packet then. You could (if it's TCP) enable reassembly for TCP and the specific dissector (if possible) in the Edit|Preferences menu. You could check the packet contents yourself by reading the packet bytes and comparing it to the protocol specification. This could reveal a dissector bug. Or you could find out that the packet is indeed wrong.

## C.1.2. [Packet size limited during capture]

The packet size was limited during capture, see "Limit each packet to n bytes" at the <u>Section 4.5, "The</u> "<u>Capture Options</u>" dialog box". While dissecting, the current protocol dissector was simply running out of packet bytes and had to give up. There's nothing else you can do now, except to repeat the whole capture process again with a higher (or no) packet size limitation.

## C.2. Packet Details Messages

These messages might appear in the packet details.

## C.2.1. [Response in frame: 123]

The current packet is the request of a detected request/response pair. You can directly jump to the corresponding response packet just by double clicking on this message.

## C.2.2. [Request in frame: 123]

Same as "Response in frame: 123" above, but the other way round.

## C.2.3. [Time from request: 0.123 seconds]

The time between the request and the response packets.

## C.2.4. [Stream setup by PROTOCOL (frame 123)]

The session control protocol (SDP, H225, etc) message which signaled the creation of this session. You can directly jump to the corresponding packet just by double clicking on this message.

# Appendix D. Related command line tools

## **D.1. Introduction**

Besides the Wireshark GUI application, there are some command line tools which can be helpful for doing some more specialized things. These tools will be described in this chapter.

## **D.2. tshark: Terminal-based Wireshark**

TShark is a terminal oriented version of Wireshark designed for capturing and displaying packets when an interactive user interface isn't necessary or available. It supports the same options as **wireshark**. For more information on **tshark**, see the manual pages (**man tshark**).

Copyright 1998-2011 Gerald Combs <gerald@wireshark.org> and contributors. This is free software; see the source for copying conditions. There is NO warranty; not even for MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

Usage: tshark [options] ... Related command line tools

```
Capture interface:
-i <interfaces name or idx of interface (def: first non-loopback)
Example D.I. Help information available from tsharts syntax
                           packet snapshot length (def: 65535)
  -s <snaplen>
                            don't capture in promiscuous mode
  -p
  -B <buffer size>
                           size of kernel buffer (def: 1MB)
  -y <link type>
                           link layer type (def: first appropriate)
                            print list of interfaces and exit
  -D
                           print list of link-layer types of iface and exit
  -L
Capture stop conditions:
                           stop after n packets (def: infinite)
  -c <packet count>
  -a <autostop cond.> ... duration:NUM - stop after NUM seconds
                            filesize:NUM - stop this file after NUM KB
                              files:NUM - stop after NUM files
Capture output:
  -b <ringbuffer opt.> ... duration:NUM - switch to next file after NUM secs
                            filesize:NUM - switch to next file after NUM KB
                               files:NUM - ringbuffer: replace after NUM files
Input file:
  -r <infile>
                            set the filename to read from (no pipes or stdin!)
Processing:
                           perform a two-pass analysis
  -2
  -R <read filter>
                           packet filter in Wireshark display filter syntax
                            disable all name resolutions (def: all enabled)
  -n
  -N <name resolve flags> enable specific name resolution(s): "mntC"
  -d <layer_type>==<selector>,<decode_as_protocol> ...
                            "Decode As", see the man page for details
                            Example: tcp.port==8888,http
Output:
  -w <outfile |->
                           write packets to a pcap-format file named "outfile"
                            (or to the standard output for "-")
  -C <config profile>
                            start with specified configuration profile
  -F <output file type>
                           set the output file type, default is libpcap
                            an empty "-F" option will list the file types
  -V
                            add output of packet tree
                                                             (Packet Details)
  -0 <protocols>
                            Only show packet details of these protocols, comma
                            separated
                           print packets even when writing to a file
  – P
  -S <separator>
                            the line separator to print between packets
                            add output of hex and ASCII dump (Packet Bytes)
  -x
  -T pdml|ps|psml|text|fields
                            format of text output (def: text)
                            field to print if -Tfields selected (e.g. tcp.port);
  -e <field>
                           this option can be repeated to print multiple fields
  -E<fieldsoption>=<value> set options for output when -Tfields selected:
     header=y|n
                           switch headers on and off
     separator=/t|/s|<char> select tab, space, printable character as separator
                       print first, last or all occurrences of each field
     occurrence=f|l|a
     aggregator=, |/s| < char> select comma, space, printable character as
                           aggregator
     quote=d|s|n
                           select double, single, no quotes for values
  -t ad|a|r|d|dd|e
                           output format of time stamps (def: r: rel. to first)
  -u s|hms
                            output format of seconds (def: s: seconds)
  -1
                            flush standard output after each packet
                           be more quiet on stdout (e.g. when using statistics)
  -q
  -X <key>:<value>
                           eXtension options, see the man page for details
  -z <statistics>
                           various statistics, see the man page for details
Miscellaneous:
  -h
                           display this help and exit
                           display version info and exit
  -v
  -o <name>:<value> ...
                           override preference setting
  -K <keytab>
                           keytab file to use for kerberos decryption
  -G [report]
                           dump one of several available reports and exit
                           default report="fields"
                           use "-G ?" for more help
```

## D.3. tcpdump: Capturing with tcpdump for viewing with Wireshark

There are occasions when you want to capture packets using **tcpdump** rather than **wireshark**, especially when you want to do a remote capture and do not want the network load associated with running Wireshark remotely (not to mention all the X traffic polluting your capture).

However, the default **tcpdump** parameters result in a capture file where each packet is truncated, because most versions of **tcpdump**, will, by default, only capture the first 68 or 96 bytes of each packet.

To ensure that you capture complete packets, use the following command:

```
tcpdump -i <interface> -s 65535 -w <some-file>
```

You will have to specify the correct **interface** and the name of a **file** to save into. In addition, you will have to terminate the capture with ^C when you believe you have captured enough packets.



#### Note!

tcpdump is not part of the Wireshark distribution. You can get it from: <u>http://</u><u>www.tcpdump.org</u> for various platforms.

## D.4. dumpcap: Capturing with dumpcap for viewing with Wireshark

Dumpcap is a network traffic dump tool. It captures packet data from a live network and writes the packets to a file. Dumpcap's native capture file format is libpcap format, which is also the format used by Wireshark, tcpdump and various other tools.

Without any options set it will use the pcap library to capture traffic from the first available network interface and write the received raw packet data, along with the packets' time stamps into a libpcap file.

Packet capturing is performed with the pcap library. The capture filter syntax follows the rules of the pcap library.

#### Example D.2. Help information available from dumpcap

```
Dumpcap 1.7.0 (SVN Rev 39165 from /trunk)
Capture network packets and dump them into a libpcap file.
See http://www.wireshark.org for more information.
Usage: dumpcap [options] ...
 -1 <interface> name or idx of interface (def: first non-loopback)
-f <capture filter> packet filter in libpcap filter syntax
-s <snaplen> packet snapshot length (def: creation)
Capture interface:
  -B <buffer size>
                            size of kernel buffer (def: 1MB)
  -y <link type>
                            link layer type (def: first appropriate)
                            print list of interfaces and exit
  -D
                            print list of link-layer types of iface and exit
  - T.
  -d
                            print generated BPF code for capture filter
  -S
                            print statistics for each interface once per second
  -M
                            for -D, -L, and -S, produce machine-readable output
RPCAP options:
                            don't ignore own RPCAP traffic in capture
  -r
                            use UDP for RPCAP data transfer
  -11
  -A <user>:<password>
                            use RPCAP password authentication
                          use packet sampling
  -m <sampling type>
                            count:NUM - capture one packet of every NUM
                            timer:NUM - capture no more than 1 packet in NUM ms
Stop conditions:
  -c <packet count>
                            stop after n packets (def: infinite)
  -a <autostop cond.> ... duration:NUM - stop after NUM seconds
                            filesize:NUM - stop this file after NUM KB
                               files:NUM - stop after NUM files
Output (files):
  -w <filename>
                          name of file to save (def: tempfile)
  -g
                            enable group read access on the output file(s)
  -b <ringbuffer opt.> ... duration:NUM - switch to next file after NUM secs
                            filesize:NUM - switch to next file after NUM KB
                               files:NUM - ringbuffer: replace after NUM files
                            use pcapng format instead of pcap
  -n
Miscellaneous:
  -t
                            use a separate thread per interface
  -q
                            don't report packet capture counts
                            print version information and exit
  -v
                            display this help and exit
  -h
Example: dumpcap -i eth0 -a duration:60 -w output.pcap
"Capture network packets from interface eth0 until 60s passed into output.pcap"
```

Use Ctrl-C to stop capturing at any time.

## **D.5.** capinfos: Print information about capture files

Included with Wireshark is a small utility called **capinfos**, which is a command-line utility to print information about binary capture files.

#### Example D.3. Help information available from capinfos

```
Capinfos 1.7.0 (SVN Rev 39165 from /trunk)
Prints various information (infos) about capture files.
See http://www.wireshark.org for more information.
Usage: capinfos [options] <infile> ...
General infos:
  -t display the capture file type
  -E display the capture file encapsulation
  -H display the SHA1, RMD160, and MD5 hashes of the file
Size infos:
  -c display the number of packets
  -s display the size of the file (in bytes)
  -d display the total length of all packets (in bytes)
  -l display the packet size limit (snapshot length)
Time infos:
  -u display the capture duration (in seconds)
  -a display the capture start time
  -e display the capture end time
  -o display the capture file chronological status (True/False)
  -S display start and end times as seconds
Statistic infos:
  -y display average data rate (in bytes/sec)
  -i display average data rate (in bits/sec)
  -z display average packet size (in bytes)
  -x display average packet rate (in packets/sec)
Output format:
  -L generate long report (default)
  -T generate table report
Table report options:
  -R generate header record (default)
  -r do not generate header record
  -B separate infos with TAB character (default)
  -m separate infos with comma (,) character
  -b separate infos with SPACE character
  -N do not quote infos (default)
  -q quote infos with single quotes (')
  -Q quote infos with double quotes (")
Miscellaneous:
  -h display this help and exit
  -C cancel processing if file open fails (default is to continue)
  -A generate all infos (default)
Options are processed from left to right order with later options superceeding
or adding to earlier options.
```

If no options are given the default is to display all infos in long report output format.

## **D.6. rawshark: Dump and analyze network traffic.**

Rawshark reads a stream of packets from a file or pipe, and prints a line describing its output, followed by a set of matching fields for each packet on stdout.

```
Example D.4. Help information available from rawshark
```

```
Rawshark 1.7.0 (SVN Rev 39165 from /trunk)
Dump and analyze network traffic.
See http://www.wireshark.org for more information.
Copyright 1998-2011 Gerald Combs <gerald@wireshark.org> and contributors.
This is free software; see the source for copying conditions. There is NO
warranty; not even for MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.
Usage: rawshark [options] ...
Input file:
  -r <infile>
                           set the pipe or file name to read from
Processing:
  -d <encap:dlt>|<proto:protoname>
                          packet encapsulation or protocol
  -F <field>
                           field to display
                          disable all name resolution (def: all enabled)
  -n
  -N <name resolve flags> enable specific name resolution(s): "mntC"
                         use the system's packet header format
  -p
                          (which may have 64-bit timestamps)
  -R <read filter>
                           packet filter in Wireshark display filter syntax
  -s
                           skip PCAP header on input
Output:
  -1
                           flush output after each packet
  -S
                           format string for fields
                           (%D - name, %S - stringval, %N numval)
                           output format of time stamps (def: r: rel. to first)
  -t ad|a|r|d|dd|e
Miscellaneous:
                          display this help and exit
  -h
                           override preference setting
  -o <name>:<value> ...
                           display version info and exit
  -17
```

## D.7. editcap: Edit capture files

Included with Wireshark is a small utility called **editcap**, which is a command-line utility for working with capture files. Its main function is to remove packets from capture files, but it can also be used to convert capture files from one format to another, as well as to print information about capture files.

#### Related command line tools

Editcap 1.7.0 (SVN Rev 39165 from /trunk) Edit and/or translate the format of capture files. See http://www.wireshark.org for more information. Example D.5. Help information available from editcap Usage: editcap [options] ... <infile> <outfile> [ <packet#>[-<packet#>] ... ] <infile> and <outfile> must both be present. A single packet or a range of packets can be selected. Packet selection: keep the selected packets; default is to delete them. -r -A <start time> only output packets whose timestamp is after (or equal to) the given time (format as YYYY-MM-DD hh:mm:ss). -B <stop time> only output packets whose timestamp is before the given time (format as YYYY-MM-DD hh:mm:ss). Duplicate packet removal: remove packet if duplicate (window == 5). -d remove packet if duplicate; configurable <dup window> -D <dup window> Valid <dup window> values are 0 to 1000000. NOTE: A <dup window> of 0 with -v (verbose option) is useful to print MD5 hashes. -w <dup time window> remove packet if duplicate packet is found EQUAL TO OR LESS THAN <dup time window> prior to current packet. A <dup time window> is specified in relative seconds (e.g. 0.000001). NOTE: The use of the 'Duplicate packet removal' options with other editcap options except -v may not always work as expected. Specifically the -r, -t or -S options will very likely NOT have the desired effect if combined with the -d, -D or -w. Packet manipulation: -s <snaplen> truncate each packet to max. <snaplen> bytes of data. -C <choplen> chop each packet by <choplen> bytes. Positive values chop at the packet beginning, negative values at the packet end. -t <time adjustment> adjust the timestamp of each packet; <time adjustment> is in relative seconds (e.g. -0.5). -S <strict adjustment> adjust timestamp of packets if necessary to insure strict chronological increasing order. The <strict adjustment> is specified in relative seconds with values of 0 or 0.000001 being the most reasonable. A negative adjustment value will modify timestamps so that each packet's delta time is the absolute value of the adjustment specified. A value of -0 will set all packets to the timestamp of the first packet. -E <error probability> set the probability (between 0.0 and 1.0 incl.) that a particular packet byte will be randomly changed. Output File(s): -c <packets per file> split the packet output to different files based on uniform packet counts with a maximum of <packets per file> each. -i <seconds per file> split the packet output to different files based on uniform time intervals with a maximum of <seconds per file> each. -F <capture type> set the output file type; default is libpcap. an empty "-F" option will list the file types. set the output file encapsulation type; -T <encap type> default is the same as the input file. an empty "-T" option will list the encapsulation types. Miscellaneous: display this help and exit. -h -v verbose output. If -v is used with any of the 'Duplicate Packet Removal' options (-d, -D or -w) then Packet lengths

and MD5 hashes are printed to standard-out.

#### Example D.6. Capture file types available from editcap

```
$ editcap -F
editcap: option requires an argument -- F
editcap: The available capture file types for the "-F" flag are:
   5views - Accellent 5Views capture
   btsnoop - Symbian OS btsnoop
   commview - TamoSoft CommView
   dct2000 - Catapult DCT2000 trace (.out format)
   eyesdn - EyeSDN USB S0/E1 ISDN trace format
   k12text - K12 text file
   lanalyzer - Novell LANalyzer
   libpcap - Wireshark/tcpdump/... - libpcap
   modlibpcap - Modified tcpdump - libpcap
   netmon1 - Microsoft NetMon 1.x
   netmon2 - Microsoft NetMon 2.x
   nettl - HP-UX nettl trace
   ngsniffer - NA Sniffer (DOS)
   ngwsniffer 1 1 - NA Sniffer (Windows) 1.1
   ngwsniffer_2_0 - NA Sniffer (Windows) 2.00x
   niobserverv - Network Instruments Observer
   nokialibpcap - Nokia tcpdump - libpcap
   nseclibpcap - Wireshark - nanosecond libpcap
   nstrace10 - NetScaler Trace (Version 1.0)
   nstrace20 - NetScaler Trace (Version 2.0)
   pcapng - Wireshark - pcapng
   rf5 - Tektronix K12xx 32-bit .rf5 format
   rh6_11ibpcap - RedHat 6.1 tcpdump - libpcap
   snoop - Sun snoop
   suse6_3libpcap - SuSE 6.3 tcpdump - libpcap
   visual - Visual Networks traffic capture
```

#### Example D.7. Encapsulation types available from editcap

```
$ editcap -T
editcap: option requires an argument -- T
editcap: The available encapsulation types for the "-T" flag are:
   ap1394 - Apple IP-over-IEEE 1394
   arcnet - ARCNET
   arcnet_linux - Linux ARCNET
   ascend - Lucent/Ascend access equipment
   atm-pdus - ATM PDUs
   atm-pdus-untruncated - ATM PDUs - untruncated
   atm-rfc1483 - RFC 1483 ATM
   bacnet-ms-tp - BACnet MS/TP
   ber - ASN.1 Basic Encoding Rules
   bluetooth-h4 - Bluetooth H4
   bluetooth-h4-linux - Bluetooth H4 with linux header
   bluetooth-hci - Bluetooth without transport layer
   can20b - Controller Area Network 2.0B
   chdlc - Cisco HDLC
   chdlc-with-direction - Cisco HDLC with Directional Info
   cosine - CoSine L2 debug log
   dct2000 - Catapult DCT2000
   docsis - Data Over Cable Service Interface Specification
   dpnss_link - Digital Private Signalling System No 1 Link Layer
   dvbci - DVB-CI (Common Interface)
   enc - OpenBSD enc(4) encapsulating interface
   erf - Endace Record File
   ether - Ethernet
   ether-nettl - Ethernet with nettl headers
   fc2 - Fibre Channel FC-2
   fc2sof - Fibre Channel FC-2 With Frame Delimiter
```

```
fddi - FDDI
fddi-nettl - FDDI with nettl headers
fddi-swapped - FDDI with bit-swapped MAC addresses
flexray - FlexRay
frelay - Frame Relay
frelay-with-direction - Frame Relay with Directional Info
gcom-serial - GCOM Serial
gcom-tiel - GCOM TIE1
gprs-llc - GPRS LLC
gsm_um - GSM Um Interface
hhdlc - HiPath HDLC
i2c - I2C
ieee-802-11 - IEEE 802.11 Wireless LAN
ieee-802-11-avs - IEEE 802.11 plus AVS WLAN header
ieee-802-11-netmon - IEEE 802.11 plus Network Monitor radio header
ieee-802-11-radio - IEEE 802.11 Wireless LAN with radio information
ieee-802-11-radiotap - IEEE 802.11 plus radiotap WLAN header
ieee-802-16-mac-cps - IEEE 802.16 MAC Common Part Sublayer
ios - Cisco IOS internal
ip-over-fc - RFC 2625 IP-over-Fibre Channel
ipfix - IPFIX
ipmb - Intelligent Platform Management Bus
ipnet - Solaris IPNET
irda - IrDA
isdn - ISDN
jfif - JPEG/JFIF
juniper-atm1 - Juniper ATM1
juniper-atm2 - Juniper ATM2
juniper-chdlc - Juniper C-HDLC
juniper-ether - Juniper Ethernet
juniper-frelay - Juniper Frame-Relay
juniper-ggsn - Juniper GGSN
juniper-mlfr - Juniper MLFR
juniper-mlppp - Juniper MLPPP
juniper-ppp - Juniper PPP
juniper-pppoe - Juniper PPPoE
juniper-vp - Juniper Voice PIC
k12 - K12 protocol analyzer
lapb - LAPB
lapd - Lapd header
lapd - LAPD
layer1-event - EyeSDN Layer 1 event
lin - Local Interconnect Network
linux-atm-clip - Linux ATM CLIP
linux-sll - Linux cooked-mode capture
ltalk - Localtalk
most - Media Oriented Systems Transport
mpeg - MPEG
mtp2 - SS7 MTP2
mtp2-with-phdr - MTP2 with pseudoheader
mtp3 - SS7 MTP3
mux27010 - MUX27010
nstrace10 - NetScaler Encapsulation 1.0 of Ethernet
nstrace20 - NetScaler Encapsulation 2.0 of Ethernet
null - NULL
packetlogger - PacketLogger
pflog - OpenBSD PF Firewall logs
pflog-old - OpenBSD PF Firewall logs, pre-3.4
ppi - Per-Packet Information header
ppp - PPP
ppp-with-direction - PPP with Directional Info
prism - IEEE 802.11 plus Prism II monitor mode header
raw-icmp-nettl - Raw ICMP with nettl headers
raw-icmpv6-nettl - Raw ICMPv6 with nettl headers
raw-telnet-nettl - Raw telnet with nettl headers
rawip - Raw IP
rawip-nettl - Raw IP with nettl headers
```

```
rawip4 - Raw IPv4
rawip6 - Raw IPv6
redback - Redback SmartEdge
sccp - SS7 SCCP
sdlc - SDLC
sita-wan - SITA WAN packets
slip - SLIP
socketcan - SocketCAN
symantec - Symantec Enterprise Firewall
tnef - Transport-Neutral Encapsulation Format
tr - Token Ring
tr-nettl - Token Ring with nettl headers
tzsp - Tazmen sniffer protocol
unknown - Unknown
unknown-nettl - Unknown link-layer type with nettl headers
usb - Raw USB packets
usb-linux - USB packets with Linux header
usb-linux-mmap - USB packets with Linux header and padding
user0 - USER 0
user1 - USER 1
user10 - USER 10
user11 - USER 11
user12 - USER 12
user13 - USER 13
user14 - USER 14
user15 - USER 15
user2 - USER 2
user3 - USER 3
user4 - USER 4
user5 - USER 5
user6 - USER 6
user7 - USER 7
user8 - USER 8
user9 - USER 9
whdlc - Wellfleet HDLC
wpan - IEEE 802.15.4 Wireless PAN
wpan-nofcs - IEEE 802.15.4 Wireless PAN with FCS not present
wpan-nonask-phy - IEEE 802.15.4 Wireless PAN non-ASK PHY
x25-nettl - X25 with nettl headers
x2e-serial - X2E serial line capture
x2e-xoraya - X2E Xoraya
```

## **D.8.** mergecap: Merging multiple capture files into one

Mergecap is a program that combines multiple saved capture files into a single output file specified by the -w argument. Mergecap knows how to read libpcap capture files, including those of tcpdump. In addition, Mergecap can read capture files from snoop (including Shomiti) and atmsnoop, LanAlyzer, Sniffer (compressed or uncompressed), Microsoft Network Monitor, AIX's iptrace, NetXray, Sniffer Pro, RADCOM's WAN/LAN analyzer, Lucent/Ascend router debug output, HP-UX's nettl, and the dump output from Toshiba's ISDN routers. There is no need to tell Mergecap what type of file you are reading; it will determine the file type by itself. Mergecap is also capable of reading any of these file formats if they are compressed using gzip. Mergecap recognizes this directly from the file; the '.gz' extension is not required for this purpose.

By default, it writes the capture file in libpcap format, and writes all of the packets in the input capture files to the output file. The -F flag can be used to specify the format in which to write the capture file; it can write the file in libpcap format (standard libpcap format, a modified format used by some patched versions of libpcap, the format used by Red Hat Linux 6.1, or the format used by SuSE Linux 6.3), snoop format,

uncompressed Sniffer format, Microsoft Network Monitor 1.x format, and the format used by Windowsbased versions of the Sniffer software.

Packets from the input files are merged in chronological order based on each frame's timestamp, unless the -a flag is specified. Mergecap assumes that frames within a single capture file are already stored in chronological order. When the -a flag is specified, packets are copied directly from each input file to the output file, independent of each frame's timestamp.

If the -s flag is used to specify a snapshot length, frames in the input file with more captured data than the specified snapshot length will have only the amount of data specified by the snapshot length written to the output file. This may be useful if the program that is to read the output file cannot handle packets larger than a certain size (for example, the versions of snoop in Solaris 2.5.1 and Solaris 2.6 appear to reject Ethernet frames larger than the standard Ethernet MTU, making them incapable of handling gigabit Ethernet captures if jumbo frames were used).

If the -T flag is used to specify an encapsulation type, the encapsulation type of the output capture file will be forced to the specified type, rather than being the type appropriate to the encapsulation type of the input capture file. Note that this merely forces the encapsulation type of the output file to be the specified type; the packet headers of the packets will not be translated from the encapsulation type of the input capture file to the specified encapsulation type (for example, it will not translate an Ethernet capture to an FDDI capture if an Ethernet capture is read and '-T fddi' is specified).

#### Example D.8. Help information available from mergecap

```
Mergecap 1.7.0 (SVN Rev 39165 from /trunk)
Merge two or more capture files into one.
See http://www.wireshark.org for more information.
Usage: mergecap [options] -w <outfile> - <infile> ...
Out.put.:
                    concatenate rather than merge files.
  -a
                    default is to merge based on frame timestamps.
                    truncate packets to <snaplen> bytes of data.
  -s <snaplen>
  -w <outfile>|-
                  set the output filename to <outfile> or '-' for stdout.
  -F <capture type> set the output file type; default is libpcap.
                    an empty "-F" option will list the file types.
  -T <encap type>
                    set the output file encapsulation type;
                    default is the same as the first input file.
                    an empty "-T" option will list the encapsulation types.
Miscellaneous:
  -h
                    display this help and exit.
  -v
                    verbose output.
```

A simple example merging dhcp-capture.libpcap and imap-1.libpcap into outfile.libpcap is shown below.

#### Example D.9. Simple example of using mergecap

\$ mergecap -w outfile.libpcap dhcp-capture.libpcap imap-1.libpcap

## D.9. text2pcap: Converting ASCII hexdumps to network captures

There may be some occasions when you wish to convert a hex dump of some network traffic into a libpcap file.

**Text2pcap** is a program that reads in an ASCII hex dump and writes the data described into a libpcapstyle capture file. text2pcap can read hexdumps with multiple packets in them, and build a capture file of multiple packets. text2pcap is also capable of generating dummy Ethernet, IP and UDP headers, in order to build fully processable packet dumps from hexdumps of application-level data only.

Text2pcap understands a hexdump of the form generated by od  $-A \times -t \times 1$ . In other words, each byte is individually displayed and surrounded with a space. Each line begins with an offset describing the position in the file. The offset is a hex number (can also be octal - see -o), of more than two hex digits. Here is a sample dump that text2pcap can recognize:

 000000
 00
 e0
 1e
 a7
 05
 6f
 00
 10
 .......

 000008
 5a
 a0
 b9
 12
 08
 00
 46
 00
 .......

 000010
 03
 68
 00
 00
 00
 0a
 2e
 .......

 000018
 ee
 33
 0f
 19
 08
 7f
 0f
 19
 ........

 000020
 03
 80
 94
 04
 00
 00
 10
 01
 .............

 000028
 16
 a2
 0a
 00
 350
 00
 0c
 ...............

 000030
 01
 01
 01
 10
 ................

There is no limit on the width or number of bytes per line. Also the text dump at the end of the line is ignored. Bytes/hex numbers can be uppercase or lowercase. Any text before the offset is ignored, including email forwarding characters '>'. Any lines of text between the bytestring lines is ignored. The offsets are used to track the bytes, so offsets must be correct. Any line which has only bytes without a leading offset is ignored. An offset is recognized as being a hex number longer than two characters. Any text after the bytes is ignored (e.g. the character dump). Any hex numbers in this text are also ignored. An offset of zero is indicative of starting a new packet, so a single text file with a series of hexdumps can be converted into a packet capture with multiple packets. Multiple packets are read in with timestamps differing by one second each. In general, short of these restrictions, text2pcap is pretty liberal about reading in hexdumps and has been tested with a variety of mangled outputs (including being forwarded through email multiple times, with limited line wrap etc.)

There are a couple of other special features to note. Any line where the first non-whitespace character is '#' will be ignored as a comment. Any line beginning with #TEXT2PCAP is a directive and options can be inserted after this command to be processed by text2pcap. Currently there are no directives implemented; in the future, these may be used to give more fine grained control on the dump and the way it should be processed e.g. timestamps, encapsulation type etc.

Text2pcap also allows the user to read in dumps of application-level data, by inserting dummy L2, L3 and L4 headers before each packet. Possibilities include inserting headers such as Ethernet, Ethernet + IP, Ethernet + IP + UDP, or Ethernet + IP + TCP before each packet. This allows Wireshark or any other full-packet decoder to handle these dumps.

```
Related command line tools
Text2pcap 1.7.0 (SVN Rev 39165 from /trunk)
Generate a capture file from an ASCII hexdump of packets.
See http://www.wireshark.org for more information.
Example D.10. Help information available for text2pcap
Usage: text2pcap [options] <infile> <outfile>
where <infile> specifies input filename (use - for standard input)
      <outfile> specifies output filename (use - for standard output)
Input:
  -o hex|oct|dec
                         parse offsets as (h)ex, (o)ctal or (d)ecimal;
                          default is hex.
  -t <timefmt>
                          treat the text before the packet as a date/time code;
                          the specified argument is a format string of the sort
                          supported by strptime.
                          Example: The time "10:15:14.5476" has the format code
                          "%H:%M:%S."
                         NOTE: The subsecond component delimiter, '.', must be
                         given, but no pattern is required; the remaining
                          number is assumed to be fractions of a second.
                         NOTE: Date/time fields from the current date/time are
                          used as the default for unspecified fields.
                          enable ASCII text dump identification.
  -a
                          It allows to identify the start of the ASCII text
                         dump and not include it in the packet even if it
                          looks like HEX dump.
                          NOTE: Do not enable it if the input file does not
                          contain the ASCII text dump.
Output:
  -l <typenum>
                         link-layer type number; default is 1 (Ethernet).
                          See the file net/bpf.h for list of numbers.
                          Use this option if your dump is a complete hex dump
                          of an encapsulated packet and you wish to specify
                          the exact type of encapsulation.
                          Example: -1 7 for ARCNet packets.
  -m <max-packet>
                         max packet length in output; default is 64000
Prepend dummy header:
  -e <13pid>
                         prepend dummy Ethernet II header with specified L3PID
                          (in HEX).
                          Example: -e 0x806 to specify an ARP packet.
                          prepend dummy IP header with specified IP protocol
  -i <proto>
                          (in DECIMAL).
                          Automatically prepends Ethernet header as well.
                          Example: -i 46
                          prepend dummy UDP header with specified
  -u <srcp>,<destp>
                          dest and source ports (in DECIMAL).
                          Automatically prepends Ethernet & IP headers as well.
                          Example: -u 1000,69 to make the packets look like
                         TFTP/UDP packets.
                         prepend dummy TCP header with specified
  -T <srcp>,<destp>
                          dest and source ports (in DECIMAL).
                          Automatically prepends Ethernet & IP headers as well.
                          Example: -T 50,60
  -s <srcp>,<dstp>,<taq> prepend dummy SCTP header with specified
                          dest/source ports and verification tag (in DECIMAL).
                          Automatically prepends Ethernet & IP headers as well.
                          Example: -s 30,40,34
  -S <srcp>,<dstp>,<ppi> prepend dummy SCTP header with specified
                          dest/source ports and verification tag 0.
                          Automatically prepends a dummy SCTP DATA
                          chunk header with payload protocol identifier ppi.
                          Example: -S 30,40,34
Miscellaneous:
  -h
                         display this help and exit.
  -d
                         show detailed debug of parser states.
                         generate no output at all (automatically turns off -d).
  -q
```

## D.10. idl2wrs: Creating dissectors from CORBA IDL files

In an ideal world idl2wrs would be mentioned in the users guide in passing and documented in the developers guide. As the developers guide has not yet been completed it will be documented here.

## D.10.1. What is it?

As you have probably guessed from the name, **idl2wrs** takes a user specified IDL file and attempts to build a dissector that can decode the IDL traffic over GIOP. The resulting file is "C" code, that should compile okay as a Wireshark dissector.

**idl2wrs** basically parses the data struct given to it by the omniidl compiler, and using the GIOP API available in packet-giop.[ch], generates get\_CDR\_xxx calls to decode the CORBA traffic on the wire.

It consists of 4 main files.

README.idl2wrs	This document
wireshark_be.py	The main compiler backend
wireshark_gen.py	A helper class, that generates the C code.
idl2wrs	A simple shell script wrapper that the end user should use to generate the dissector from the IDL file(s).

## D.10.2. Why do this?

It is important to understand what CORBA traffic looks like over GIOP/IIOP, and to help build a tool that can assist in troubleshooting CORBA interworking. This was especially the case after seeing a lot of discussions about how particular IDL types are represented inside an octet stream.

I have also had comments/feedback that this tool would be good for say a CORBA class when teaching students what CORBA traffic looks like "on the wire".

It is also COOL to work on a great Open Source project such as the case with "Wireshark" (  $\underline{http://www.wireshark.org}$  )

## D.10.3. How to use idl2wrs

To use the idl2wrs to generate Wireshark dissectors, you need the following:

#### Prerequisites to using idl2wrs

- 1. Python must be installed. See http://python.org/
- 2. omniidl from the omniORB package must be available. See http://omniorb.sourceforge.net/
- 3. Of course you need Wireshark installed to compile the code and tweak it if required. idl2wrs is part of the standard Wireshark distribution

To use idl2wrs to generate an Wireshark dissector from an idl file use the following procedure:

#### Procedure for converting a CORBA idl file into a Wireshark dissector

1. To write the C code to stdout.

```
idl2wrs <your_file.idl>
e.g.:
idl2wrs echo.idl
```

2. To write to a file, just redirect the output.

```
idl2wrs echo.idl > packet-test-idl.c
```

You may wish to comment out the register\_giop\_user\_module() code and that will leave you with heuristic dissection.

If you don't want to use the shell script wrapper, then try steps 3 or 4 instead.

3. To write the C code to stdout.

Usage: omniidl -p ./ -b wireshark\_be <your file.idl>

e.g.:

```
omniidl -p ./ -b wireshark_be echo.idl
```

4. To write to a file, just redirect the output.

omniidl -p ./ -b wireshark\_be echo.idl > packet-test-idl.c

You may wish to comment out the register\_giop\_user\_module() code and that will leave you with heuristic dissection.

5. Copy the resulting C code to subdirectory epan/dissectors/ inside your Wireshark source directory.

cp packet-test-idl.c /dir/where/wireshark/lives/epan/dissectors/

The new dissector has to be added to Makefile.common in the same directory. Look for the declaration CLEAN\_DISSECTOR\_SRC and add the new dissector there. For example,

```
CLEAN_DISSECTOR_SRC = \
packet-2dparityfec.c \
packet-3com-njack.c \
...
```

becomes

```
CLEAN_DISSECTOR_SRC = \
packet-test-idl.c \
packet-2dparityfec.c \
packet-3com-njack.c \
...
```

For the next steps, go up to the top of your Wireshark source directory.

6. Run configure

./configure (or ./autogen.sh)

7. Compile the code

make

8. Good Luck !!

## D.10.4. TODO

- 1. Exception code not generated (yet), but can be added manually.
- 2. Enums not converted to symbolic values (yet), but can be added manually.
- 3. Add command line options etc
- 4. More I am sure :-)

## D.10.5. Limitations

See the TODO list inside packet-giop.c

## D.10.6. Notes

- 1. The "-p ./" option passed to omniidl indicates that the wireshark\_be.py and wireshark\_gen.py are residing in the current directory. This may need tweaking if you place these files somewhere else.
- 2. If it complains about being unable to find some modules (e.g. tempfile.py), you may want to check if PYTHONPATH is set correctly. On my Linux box, it is PYTHONPATH=/usr/lib/python2.4/

# Appendix E. This Document's License (GPL)

As with the original license and documentation distributed with Wireshark, this document is covered by the GNU General Public License (GNU GPL).

If you haven't read the GPL before, please do so. It explains all the things that you are allowed to do with this code and documentation.

GNU GENERAL PUBLIC LICENSE Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users. This General Public License applies to most of the Free Software Foundation's software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Library General Public License instead.) You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free

program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

GNU GENERAL PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you".

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.

1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

a) You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.

b) You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.

c) If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:

a) Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,

b) Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,

c) Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.

6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.

7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.

10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free

Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

#### NO WARRANTY

11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

<one line to give the program's name and a brief idea of what it does.>
Copyright (C) <year> <name of author>

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA

Also add information on how to contact you by electronic and paper mail.

If the program is interactive, make it output a short notice like this when it starts in an interactive mode:

Gnomovision version 69, Copyright (C) year name of author Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type `show w'. This is free software, and you are welcome to redistribute it under certain conditions; type `show c' for details. The hypothetical commands `show w' and `show c' should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than `show w' and `show c'; they could even be mouse-clicks or menu items--whatever suits your program.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the program, if necessary. Here is a sample; alter the names:

Yoyodyne, Inc., hereby disclaims all copyright interest in the program `Gnomovision' (which makes passes at compilers) written by James Hacker.

<signature of Ty Coon>, 1 April 1989 Ty Coon, President of Vice

This General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Library General Public License instead of this License.