

Dell Data Security

Endpoint Security Suite Pro Advanced Installation Guide
v1.8



Notes, cautions, and warnings

NOTE: A NOTE indicates important information that helps you make better use of your product.

CAUTION: A CAUTION indicates either potential damage to hardware or loss of data and tells you how to avoid the problem.

WARNING: A WARNING indicates a potential for property damage, personal injury, or death.

© 2017 Dell Inc. All rights reserved. Dell, EMC, and other trademarks are trademarks of Dell Inc. or its subsidiaries. Other trademarks may be trademarks of their respective owners.

Registered trademarks and trademarks used in the Dell Encryption, Endpoint Security Suite Pro, Endpoint Security Suite Enterprise, and Data Guardian suite of documents: Dell™ and the Dell logo, Dell Precision™, OptiPlex™, ControlVault™, Latitude™, XPS®, and KACE™ are trademarks of Dell Inc. Cylance®, CylancePROTECT, and the Cylance logo are registered trademarks of Cylance, Inc. in the U.S. and other countries. McAfee® and the McAfee logo are trademarks or registered trademarks of McAfee, Inc. in the US and other countries. Intel®, Pentium®, Intel Core Inside Duo®, Itanium®, and Xeon® are registered trademarks of Intel Corporation in the U.S. and other countries. Adobe®, Acrobat®, and Flash® are registered trademarks of Adobe Systems Incorporated. Authen Tec® and Eikon® are registered trademarks of Authen Tec. AMD® is a registered trademark of Advanced Micro Devices, Inc. Microsoft®, Windows®, and Windows Server®, Internet Explorer®, MS-DOS®, Windows Vista®, MSN®, ActiveX®, Active Directory®, Access®, ActiveSync®, BitLocker®, BitLocker To Go®, Excel®, Hyper-V®, Silverlight®, Outlook®, PowerPoint®, OneDrive®, SQL Server®, and Visual C++® are either trademarks or registered trademarks of Microsoft Corporation in the United States and/or other countries. VMware® is a registered trademark or trademark of VMware, Inc. in the United States or other countries. Box® is a registered trademark of Box. DropboxSM is a service mark of Dropbox, Inc. Google™, Android™, Google™ Chrome™, Gmail™, YouTube®, and Google™ Play are either trademarks or registered trademarks of Google Inc. in the United States and other countries. Apple®, Aperture®, App StoreSM, Apple Remote Desktop™, Apple TV®, Boot Camp™, FileVault™, iCloud®SM, iPad®, iPhone®, iPhoto®, iTunes Music Store®, Macintosh®, Safari®, and Siri® are either servicemarks, trademarks, or registered trademarks of Apple, Inc. in the United States and/or other countries. GO ID®, RSA®, and SecurID® are registered trademarks of Dell EMC. EnCase™ and Guidance Software® are either trademarks or registered trademarks of Guidance Software. Entrust® is a registered trademark of Entrust®, Inc. in the United States and other countries. InstallShield® is a registered trademark of Flexera Software in the United States, China, European Community, Hong Kong, Japan, Taiwan, and United Kingdom. Micron® and RealSSD® are registered trademarks of Micron Technology, Inc. in the United States and other countries. Mozilla® Firefox® is a registered trademark of Mozilla Foundation in the United States and/or other countries. iOS® is a trademark or registered trademark of Cisco Systems, Inc. in the United States and certain other countries and is used under license. Oracle® and Java® are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners. SAMSUNG™ is a trademark of SAMSUNG in the United States or other countries. Seagate® is a registered trademark of Seagate Technology LLC in the United States and/or other countries. Travelstar® is a registered trademark of HGST, Inc. in the United States and other countries. UNIX® is a registered trademark of The Open Group. VALIDITY™ is a trademark of Validity Sensors, Inc. in the United States and other countries. VeriSign® and other related marks are the trademarks or registered trademarks of VeriSign, Inc. or its affiliates or subsidiaries in the U.S. and other countries and licensed to Symantec Corporation. KVM on IP® is a registered trademark of Video Products. Yahoo!® is a registered trademark of Yahoo! Inc. This product uses parts of the 7-Zip program. The source code can be found at 7-zip.org. Licensing is under the GNU LGPL license + unRAR restrictions (7-zip.org/license.txt).

Endpoint Security Suite Pro Advanced Installation Guide

2017 - 08

Rev. A01

Contents

1 Introduction.....	6
Before You Begin.....	6
Using This Guide.....	7
Contact Dell ProSupport.....	7
2 Requirements.....	9
All Clients.....	9
All Clients - Prerequisites.....	9
All Clients - Hardware.....	9
All Clients - Localization.....	10
Encryption Client.....	10
Encryption Client Prerequisites.....	10
Encryption Client Hardware.....	11
Encryption Client Operating Systems.....	11
Encryption Client Operating Systems with Deferred Activation.....	11
Encryption External Media Operating Systems.....	11
Threat Protection Client.....	12
Threat Protection Client Operating Systems.....	12
Threat Protection Client Ports.....	12
SED Client.....	13
OPAL Drivers.....	14
SED Client Prerequisites.....	14
SED Client Hardware.....	14
Authentication Options with SED Client.....	15
SED Client International Keyboards SED Client Localization SED Client Operating Systems.....	16
Advanced Authentication Client.....	17
Advanced Authentication Client Hardware.....	17
Advanced Authentication Client Operating Systems.....	18
BitLocker Manager Client.....	18
BitLocker Manager Client Prerequisites.....	19
BitLocker Manager Client Operating Systems.....	19
3 Registry Settings.....	20
Encryption Client Registry Settings.....	20
Threat Protection Client Registry Settings.....	24
SED Client Registry Settings.....	24
Advanced Authentication Client Registry Settings.....	26
BitLocker Manager Client Registry Settings.....	26
4 Install Using the Master Installer.....	28
Install Interactively Using the Master Installer.....	28
Install by Command Line Using the Master Installer.....	31



5 Uninstall Using the Endpoint Security Suite Pro Master Installer.....	33
Uninstall the Endpoint Security Suite Pro Master Installer.....	33
Command Line Uninstallation.....	33
6 Install Using the Child Installers.....	34
Install Drivers.....	35
Install Encryption Client.....	35
Command Line Installation.....	35
Install Threat Protection Clients.....	37
Command Line Installation.....	38
Install SED Management and Advanced Authentication Clients.....	39
Command Line Installation.....	39
Install BitLocker Manager Client.....	40
Command Line Installation.....	40
7 Uninstall Using the Child Installers.....	42
Uninstall Threat Protection Clients.....	43
Command Line Uninstallation.....	43
Uninstall Encryption Client.....	43
Process.....	43
Command Line Uninstallation.....	44
Uninstall SED and Advanced Authentication Clients.....	45
Process.....	45
Deactivate the PBA.....	45
Uninstall SED Client and Advanced Authentication Clients.....	46
Uninstall BitLocker Manager Client.....	46
Command Line Uninstallation.....	46
8 Commonly Used Scenarios.....	47
Encryption Client, Threat Protection, and Advanced Authentication.....	48
Encryption Client and Threat Protection.....	49
SED Client (including Advanced Authentication) and Encryption External Media.....	49
BitLocker Manager and Encryption External Media.....	50
9 Pre-Installation Configuration for SED UEFI, and BitLocker Manager.....	51
Initialize the TPM.....	51
Pre-Installation Configuration for UEFI Computers.....	51
Enable Network Connectivity During UEFI Preboot Authentication.....	51
Disable Legacy Option ROMs.....	52
Pre-Installation Configuration to Set Up a BitLocker PBA Partition.....	52
10 Set GPO on Domain Controller to Enable Entitlements.....	53
11 Extract the Child Installers from the Endpoint Security Suite Pro Master Installer.....	56
12 Configure Key Server for Uninstallation of Encryption Client Activated Against Security Management Server.....	57



Services Panel - Add Domain Account User.....	57
Key Server Config File - Add User for Security Management Server Communication.....	58
Sample Configuration File.....	59
Services Panel - Restart Key Server Service.....	59
Remote Management Console - Add Forensic Administrator.....	59
13 Use the Administrative Download Utility (CMGAd).....	61
Use the Administrative Download Utility in Forensic Mode.....	61
Use the Administrative Download Utility in Admin Mode.....	63
14 Configure Deferred Activation.....	65
Deferred Activation Customization.....	65
Prepare the Computer for Installation.....	66
Install the Encryption Client with Deferred Activation.....	66
Activate the Encryption Client with Deferred Activation.....	66
Troubleshoot Deferred Activation.....	67
Troubleshoot Activation.....	67
15 Troubleshooting.....	70
All Clients - Troubleshooting.....	70
All Clients - Protection Status.....	70
Encryption Client Troubleshooting.....	70
Upgrade to the Windows 10 Creators Update.....	70
(Optional) Create an Encryption Removal Agent Log File.....	70
Find TSS Version.....	71
Encryption External Media and PCS Interactions.....	71
Use WSScan.....	71
Use WSProbe.....	75
Check Encryption Removal Agent Status.....	76
SED Client Troubleshooting.....	77
Use the Initial Access Code Policy.....	77
Create a PBA Log File for Troubleshooting.....	78
Dell ControlVault Drivers.....	79
Update Dell ControlVault Drivers and Firmware.....	79
UEFI Computers.....	93
Troubleshoot Network Connection.....	93
TPM and BitLocker.....	93
TPM and BitLocker Error Codes.....	93
16 Glossary.....	124



Introduction

This guide details how to install and configure Threat Protection, the Encryption client, SED management client, Advanced Authentication, and BitLocker Manager.

All policy information, and their descriptions are found in the AdminHelp.

Before You Begin

1 Install the Security Management Server/Security Management Server Virtual before deploying clients. Locate the correct guide as shown below, follow the instructions, and then return to this guide.

- *Dell Security Management Server Installation and Migration Guide*
- *Dell Security Management Server Virtual Quick Start Guide and Installation Guide*

Verify that policies are set as desired. Browse through the AdminHelp, available from the **?** at the far right of the screen. The AdminHelp is page-level help designed to help you set and modify policy and understand your options with your Security Management Server/Security Management Server Virtual.



- 2 Thoroughly read the [Requirements](#) chapter of this document.
- 3 Deploy clients to end users.

Using This Guide

Use this guide in the following order.

- See [Requirements](#) for client prerequisites, computer hardware and software information, limitations, and special registry modifications needed for features.
- If needed, see [Pre-Installation Configuration for SED UEFI, and BitLocker](#).
- If your clients will be entitled using Dell Digital Delivery (DDD), see [Set GPO on Domain Controller to Enable Entitlements](#).
- If installing clients using the Endpoint Security Suite Pro master installer, see:
 - [Install Interactively Using the Master Installer](#)
 - or
 - [Install by Command Line Using the Master Installer](#)
- If installing clients using the child installers, the child installer executable files must be extracted from the master installer. See [Extract the Child Installers from the Master Installer](#), then return here.
- Install Child Installers by Command line:
 - [Install Drivers](#) - Download the appropriate drivers and firmware based on your authentication hardware.
 - [Install Encryption Client](#) - use these instructions to install the Encryption client, which is the component that enforces security policy, whether a computer is connected to the network, disconnected from the network, lost, or stolen.
 - [Install Threat Protection Clients](#) - use these instructions to install the Threat Protection clients, which are comprised of the following policy-based Threat Protection features:
 - Malware Protection - Checks for viruses, spyware, unwanted programs, and other threats by automatically scanning items when users access them or on demand at any time.
 - Client Firewall - Monitors communication between the computer and resources on the network and the Internet. Intercepts suspicious communications.
 - Web Filter - Displays safety ratings and reports for websites during online browsing and searching. Web Filtering enables the site administrator to block access to websites based on safety rating or content.
 - [Install SED Management and Advanced Authentication Clients](#) - use these instructions to install encryption software for SEDs. Although SEDs provide their own encryption, they lack a platform to manage their encryption and policies. With SED management, all policies, storage, and retrieval of encryption keys are available from a single console, reducing the risk that computers are unprotected in the event of loss or unauthorized access.

The Advanced Authentication client manages multiple authentication methods, including PBA for SEDs, Single Sign-on (SSO), and user credentials such as fingerprints and passwords. In addition, it provides Advanced Authentication capabilities to access websites and applications.
 - [Install BitLocker Manager Client](#) - use these instructions to install the BitLocker Manager client, designed to improve the security of BitLocker deployments and to simplify and reduce the cost of ownership.

 **NOTE:**

Most child installers can be installed interactively, but installations are not described in this guide.

- See [Commonly Used Scenarios](#) for scripts of our most commonly used scenarios.

Contact Dell ProSupport

Call 877-459-7304, extension 4310039 for 24x7 phone support for your Dell product.



Additionally, online support for Dell products is available at dell.com/support. Online support includes drivers, manuals, technical advisories, FAQs, and emerging issues.

Be sure to help us quickly connect you to the right technical expert by having your Service Code available when you call.

For phone numbers outside of the United States, check [Dell ProSupport International Phone Numbers](#).



Requirements

All Clients

These requirements apply to all clients. Requirements listed in other sections apply to specific clients.

- IT best practices should be followed during deployment. This includes, but is not limited to, controlled test environments for initial tests, and staggered deployments to users.
- The user account performing the installation/upgrade/uninstallation must be a local or domain administrator user, which can be temporarily assigned by a deployment tool such as Microsoft SMS or Dell KACE. A non-administrator user that has elevated privileges is not supported.
- Back up all important data before beginning installation/uninstallation.
- Do not make changes to the computer, including inserting or removing external (USB) drives during installation.
- Ensure that outbound port 443 is available to communicate with the Security Management Server/Security Management Server Virtual if your master installer clients will be entitled using Dell Digital Delivery (DDD). The entitlement functionality will not work if port 443 is blocked (for any reason). DDD is not used if installing using the child installers.
- Be sure to periodically check www.dell.com/support for the most current documentation and Technical Advisories.

All Clients - Prerequisites

- Microsoft .Net Framework 4.5.2 (or later) is required for the Endpoint Security Suite Pro master installer and child installer clients. The installer *does not* install the Microsoft .Net Framework component.

All computers shipped from the Dell factory are pre-installed with the full version of Microsoft .Net Framework 4.5.2 (or later). However, if you are not installing on Dell hardware or are upgrading the client on older Dell hardware, you should verify which version of Microsoft .Net is installed and update the version **prior to installing the client** to prevent installation/upgrade failures. To verify the version of Microsoft .Net installed, follow these instructions on the computer targeted for installation: [http://msdn.microsoft.com/en-us/library/hh925568\(v=vs.110\).aspx](http://msdn.microsoft.com/en-us/library/hh925568(v=vs.110).aspx). To install Microsoft .Net Framework 4.5.2, go to <https://www.microsoft.com/en-us/download/details.aspx?id=42643>.

- Drivers and firmware for ControlVault, fingerprint readers and smart cards (as shown below) are not included in the Endpoint Security Suite Pro master installer or child installer executable files. The drivers and firmware must be kept up-to-date, and can be downloaded from <http://www.dell.com/support> and selecting your computer model. Download the appropriate drivers and firmware based on your authentication hardware.
 - ControlVault
 - NEXT Biometrics Fingerprint Driver
 - Validity Fingerprint Reader 495 Driver
 - O2Micro Smart Card Driver

All Clients - Hardware

- The following table details supported computer hardware.

Hardware

- Minimum hardware requirements must meet the minimum specifications of the operating system.



All Clients - Localization

- The Encryption, Threat Protection, and BitLocker Manager clients are Multilingual User Interface (MUI) compliant and are localized in the following languages.

Language Support

- | | |
|----------------|--|
| • EN - English | • JA - Japanese |
| • ES - Spanish | • KO - Korean |
| • FR - French | • PT-BR - Portuguese, Brazilian |
| • IT - Italian | • PT-PT - Portuguese, Portugal (Iberian) |
| • DE - German | |

Encryption Client

- The client computer must have network connectivity to activate.
- To reduce initial encryption time, run the Windows Disk Cleanup Wizard to remove temporary files and any other unnecessary data.
- Turn off sleep mode during the initial encryption sweep to prevent an unattended computer from going to sleep. Encryption cannot occur on a sleeping computer (nor can decryption).
- The Encryption client does not support dual boot configurations since it is possible to encrypt system files of the other operating system, which would interfere with its operation.
- The Encryption client now supports Audit Mode. Audit Mode allows administrators to deploy the Encryption client as part of the corporate image, rather than using a third-party SCCM or similar solutions to deploy the Encryption client. For instructions about how to install the Encryption client in a corporate image, see <http://www.dell.com/support/article/us/en/19/SLN304039>.
- The Encryption client has been tested and is compatible with McAfee, the Symantec client, Kaspersky, and MalwareBytes. Hard-coded exclusions are in place in for these anti-virus providers to prevent incompatibilities between anti-virus scanning and encryption. The Encryption client has also been tested with the Microsoft Enhanced Mitigation Experience Toolkit.

If your organization uses an anti-virus provider that is not listed, see <http://www.dell.com/support/article/us/en/19/SLN288353/> or [Contact Dell ProSupport](#) for help.

- The TPM is used for sealing the GPK. Therefore, if running the Encryption client, clear the TPM in the BIOS before installing a new operating system on the client computer.
- Operating system re-install is not supported. To re-install the operating system, perform a backup of the target computer, wipe the computer, install the operating system, then recover the encrypted data following established recovery procedures.

Encryption Client Prerequisites

- The master installer installs the following prerequisites if not already installed on the computer. **When using the child installer**, you must install this component before installing the Encryption client.

Prerequisite

- Visual C++ 2012 Update 4 or later Redistributable Package (x86 and x64)
- Visual C++ 2015 Update 3 or later Redistributable Package (x86 and x64)



Encryption Client Hardware

- The following table details supported hardware.

Optional Embedded Hardware

- TPM 1.2 or 2.0

Encryption Client Operating Systems

- The following table details supported operating systems.

Windows Operating Systems (32- and 64-bit)

- Windows 7 SP0-SP1: Enterprise, Professional, Ultimate
- Windows Embedded Standard 7 with Application Compatibility template (hardware encryption is not supported)
- Windows 8: Enterprise, Pro
- Windows 8.1 Update 0-1: Enterprise Edition, Pro Edition
- Windows Embedded 8.1 Industry Enterprise (hardware encryption is not supported)
- Windows 10: Education, Enterprise, Pro through Creators Update (Redstone 2)
- VMware Workstation 5.5 and higher



NOTE:

When using UEFI mode, the Secure Hibernation policy is not supported.

Encryption Client Operating Systems with Deferred Activation

- Deferred activation allows the Active Directory user account used during activation to be independent of the account used to login to the endpoint. Instead of the network provider capturing the authentication information, the user instead manually specifies the Active Directory-based account when prompted. Once the credentials are entered, the authentication information is securely sent to the Dell Server which validates it against the configured Active Directory domains. For more information, see <http://www.dell.com/support/article/us/en/19/sln306341>.
- The following table details supported operating systems with deferred activation.

Windows Operating Systems (32- and 64-bit)

- Windows 7 SP0-SP1: Home Basic, Home Premium, Enterprise, Professional, Ultimate
- Windows Embedded Standard 7 with Application Compatibility template (hardware encryption is not supported)
- Windows 8: Home Basic, Home Premium, Enterprise, Pro
- Windows 8.1 Update 0-1: Enterprise Edition, Pro Edition
- Windows Embedded 8.1 Industry Enterprise (hardware encryption is not supported)
- Windows 10: Home Basic, Home Premium, Education, Enterprise, Pro through Creators Update (Redstone 2)
- VMware Workstation 5.5 and higher

Encryption External Media Operating Systems

- The following table details the operating systems supported when accessing media protected by Encryption External Media.



NOTE:

External media must have approximately 55MB available plus open space on the media that is equal to the largest file to be encrypted to host Encryption External Media.

NOTE:

Windows XP is supported when using Encryption External Media Explorer only.

Windows Operating Systems Supported to Access Encryption External Media-Protected Media (32- and 64-bit)

- Windows 7 SP0-SP1: Home Basic, Home Premium, Enterprise, Professional, Ultimate
- Windows Embedded Standard 7 with Application Compatibility template (hardware encryption is not supported)
- Windows 8: Home Basic, Home Premium, Enterprise, Pro
- Windows 8.1 Update 0-1: Enterprise Edition, Pro Edition
- Windows Embedded 8.1 Industry Enterprise (hardware encryption is not supported)
- Windows 10: Home Basic, Home Premium, Education, Enterprise, Pro through Creators Update (Redstone 2)

Mac Operating Systems Supported to Access Encryption External Media-Protected Media (64-bit kernels)

- Mac OS X Yosemite 10.10.5
- Mac OS X El Capitan 10.11.6
- macOS Sierra 10.12.5 and 10.12.6

Threat Protection Client

- The Threat Protection clients cannot be installed without the Encryption client being detected on the computer. Installation will fail if attempted.
- To successfully install Threat Protection, the computer must have network connectivity.
- Uninstall other vendors' anti-virus, anti-malware, anti-spyware, and firewall applications before installing the Threat Protection clients to prevent installation failures. Conflicting software does not include Windows Defender and Endpoint Security Suite Pro.
- The Web Protection feature is supported with Internet Explorer only.

Threat Protection Client Operating Systems

- The following table details supported operating systems.

Windows Operating Systems (32- and 64-bit)

- Windows 7 SP0-SP1: Enterprise, Professional, Ultimate
- Windows 8: Enterprise, Pro
- Windows 8.1 Update 0-1: Enterprise Edition, Pro Edition
- Windows 10: Education, Enterprise, Pro through Creators Update (Redstone 1)

Threat Protection Client Ports

- To ensure that Threat Protection clients receive the most current Threat Protection updates, ports 443 and 80 must be available for the client to communicate with the various destination servers. If the ports are blocked for any reason, anti-virus signature updates (DAT files) cannot be downloaded, so computers may not have the most current protection. Ensure that client computers can access the URLs, as follows.



Use	Application Protocol	Transport Protocol	Port Number	Destination	Direction	Notes
Anti-virus Updates	HTTP	TCP	443/fallback 80	vs.mcafeeasap.com	Outbound	
Anti-virus Engine/ Signature Updates	SSL	TCP	443	vs.mcafeeasap.com	Outbound	
Anti-Spam Engine	HTTP	TCP	443	vs.mcafeeasap.com	Outbound	
Anti-Spam Rules and Streaming Updates	HTTP	TCP	80	vs.mcafeeasap.com	Outbound	Packet types: X-SU3X-SU3-Component-Name X-SU3-Component-Type X-SU3-Status
Reputation Service	SSL	TCP	443	tunnel.web.trustedsource.org	Outbound	
Reputation Service Feedback	SSL	TCP	443	gtifedback.trustedsource.org	Outbound	
Quarantine Manager	HTTP	TCP	80	Your Security Management Server/Security Management Server Virtual	Bi-directional	
	HTTPS		443			
URL Reputation Database Update	HTTP	TCP	80	list.smartfilter.com	Outbound	
URL Reputation Lookup	SSL	TCP	443	tunnel.web.trustedsource.org	Outbound	

SED Client

- The computer must have a wired network connection to successfully install SED management.
- IPv6 is not supported.
- Be prepared to shut down and restart the computer after you apply policies and are ready to begin enforcing them.
- Computers equipped with self-encrypting drives cannot be used with HCA cards. Incompatibilities exist that prevent the provisioning of the HCA. Dell does not sell computers with self-encrypting drives that support the HCA module. This unsupported configuration would be an after-market configuration.
- If the computer targeted for encryption is equipped with a self-encrypting drive, ensure that the Active Directory option, *User Must Change Password at Next Logon*, is disabled. Preboot Authentication does not support this Active Directory option.
- Dell recommends that you do not change the authentication method after the PBA has been activated. If you must switch to a different authentication method, you must either:
 - Remove all the users from the PBA.
 - or
 - Deactivate the PBA, change the authentication method, and then re-activate the PBA.

IMPORTANT:

Due to the nature of RAID and SEDs, SED management does not support RAID. The issue with *RAID=On* with SEDs is that RAID requires access to the disk to read and write RAID-related data at a high sector not available on a locked SED from start and cannot wait to read this data until after the user is logged on. Change the SATA operation in the BIOS from *RAID=On* to *AHCI* to resolve the issue. If the operating system does not have the AHCI controller drivers pre-installed, the operating system will blue screen when switched from *RAID=On* to *AHCI*.



- Configuration of self-encrypting drives for Dell's SED management differ between NVMe and non-NVMe (SATA) drives, as follows.
 - Any NVMe drive that is being leveraged as an SED – The BIOS' SATA operation must be set to RAID ON, as Dell's SED management does not support AHCI on NVMe drives.
 - Any NVMe drive that is being leveraged as an SED – The BIOS's boot mode must be UEFI and Legacy option ROMs must be disabled.
 - Any non-NVMe drive that is being leveraged as an SED – The BIOS' SATA operation must be set to AHCI, as Dell's SED management does not support RAID with non-NVMe drives.
 - RAID ON is not supported because access to read and write RAID-related data (at a sector that is not available on a locked non-NVMe drive) is not accessible at start-up, and cannot wait to read this data until after the user is logged on.
 - The operating system will crash when switched from RAID ON > AHCI if the AHCI controller drivers are not pre-installed. For instructions on how to switch from RAID > AHCI (or vice versa), see <http://www.dell.com/support/article/us/en/19/SLN306460>.

Supported OPAL compliant SEDs require updated Intel Rapid Storage Technology Drivers, located at <http://www.dell.com/support/home/us/en/19/product-support/product/dell-dp-endpt-security-suite/drivers>. Dell recommends Intel Rapid Storage Technology Driver version 15.2.0.0 or later, with NVMe drives.

- SED Management is not supported with Server Encryption.

OPAL Drivers

- Supported OPAL compliant SEDs require updated Intel Rapid Storage Technology Drivers, located at <http://www.dell.com/support>.

SED Client Prerequisites

- The Endpoint Security Suite Pro master installer installs the following prerequisites if not already installed on the computer. **When using the child installer**, you must install these components before installing SED management.

Prerequisites

- Visual C++ 2012 Update 4 or later Redistributable Package (x86 and x64)
- Visual C++ 2015 Update 3 or later Redistributable Package (x86 and x64)

SED Client Hardware

OPAL Compliant SEDs

- For the most up-to-date list of Opal compliant SEDs supported with the SED management, refer to this KB article: <http://www.dell.com/support/article/us/en/19/SLN296720>.

Dell Computer Models Supported with UEFI

- The following table details Dell computer models supported with UEFI.

Dell Computer Models - UEFI Support

Latitude 3180	Precision M3510	Optiplex 3040 Micro, Mini Tower, Small Form Factor	Venue Pro 11 (Models 5175/5179)
Latitude 3189	Precision M3520	Optiplex 3046	Venue Pro 11 (Model 7139)
Latitude 3380	Precision M4800	OptiPlex 3050 All-In-One	
Latitude 3480	Precision M5510	OptiPlex 3050 Tower, Small Form Factor, Micro	
Latitude 3580	Precision M5520	Optiplex 5040 Mini Tower, Small Form Factor	
Latitude 5280	Precision M6800		
Latitude 5480	Precision M7510		
	Precision M7520		



Dell Computer Models - UEFI Support

- Latitude 5580
 - Latitude 7370
 - Latitude 7380
 - Latitude E5270
 - Latitude E5285
 - Latitude E5289 2-in-1
 - Latitude E5470
 - Latitude E5570
 - Latitude E7240
 - Latitude E7250
 - Latitude E7260
 - Latitude E7265
 - Latitude E7270
 - Latitude E7275
 - Latitude E7280
 - Latitude E7350
 - Latitude 7389 2-in-1
 - Latitude E7440
 - Latitude E7450
 - Latitude E7460
 - Latitude E7470
 - Latitude E7480
 - Latitude 12 Rugged Extreme
 - Latitude 12 Rugged Tablet (Model 7202)
 - Latitude 14 Rugged Extreme
 - Latitude 14 Rugged
- Precision M7710
 - Precision M7720
 - Precision D5720 All-in-One
 - Precision T3420
 - Precision T3620
 - Precision T7810
 - XPS 15 9560
- OptiPlex 5050 Tower, Small Form Factor, Micro
 - OptiPlex 7020
 - Optiplex 7040 Micro, Mini Tower, Small Form Factor
 - OptiPlex 7050 Tower, Small Form Factor, Micro
 - Optiplex 3240 All-In-One
 - OptiPlex 5250 All-In-One
 - Optiplex 7440 All-In-One
 - OptiPlex 7450 All-In-One
 - OptiPlex 9020 Micro



NOTE:

Authentication features are supported with UEFI mode on these computers running Windows 8, Windows 8.1, and Windows 10 with qualified [Opal Compliant SEDs](#). Other computers running Windows 7, Windows 8, Windows 8.1, and Windows 10 support Legacy Boot mode.

- For a list of docking stations and adapters supported with the SED client, see <http://www.dell.com/support/article/us/en/19/sln296720/>.

Authentication Options with SED Client

- Specific hardware is required, to use [smart cards](#) and to [authenticate on UEFI computers](#). Configuration is required to use [smart cards with Preboot Authentication](#). The following tables show authentication options available by operating system, when hardware and configuration requirements are met.

Non-UEFI

	PBA			
	Password	Fingerpr t	Contacted Smart card	SIPR Card
Windows 7 SP0- SP1	X ¹		X ^{1,2}	
Windows 8	X ¹		X ^{1,2}	



Non-UEFI

PBA				
	Password	Fingerprint	Contacted Smart card	SIPR Card
Windows 8.1	X ¹		X ^{1,2}	
Windows 10	X ¹		X ^{1,2}	

1. Available when authentication drivers are downloaded from support.dell.com.

2. Available with a supported OPAL SED.

UEFI

PBA - on supported Dell computers				
	Password	Fingerprint	Contacted Smart card	SIPR Card
Windows 7				
Windows 8	X ¹		X ¹	
Windows 8.1	X ¹		X ¹	
Windows 10	X ¹		X ¹	

1. Available with a supported OPAL SED on supported UEFI computers.

SED Client International Keyboards

- The following table lists international keyboards supported with Preboot Authentication on UEFI and non-UEFI computers.

International Keyboard Support - UEFI

- DE-CH - Swiss German
- DE-FR - Swiss French

International Keyboard Support - Non-UEFI

- AR - Arabic (using Latin letters)
- DE-CH - Swiss German
- DE-FR - Swiss French

SED Client Localization

The SED and Advanced Authentication clients are Multilingual User Interface (MUI) compliant and are localized the following languages. UEFI Mode and Preboot Authentication are supported in the following languages **except** Russian, Traditional Chinese, or Simplified Chinese.



Language Support

- EN - English
- FR - French
- IT - Italian
- DE - German
- ES - Spanish
- JA - Japanese
- KO - Korean
- ZH-CN - Chinese, Simplified
- ZH-TW - Chinese, Traditional/Taiwan
- PT-BR - Portuguese, Brazilian
- PT-PT - Portuguese, Portugal (Iberian)
- RU - Russian

SED Client Operating Systems

- The following table details the supported operating systems.

Windows Operating Systems (32- and 64-bit)

- Windows 7 SP0-SP1: Enterprise, Professional (supported with Legacy Boot mode but not UEFI)



NOTE:

Legacy Boot mode is supported on Windows 7. UEFI is not supported on Windows 7.

NVMe self-encrypting drives are not supported with Windows 7.

- Windows 8: Enterprise, Pro,
- Windows 8.1: Enterprise Edition, Pro Edition
- Windows 10: Education, Enterprise, Pro through Creators Update (Redstone 2)

Advanced Authentication Client

- When using Advanced Authentication, users will be securing access to the computer using advanced authentication credentials that are managed and enrolled using Advanced Authentication. Advanced Authentication will be the primary manager of the authentication credentials for Windows Sign-in, including Windows password, fingerprint, and smart cards. Picture password, PIN, and fingerprint credentials enrolled using the Microsoft Operating System will not be recognized at Windows Sign-in.

To continue using the Microsoft Operating System to manage user credentials, do not install Advanced Authentication or uninstall it.

- An SED does not require a TPM to provide Advanced Authentication or encryption.

Advanced Authentication Client Hardware

- The following table details supported authentication hardware.

Fingerprint and Smart Card Readers

- Validity VFS495 in Secure Mode
- ControlVault Swipe Reader
- UPEK TCS1 FIPS 201 Secure Reader 1.6.3.379
- AuthenTec Eikon and Eikon To Go USB Readers



Contactless Cards

- Contactless Cards using Contactless Card Readers built-in to specified Dell laptops

Smart Cards

- PKCS #11 Smart Cards using the [ActivIdentity](#) client



NOTE:

The ActivIdentity client is not pre-loaded and must be installed separately.

- CSP Cards
 - Common Access Cards (CACs)
 - Class B/SIPR Net Cards
- The following table details Dell computer models supported with SIPR Net cards.

Dell Computer Models - Class B/SIPR Net Card Support

- | | | |
|------------------|-------------------|------------------------------|
| • Latitude E6440 | • Precision M2800 | • Latitude 14 Rugged Extreme |
| • Latitude E6540 | • Precision M4800 | • Latitude 12 Rugged Extreme |
| | • Precision M6800 | • Latitude 14 Rugged |

Advanced Authentication Client Operating Systems

Windows Operating Systems

- The following table details supported operating systems.

Windows Operating Systems (32- and 64-bit)

- Windows 7 SP0-SP1: Enterprise, Professional, Ultimate
- Windows 8: Enterprise, Pro
- Windows 8.1 Update 0-1: Enterprise Edition, Pro Edition
- Windows 10: Education, Enterprise, Pro through Creators Update (Redstone 2)



NOTE: UEFI mode is not supported on Windows 7.

BitLocker Manager Client

- Consider reviewing [Microsoft BitLocker requirements](#) if BitLocker is not yet deployed in your environment.
- Ensure that the PBA partition is already set up. If BitLocker Manager is installed before the PBA partition is set up, BitLocker cannot be enabled and BitLocker Manager will not be operational. See [Pre-Installation Configuration to Set Up a BitLocker PBA Partition](#).
- The keyboard, mouse, and video components must be directly connected to the computer. Do not use a KVM switch to manage peripherals as the KVM switch can interfere with the computer's ability to properly identify hardware.
- Turn on and enable the TPM. BitLocker Manager will take ownership of the TPM and will not require a reboot. However, if a TPM ownership already exists, BitLocker Manager will begin the encryption setup process (no restart is required). The point is that the TPM must be "owned" and enabled.
- The BitLocker Manager client will use the approved AES FIPS validated algorithms if FIPS mode is enabled for the GPO security setting "System cryptography: Use FIPS compliant algorithms for encryption, hashing, and signing" on the device and you manage that device via our product. We do not force this mode as default for BitLocker-encrypted clients because Microsoft now suggests customers not use their FIPS validated encryption due to numerous issues with application compatibility, recovery, and media encryption: <http://blogs.technet.com>.



BitLocker Manager Client Prerequisites

- The Endpoint Security Suite Pro master installer installs the following prerequisites if not already installed on the computer. **When using the child installer**, you must install these components before installing BitLocker Manager.

Prerequisites

- Visual C++ 2012 Update 4 or later Redistributable Package (x86 and x64)
- Visual C++ 2015 Update 3 or later Redistributable Package (x86 and x64)

BitLocker Manager Client Operating Systems

- The following table details supported operating systems.

Windows Operating Systems

- Windows 7 SP0-SP1: Enterprise, Ultimate (32- and 64-bit)
- Windows 8: Enterprise (64-bit)
- Windows 8.1: Enterprise Edition, Pro Edition (64-bit)
- Windows 10: Education, Enterprise, Pro through Creators Update (Redstone 2)
- Windows Server 2008 R2: Standard Edition, Enterprise Edition (64-bit)
- Windows Server 2012
- Windows Server 2012 R2: Standard Edition, Enterprise Edition (64-bit)
- Windows Server 2016



Registry Settings

- This section details all Dell ProSupport approved registry settings for local **client** computers, regardless of the reason for the registry setting. If a registry setting overlaps two products, it will be listed in each category.
- These registry changes should be done by Administrators only and may not be appropriate or work in all scenarios.

Encryption Client Registry Settings

- If a self-signed certificate is used on the Dell Security Management Server for Windows, certificate trust validation must remain disabled on the client computer (trust validation is *disabled* by default with Security Management Server for Windows). Before *enabling* trust validation on the client computer, the following requirements must be met.
 - A certificate signed by a root authority, such as EnTrust or Verisign, must be imported into Security Management Server/Security Management Server Virtual.
 - The full chain of trust of the certificate must be stored in the Microsoft keystore on the client computer.
 - To *enable* trust validation for the Encryption client, change the value of the following registry entry to 0 on the client computer.

[HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield]

"IgnoreCertErrors"=DWORD:00000000

0 = Fail if a certificate error is encountered

1= Ignores errors

- To use smart cards with Windows Authentication, the following registry value must be set on the client computer.

[HKLM\SOFTWARE\DigitalPersona\Policies\Default\SmartCards]

"MSSmartcardSupport"=DWORD:1

- To create an Encryption Removal Agent log file, create the following registry entry on the computer targeted for decryption. See [\(Optional\) Create an Encryption Removal Agent Log File](#).

[HKLM\Software\Credant\DecryptionAgent]

"LogVerbosity"=DWORD:2

0: no logging

1: logs errors that prevent the Service from running

2: logs errors that prevent complete data decryption (recommended level)

3: logs information about all decrypting volumes and files

5: logs debugging information

- By default, during installation, the system tray icon is displayed. Use the following registry setting to hide the system tray icon for all managed users on a computer after the original installation. Create or modify the registry setting as follows:

[HKLM\Software\CREDANT\CMGShield]

"HIDESYSTRAYICON"=DWORD:1

- By default, all temporary files in the c:\windows\temp directory are automatically deleted during installation. Deletion of temporary files speeds initial encryption and occurs before the initial encryption sweep.

However, if your organization uses a third-party application that requires the file structure within the \temp directory to be preserved, you should prevent this deletion.

To disable temporary file deletion, create or modify the registry setting as follows:

[HKLM\SOFTWARE\CREDANT\CMGShield]

"DeleteTempFiles"=REG_DWORD:0

Not deleting temporary files increases initial encryption time.

- The Encryption client displays the *length of each policy update delay* prompt for five minutes each time. If the user does not respond to the prompt, the next delay begins. The final delay prompt includes a countdown and progress bar, and it displays until the user responds, or the final delay expires and the required logoff/reboot occurs.

You can change the behavior of the user prompt to begin or delay encryption, to prevent encryption processing following no user response to the prompt. To do this, set the registry the following registry value:

[HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield]

"SnoozeBeforeSweep"=DWORD:1

Any non-zero value will change the default behavior to snooze. With no user interaction, encryption processing will be delayed up to the number of configurable allowed delays. Encryption processing begins when the final delay expires.

Calculate the maximum possible delay as follows (a maximum delay would involve the user never responding to a delay prompt, each of which displays for 5 minutes):

(NUMBER OF POLICY UPDATE DELAYS ALLOWED × LENGTH OF EACH POLICY UPDATE DELAY) + (5 MINUTES × [NUMBER OF POLICY UPDATE DELAYS ALLOWED - 1])

- Use the following registry setting to have the Encryption client poll the Security Management Server/Security Management Server Virtual for a forced policy update. Create or modify the registry setting as follows:

[HKLM\SOFTWARE\Credant\CMGShield\Notify]

"PingProxy"=DWORD value:1

The registry setting will automatically disappear when done.

- Use the following registry settings to either allow the Encryption client to send an optimized inventory to the Security Management Server/Security Management Server Virtual, send a full inventory to the Security Management Server/Security Management Server Virtual, or to send a full inventory for all activated users to the Security Management Server/Security Management Server Virtual.

- Send Optimized Inventory to Security Management Server/Security Management Server Virtual:

Create or modify the registry setting as follows:

[HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield]

"OnlySendInvChanges"=REG_DWORD:1

If no entry is present, optimized inventory is sent to the Security Management Server/Security Management Server Virtual.

- Send Full Inventory to Security Management Server/Security Management Server Virtual:

Create or modify the registry setting as follows:

[HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield]



"OnlySendInvChanges"=REG_DWORD:0

If no entry is present, optimized inventory is sent to the Security Management Server/Security Management Server Virtual.

- Send Full Inventory for All Activated Users

[HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield]

"RefreshInventory"=REG_DWORD:1

This entry is deleted from the registry as soon as it is processed. The value is saved in the vault, so even if the computer is rebooted before the inventory upload takes place, the Encryption client still honors this request the next successful inventory upload.

This entry supersedes the OnlySendInvChanges registry value.

- Slotted Activation is a feature that allows you to spread activations of clients over a set time period in order to ease Security Management Server/Security Management Server Virtual load during a mass deployment. Activations are delayed based on algorithmically generated time slots to provide a smooth distribution of activation times.

For users requiring activation through VPN, a slotted activation configuration for the client may be required, to delay initial activation for long enough to allow time for the VPN client to establish a network connection.

These registry entries require a restart of the computer for the updates to take effect.

- **Slotted Activation**

To enable or disable this feature, create a DWORD with the name **SlottedActivation** under the following parent key:

[HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield\]

- **Activation Slot**

To enable or disable this feature, create a subkey with the name **ActivationSlot** under the following parent key:

[HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield\]

Activation Slot - a string that defines the period within which the Dell Encryption client will attempt to activate with the Security Management Server/Security Management Server Virtual. These values are defined in seconds, and the syntax is defined by <lowervalue>,<uppervalue>. An example would be 120,300. This means that the Encryption client will attempt to activate at a random time between 2 minutes and 5 minutes after user login.

- **Calendar Repeat**

To enable or disable this feature, create a subkey with the name **CalRepeat** under the following parent key:

[HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield\ActivationSlot]

CalRepeat - A DWORD that defines the time period in seconds that the activation slot interval occurs. Use this setting to override the time period in seconds that the activation slot interval occurs. 25200 seconds are available for slotting activations during a seven-hour period. The default setting is 86400 seconds, which represents a daily repeat. The suggested decimal value is 600, which represents 10 minutes.

- **Slot Interval**

To enable or disable this feature, create a subkey with the name **SlotInterval** under the following parent key:

[HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield\ActivationSlot]

Slot Interval - A string value that defines the intervals between slot activations. The suggested setting is 45,120. This represents activation time being randomly assigned between 45 and 120 seconds.

- **Missed Threshold**

To enable or disable this feature, create a subkey with the name **MissThreshold** under the following parent key:



[HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield\ActivationSlot]

MissThreshold - a DWORD value that contains a positive integer that defines the number of attempts to activate before a log off is required. If the MissThreshold is reached, activation attempts will cease until the next login for the unactivated user. The count for MissThreshold is always reset on logoff.

The following registry keys collect slotted activation user data:

[HKCU/Software/CREDANT/ActivationSlot] (per-user data)

Deferred time to attempt the slotted activation, which is set when the user logs onto the network for the first time after slotted activation is enabled. The activation slot is recalculated for each activation attempt.

[HKCU/Software/CREDANT/SlotAttemptCount] (per-user data)

Number of failed or missed attempts, when the time slot arrives and activation is attempted but fails. When this number reaches the value set in ACTIVATION_SLOT_MISSTHRESHOLD, the computer attempts one immediate activation upon connecting to the network.

- To detect unmanaged users on the client computer, set the following registry value on the client computer:

[HKLM\SOFTWARE\Credant\CMGShield\ManagedUsers\]

"UnmanagedUserDetected"=DWORD value:1

Detect unmanaged users on this computer=1

Do not detect unmanaged users on this computer=0

- To enable silent automatic reactivation in the rare case that a user becomes deactivated, the following registry value must be set on the client computer.

[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\CMGShield]

"AutoReactivation"=DWORD:00000001

0=Disabled (default)

1=Enabled

- System Data Encryption (SDE) is enforced based on the policy value for SDE Encryption Rules. Additional directories are protected by default when the SDE Encryption Enabled policy is Selected. For more information, search "SDE Encryption Rules" in AdminHelp. When the Encryption client is processing a policy update that includes an active SDE policy, the current user profile directory is encrypted by default with the SDUser key (a User key) rather than the SDE key (a Device key). The SDUser key is also used to encrypt files or folders that are copied (not moved) into a user directory that is not a encrypted with SDE.

To disable the SDUser key and use the SDE key to encrypt these user directories, create the following registry entry on the computer:

[HKEY_LOCAL_MACHINE\SOFTWARE\Credant\CMGShield]

"EnableSDUserKeyUsage"=DWORD:00000000

If this registry key is not present or is set to anything other than 0, the SDUser key will be used to encrypt these user directories.

For more information about SDUser, see www.dell.com/support/article/us/en/19/SLN304916

- Setting the registry entry, EnableNGMetadata, if issues occur related with Microsoft updates on computers with Common key-encrypted data or with encrypting, decrypting, or unzipping large numbers of files within a folder.

Set the EnableNGMetadata registry entry in the following location:

[HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services\CmgShieldFFE]



"EnableNGMetadata" = DWORD:1

0=Disabled (default)

1=Enabled

- The non-domain activation feature can be enabled by contacting Dell ProSupport and requesting instructions.

Threat Protection Client Registry Settings

- Threat Protection events that the client sends to the Security Management Server/Security Management Server Virtual are not automatically archived on the client computer. Set the following registry key to archive events on the client computer, for example, if Security Management Server/Security Management Server Virtual access is unavailable.

[HKLM\Software\Dell\Dell Data Protection\ThreatProtection]

"ArchiveEvents"=DWORD:1

0=Disabled, 1=Enabled

Log verbosity is set to Warning by default. To configure Debug log verbosity, set the following registry key.

[HKLM\Software\Dell\Dell Data Protection]

"LogVerbosity"=DWORD:10

10=Debug verbosity

- Pop-up notifications display on the client computer when a threat is detected. Set this registry key to 1 to suppress the notifications.

[HKLM\Software\Dell\Dell Data Protection]

"DDPTPHideToasters"=DWORD:1

0=Disabled (default), 1=Enabled (suppress notifications)

To display notifications of a minimum severity level, set this registry key.

[HKLM\Software\Dell\Dell Data Protection]

"DDPTPEventSeverityFilter"=DWORD:3

0=Information (displays all events), 1=Warning, 2=Minor, 3=Major (default, show Major and Critical only), 4=Critical

If "DDPTPHideToasters" is set to 1, settings for "DDPTPEventSeverityFilter" are ignored.

SED Client Registry Settings

- To set the retry interval when the Security Management Server/Security Management Server Virtual is unavailable to communicate with the SED client, add the following registry value.

[HKLM\System\CurrentControlSet\Services\DellMgmtAgent\Parameters]

"CommErrorSleepSecs"=DWORD:300

This value is the number of seconds the SED client waits to attempt to contact the Security Management Server/Security Management Server Virtual if it is unavailable to communicate with the SED client. The default is 300 seconds (5 minutes).



- If a self-signed certificate is used on the Security Management Server/Security Management Server Virtual for SED management, SSL/TLS trust validation must remain disabled on the client computer (SSL/TLS trust validation is *disabled* by default with SED management). Before *enabling* SSL/TLS trust validation on the client computer, the following requirements must be met.
 - A certificate signed by a root authority, such as EnTrust or Verisign, must be imported into Security Management Server/Security Management Server Virtual.
 - The full chain of trust of the certificate must be stored in the Microsoft keystore on the client computer.
 - To *enable* SSL/TLS trust validation for SED management, change the value of the following registry entry to 0 on the client computer.

[HKLM\System\CurrentControlSet\Services\DellMgmtAgent\Parameters]

"DisableSSLCertTrust"=DWORD:0

0 = Enabled

1 = Disabled

- To use smart cards with Windows Authentication, the following registry value must be set on the client computer.

[HKLM\SOFTWARE\DigitalPersona\Policies\Default\SmartCards]

"MSSmartcardSupport"=DWORD:1

- To use smart cards with Preboot Authentication, the following registry value must be set on the client computer. Also set the Authentication Method policy to Smart Card in the Remote Management Console, and commit the change.

[HKLM\SOFTWARE\DigitalPersona\Policies\Default\SmartCards]

"MSSmartcardSupport"=DWORD:1

- To determine if the PBA is activated, ensure that the following value is set:

[HKLM\SYSTEM\CurrentControlSet\services\DellMgmtAgent\Parameters]

"PBAIsActivated"=DWORD (32-bit):1

A value of 1 means that the PBA is activated. A value of 0 means the PBA is not activated.

- To set the interval at which the SED client will attempt to contact the Security Management Server/Security Management Server Virtual when it is unavailable to communicate with the SED client, set the following value on the client computer:

[HKLM\System\CurrentControlSet\Services\DellMgmtAgent\Parameters]

"CommErrorSleepSecs"=DWORD Value:300

This value is the number of seconds the SED client waits to attempt to contact the Security Management Server/Security Management Server Virtual if it is unavailable to communicate with the SED client. The default is 300 seconds (5 minutes).

- The Security Server host may be changed from the original installation location if needed. The host information is read by the client computer every time a policy poll occurs. Change the following registry value on the client computer:

[HKLM\SYSTEM\CurrentControlSet\services\DellMgmtAgent]

"ServerHost"=REG_SZ:<newname>.<organization>.com

- The Security Server port may be changed from the original installation location if needed. This value is read by the client computer every time a policy poll occurs. Change the following registry value on the client computer:

[HKLM\SYSTEM\CurrentControlSet\services\DellMgmtAgent]

ServerPort=REG_SZ:8888



- The Security Server URL may be changed from the original install location if needed. This value is read by the client computer every time a policy poll occurs. Change the following registry value on the client computer:

```
[HKLM\SYSTEM\CurrentControlSet\services\DellMgmtAgent]
```

```
"ServerUrl"=REG_SZ:https://<newname>.<organization>.com:8888/agent
```

Advanced Authentication Client Registry Settings

- If you **do not** want the Advanced Authentication client to change the services associated with smart cards and biometric devices to a startup type of "automatic", disable the service startup feature. Disabling this feature also suppresses warnings associated with the required services not running.

When **disabled**, Advanced Authentication will not attempt to start these services:

- SCardSvr - Manages access to smart cards read by the computer. If this service is stopped, this computer will be unable to read smart cards. If this service is disabled, any services that explicitly depend on it will fail to start.
- SCPolicySvc - Allows the system to be configured to lock the user desktop upon smart card removal.
- WbioSrv - The Windows biometric service gives client applications the ability to capture, compare, manipulate, and store biometric data without gaining direct access to any biometric hardware or samples. The service is hosted in a privileged SVCHOST process.

By default, if the registry key does not exist or the value is set to 0, this feature is enabled.

```
[HKLM\SOFTWARE\DELL\Dell Data Protection]
```

```
SmartCardServiceCheck=REG_DWORD:0
```

0 = Enabled

1 = Disabled

- To use smart cards with Windows Authentication, the following registry value must be set on the client computer.

```
[HKLM\SOFTWARE\DigitalPersona\Policies\Default\SmartCards]
```

```
"MSSmartcardSupport"=DWORD:1
```

- To use smart cards with SED Preboot Authentication, the following registry value must be set on the client computer that is equipped with an SED.

```
[HKLM\SOFTWARE\DigitalPersona\Policies\Default\SmartCards]
```

```
"MSSmartcardSupport"=DWORD:1
```

Set the Authentication Method policy to Smart Card in the Remote Management Console, and commit the change.

BitLocker Manager Client Registry Settings

- If a self-signed certificate is used on the Security Management Server/Security Management Server Virtual for BitLocker Manager, SSL/TLS trust validation must remain disabled on the client computer (SSL/TLS trust validation is *disabled* by default with BitLocker Manager). Before *enabling* SSL/TLS trust validation on the client computer, the following requirements must be met.

- A certificate signed by a root authority, such as EnTrust or Verisign, must be imported into Security Management Server/Security Management Server Virtual .
- The full chain of trust of the certificate must be stored in the Microsoft keystore on the client computer.
- To *enable* SSL/TLS trust validation for BitLocker Manager, change the value of the following registry entry to 0 on the client computer.

```
[HKLM\System\CurrentControlSet\Services\DellMgmtAgent\Parameters]
```



"DisableSSLCertTrust"=DWORD:0

0 = Enabled

1 = Disabled



Install Using the Master Installer


- Command line switches and parameters are case-sensitive.
 - To install using non-default ports, use the child installers instead of the master installer.
 - Endpoint Security Suite Pro master installer log files are located at **C:\ProgramData\Dell\Dell Data Protection\Installer**.
 - Instruct users to see the following document and help files for application assistance:
 - See the *Dell Encrypt Help* to learn how to use the feature of the Encryption client. Access the help from **<Install dir>\Program Files\Dell\Dell Data Protection\Encryption\Help**.
 - See the *Encryption External Media Help* to learn how the features of Encryption External Media. Access the help from **<Install dir>\Program Files\Dell\Dell Data Protection\Encryption\EMS**.
 - See the *Endpoint Security Suite Pro Help* to learn how to use the features of Advanced Authentication and Threat Protection. Access the help from **<Install dir>\Program Files\Dell\Dell Data Protection\Client Security Framework\Help**.
 - Users should update their policies by right-clicking the Dell Encryption icon in the system tray and selecting **Check for Policy Updates** after installation completes.
 - The master installer installs the entire suite of products. There are two methods to install using the master installer. Choose one of the following.
 - [Install Interactively Using the Master Installer](#)
- or
- [Install by Command Line Using the Master Installer](#)

Install Interactively Using the Master Installer

- The Endpoint Security Suite Pro master installer can be located at:
 - **From Your Dell FTP Account** - Locate the installation bundle at `Endpoint-Security-Suite-Pro_Ent-1.x.x.xxx.zip`
- Use these instructions to install Endpoint Security Suite Pro interactively using the Endpoint Security Suite Pro master installer. This method can be used to install the suite of products on one computer at a time.
 - 1 Locate **DDSSuite.exe** in the Dell installation media. Copy it to the local computer.
 - 2 Double-click to launch the installer. This may take several minutes.
 - 3 Click **Next** in the Welcome dialog.
 - 4 Read the license agreement, accept the terms, and click **Next**.
 - 5 In the **Enterprise Server Name** field, enter the fully qualified host name of the Security Management Server/Security Management Server Virtual that will manage the target user, such as `server.organization.com`.
In the **Device Server URL** field, enter the URL of the Device Server (Security Server) with which the client will communicate.

The format is `https://server.organization.com:8443/xapi/` (including trailing forward slash).

Click **Next**.



6 Click **Next** to install the product in the default location of C:\Program Files\Dell\Dell Data Protection\. Dell recommends installing in the default location only, as problems may arise when installing in other locations.

7 Select the components to be installed.

Security Framework installs the underlying security framework and Advanced Authentication, the advanced authentication client that manages multiple authentication methods, including PBA and credentials such as fingerprints and passwords.

Advanced Authentication installs the files and services required for Advanced Authentication.

Encryption installs the Encryption client, the component that enforces security policy, whether a computer is connected to the network, disconnected from the network, lost, or stolen.

Threat Protection installs the Threat Protection clients, which are malware and antivirus protection to scan for viruses, spyware, and unwanted programs, client firewall to monitor communication between the computer and resources on the network and the Internet, and web filtering to display safety ratings or block access to websites during online browsing.

BitLocker Manager installs the BitLocker Manager client, designed to enhance the security of BitLocker deployments by simplifying and reducing the cost of ownership through centralized management of BitLocker encryption policies.


Advanced Threat Prevention installs the Advanced Threat Prevention client, which is next-generation antivirus protection that uses algorithmic science and machine learning to identify, classify, and prevent both known and unknown cyberthreats from executing or harming endpoints.

NOTE: Threat Protection and Advanced Threat Prevention cannot reside on the same computer. The installer automatically prevents the selection of both components. Should you wish to install Advanced Threat Prevention, download the Endpoint Security Suite Enterprise *Advanced Installation Guide* for instructions.


NOTE: If the installer detects a Windows version later than Anniversary Update (Redstone 1), the Threat Protection option does not display.

Click **Next** when your selections are complete.






- 8 Click **Install** to begin the installation. Installation will take several minutes.



- 9 Select **Yes, I want to restart my computer now** and click **Finish**.



Installation is complete.

Install by Command Line Using the Master Installer

- The switches must be specified first in a command line installation. Other parameters go inside an argument that is passed to the /v switch.

Switches

- The following table describes the switches that can be used with the Endpoint Security Suite Pro master installer.

NOTE: If you attempt to install the optional Threat Protection features on a Windows 10 Anniversary Update (Redstone 2) or later, an incompatibility warning displays.

Switch	Description
-y -gm2	Pre-extraction of Endpoint Security Suite Pro master installer. The -y and -gm2 switches must be used together. Do not separate the switches.
/S	Silent installation
/z	Pass variables to the .msi inside the DDSSuite.exe

Parameters

- The following table describes the parameters that can be used with the Endpoint Security Suite Pro master installer. The Endpoint Security Suite Pro master installer cannot exclude individual components but can receive commands to specify which components should be installed.



Parameter	Description
SUPPRESSREBOOT	Suppresses the automatic reboot after the installation completes. Can be used in SILENT mode.
SERVER	Specifies the URL of the Security Management Server/Security Management Server Virtual.
InstallPath	Specifies the path for the installation. Can be used in SILENT mode.
FEATURES	Specifies the components that can be installed in SILENT mode. DE-TP = Threat Protection and Encryption DE = Drive Encryption (Encryption client) BLM = BitLocker Manager SED = SED Management (EMAgent/Manager, PBA/GPE Drivers)
BLM_ONLY=1	Must be used when using FEATURES=BLM in the command line to exclude the SED Management plugin.

Example Command Line

- Command line parameters are case-sensitive.
- This example installs all components using the Endpoint Security Suite Pro master installer on standard ports, silently, in the default location of **C:\Program Files\Dell\Dell Data Protection**, and configures it to use the specified Security Management Server/Security Management Server Virtual.

```
"DDSSuite.exe" -y -gm2 /S /z "\"SERVER=server.organization.com\""
```

- This example installs Threat Protection and Encryption **only** using the Endpoint Security Suite Pro master installer on standard ports, silently, in the default location of **C:\Program Files\Dell\Dell Data Protection**, and configures it to use the specified Security Management Server/Security Management Server Virtual.

```
"DDSSuite.exe" -y -gm2 /S /z "\"SERVER=server.organization.com, FEATURES=DE-TP\""
```

- This example installs Threat Protection, Encryption, and SED Management using the Endpoint Security Suite Pro master installer, on standard ports, silently, with a suppressed reboot, in the default location of **C:\Program Files\Dell\Dell Data Protection**, and configures it to use the specified Security Management Server/Security Management Server Virtual.

```
"DDSSuite.exe" -y -gm2 /S /z "\"SERVER=server.organization.com, FEATURES=DE-TP, SED, SUPPRESSREBOOT=1\""
```



Uninstall Using the Endpoint Security Suite Pro Master Installer

- Each component must be uninstalled separately, followed by uninstallation of the Endpoint Security Suite Pro master installer. The clients must be uninstalled in a **specific order to prevent uninstallation failures**.
 - Follow the instructions in [Extract the Child Installers from the Master Installer](#) to obtain child installers.
 - Ensure that the same version of Endpoint Security Suite Pro master installer (and thereby clients) is used for uninstallation as installation.
 - This chapter refers you to other chapters that contain *detailed* instructions of how to uninstall the child installers. This chapter explains the last step **only**, uninstalling the master installer.
 - Uninstall the clients in the following order.
 - a [Uninstall Threat Protection Clients](#).
 - b [Uninstall Encryption Client](#).
 - c [Uninstall SED and Advanced Authentication Clients](#).
 - d [Uninstall BitLocker Manager Client](#).
- The Driver package does not need to be uninstalled.
- Proceed to [Uninstall the Master Installer](#).

Uninstall the Endpoint Security Suite Pro Master Installer

Now that all of the individual clients have been uninstalled, the master installer can be uninstalled.

Command Line Uninstallation

- The following example silently uninstalls the Endpoint Security Suite Pro master installer.

```
"DDSSuite.exe" -y -gm2 /S /x
```

Reboot the computer when finished.



Install Using the Child Installers

- To install each client individually, the child executable files must first be extracted from the Endpoint Security Suite Pro master installer, as shown in [Extract the Child Installers from the Master Installer](#).
- Command examples included in this section assume the commands are run from **C:\extracted**.
- Command line switches and parameters are case-sensitive.
- Be sure to enclose a value that contains one or more special characters, such as a blank space in the command line, in escaped quotation marks.
- Use these installers to install the clients using a scripted installation, batch files, or any other push technology available to your organization.
- The reboot has been suppressed in the command line examples. However, an eventual reboot is required. Encryption cannot begin until the computer has rebooted.
- Log files - Windows creates unique child installer installation log files for the logged in user at %temp%, located at **C:\Users\<UserName>\AppData\Local\Temp**.

If you decide to add separate a log file when you run the installer, ensure that the log file has a unique name, as child installer log files do not append. The standard .msi command can be used to create a log file by using `/!*v C:\<any directory>\<any log file name>.log`.

- All child installers use the same basic .msi switches and display options, except where noted, for command line installations. The switches must be specified first. The `/v` switch is required and takes an argument. Other parameters go inside an argument that is passed to the `/v` switch.

Display options can be specified at the end of the argument passed to the `/v` switch to achieve the expected behavior. Do not use both `/q` and `/qn` in the same command line. Only use `!` and `-` after `/qb`.

Switch	Meaning
<code>/v</code>	Pass variables to the .msi inside the setup.exe. The content must always be enclosed in plain-text quotes.
<code>/s</code>	Silent mode
<code>/x</code>	Uninstall mode
<code>/a</code>	Administrative install (will copy all files inside the .msi)

NOTE:

With `/v`, the Microsoft default options are available. For a list of options, see [https://msdn.microsoft.com/en-us/library/windows/desktop/aa367988\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/windows/desktop/aa367988(v=vs.85).aspx).

Option	Meaning
<code>/q</code>	No Progress dialog, restarts itself after process completion
<code>/qb</code>	Progress dialog with Cancel button, prompts for restart
<code>/qb-</code>	Progress dialog with Cancel button, restarts itself after process completion
<code>/qb!</code>	Progress dialog without Cancel button, prompts for restart

Option	Meaning
/qb!-	Progress dialog without Cancel button, restarts itself after process completion
/qn	No user interface
/norestart	Suppress reboot

- Instruct users to see the following document and help files for application assistance:
 - See the *Dell Encrypt Help* to learn how to use the feature of the Encryption client. Access the help from <Install dir>\Program Files\Dell\Dell Data Protection\Encryption\Help.
 - See the *Encryption External Media Help* to learn how the features of Encryption External Media. Access the help from <Install dir>\Program Files\Dell\Dell Data Protection\Encryption\EMS.
 - See the *Endpoint Security Suite Pro Help* to learn how to use the features of Advanced Authentication and Threat Protection. Access the help from <Install dir>\Program Files\Dell\Dell Data Protection\Client Security Framework\Help.

Install Drivers

- Drivers and firmware for ControlVault, fingerprint readers and smart cards are not included in the Endpoint Security Suite Pro master installer or child installer executable files. The drivers and firmware must be kept up-to-date, and can be downloaded from <http://www.dell.com/support> and selecting your computer model. Download the appropriate drivers and firmware based on your authentication hardware.
 - ControlVault
 - NEXT Biometrics Fingerprint Driver
 - Validity Fingerprint Reader 495 Driver
 - O2Micro Smart Card Driver

If installing on non-Dell hardware, download updated drivers and firmware from that vendor's website.

Install Encryption Client

- Review [Encryption Client Requirements](#) if your organization is using a certificate signed by a root authority, such as EnTrust or Verisign. A registry setting change is needed on the client computer to enable certificate validation.
- Users should update their policies by right-clicking the Dell Data Security icon in the system tray and selecting **Check for Policy Updates** after installation completes.
- The Encryption client installer can be located at:
 - **From Your Dell FTP Account** - Locate the installation bundle at Endpoint-Security-Suite-1.x.x.xxx.zip and then [Extract the Child Installers from the Master Installer](#). After extraction, locate the file at **C:\extracted\Encryption**.

Command Line Installation

- The following table details the parameters available for the installation.

Parameters

SERVERHOSTNAME=<ServerName> (FQDN of the Dell Server for re-activation)

POLICYPROXYHOSTNAME=<RGKName> (FQDN of the default Policy Proxy)

MANAGEDDOMAIN=<MyDomain> (Domain to be used for the device)



Parameters

DEVICESERVERURL=<DeviceServerName/SecurityServerName> (URL used for activation; usually includes server name, port, and xapi)

GKPORT=<NewGKPort> (Gatekeeper port)

MACHINEID=<MachineName> (Computer name)

RECOVERYID=<RecoveryID> (Recovery ID)

REBOOT=ReallySuppress (Null allows for automatic reboots, ReallySuppress disables reboot)

HIDEOVERLAYICONS=1 (0 enables overlay icons, 1 disables overlay icons)

HIDESYSTRAYICON=1 (0 enables the systray icon, 1 disables the systray icon)

For a list of basic .msi switches and display options that can be used in command lines, refer to [Install Using the Child Installers](#).

- The following table details additional optional parameters related with activation.

Parameters

SLOTTEDACTIVATON=1 (0 disables delayed/scheduled activations, 1 enables delayed/scheduled activations)

SLOTINTERVAL=45,120 (Schedules activations through x,x notation where the first value is the lower limit of the schedule and the second value is the upper limit - in seconds)

CALREPEAT=600 (MUST match or exceed the upper limit set in SLOTINTERVAL. Number of seconds the Encryption client waits before generating an activation attempt based on SLOTINTERVAL.)

Example Command Line

- The following example installs the client with default parameters (Encryption client, Encrypt for Sharing, no dialogue, no progress bar, automatic restart, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
DDPE_XXbit_setup.exe /s /v"SERVERHOSTNAME=server.organization.com  
POLICYPROXYHOSTNAME=rgk.organization.com MANAGEDDOMAIN=ORGANIZATION DEVICESERVERURL=https://  
server.organization.com:8443/xapi/ /qn"
```

MSI Command:

```
msiexec.exe /i "Dell Data Protection Encryption.msi" /qn REBOOT="ReallySuppress"  
SERVERHOSTNAME="server.organization.com" POLICYPROXYHOSTNAME="rgk.organization.com"  
MANAGEDDOMAIN="ORGANIZATION" DEVICESERVERURL="https://server.organization.com:8443/xapi/"
```

- The following example installs the Encryption client and Encrypt for Sharing, hides the Data Security Console system tray icon, hides the overlay icons, no dialogue, no progress bar, suppresses restart, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**.

```
DDPE_XXbit_setup.exe /s /v"SERVERHOSTNAME=server.organization.com  
POLICYPROXYHOSTNAME=rgk.organization.com MANAGEDDOMAIN=ORGANIZATION DEVICESERVERURL=https://  
server.organization.com:8443/xapi/ HIDESYSTRAYICON=1 HIDEOVERLAYICONS=1  
REBOOT=ReallySuppress /qn"
```

MSI Command:

```
msiexec.exe /i "Dell Data Protection Encryption.msi" /qn REBOOT="ReallySuppress"  
SERVERHOSTNAME="server.organization.com" POLICYPROXYHOSTNAME="rgk.organization.com"  
MANAGEDDOMAIN="ORGANIZATION" DEVICESERVERURL="https://server.organization.com:8443/xapi/"  
HIDESYSTRAYICON="1" HIDEOVERLAYICONS="1"
```

- **Example Command Line to Install in Deferred Activation Mode**

- The following example installs the client with Deferred Activation in the default location of **C:\Program Files\Dell\Dell Data Protection**)



```
DDPE_XXbit_setup.exe /s /v"OPTIN=1 SERVERHOSTNAME=server.organization.com  
POLICYPROXYHOSTNAME=rgk.organization.com DEVICESERVERURL=https://server.organization.com:8443/  
xapi/ MANAGEDDOMAIN=ORGANIZATION"
```

MSI Command:

```
msiexec.exe /i "Dell Data Protection Encryption.msi" OPTIN="1"  
SERVERHOSTNAME="server.organization.com" POLICYPROXYHOSTNAME="rgk.organization.com"  
DEVICESERVERURL="https://server.organization.com:8443/xapi/" MANAGEDDOMAIN="ORGANIZATION"
```

- The following example installs the client with Deferred Activation and with default parameters (Encryption client, Encrypt for Sharing, no dialogue, no progress bar, no restart, no Encryption overlay icons, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
DDPE_XXbit_setup.exe /s /v"SERVERHOSTNAME=server.organization.com  
POLICYPROXYHOSTNAME=rgk.organization.com MANAGEDDOMAIN=ORGANIZATION DEVICESERVERURL=https://  
server.organization.com:8443/xapi/ OPTIN=1 HIDEOVERLAYICONS=1 REBOOT=ReallySuppress /qn"
```

MSI Command:

```
msiexec.exe /i "Dell Data Protection Encryption.msi" /qn REBOOT="ReallySuppress" OPTIN="1"  
SERVERHOSTNAME="server.organization.com" POLICYPROXYHOSTNAME="rgk.organization.com"  
MANAGEDDOMAIN="ORGANIZATION" DEVICESERVERURL="https://server.organization.com:8443/xapi/"  
HIDEOVERLAYICONS="1"
```

i NOTE:

Some older clients may require escape characters of \ around the values of parameters. For example:

```
DDPE_XXbit_setup.exe /v"CMG_DECRYPT="\1\" CMGSILENTMODE="\1\" DA_SERVER=  
\"server.organization.com\" DA_PORT="\8050\" SVC PN="\administrator@organization.com\"  
DA_RUNAS="\domain\username\" DA_RUNASPWD="\password\" /qn"
```

Install Threat Protection Clients

- Threat Protection and Advanced Threat Prevention **cannot reside on the same computer**. Do not install both of these components on the same computer, as compatibility issues will occur. If you wish to install Advanced Threat Prevention, download the Endpoint Security Suite Enterprise Advanced Installation Guide for instructions.
- The installers must be run in a specific order. Failure to install the components in the proper order will result in installation failure. Run the installers in the following order:

i NOTE: If you attempt to install the optional Threat Protection features on a Windows 10 Anniversary Update (Redstone 2) or later, an incompatibility warning displays.

- 1 [\Advanced Authentication](#) (Threat Protection needs the Dell Encryption Management Agent component).
- 2 [\Advanced Authentication](#) (Advanced Authentication and Auth should be installed together)
- 3 The Encryption client is required with the Threat Protection components. Go to Example Command Line for an example installation.
- 4 Threat Protection Clients, as shown in [Command Line Installation](#).

- The SED and Advanced Authentication client installers can be located at:

- **From Your Dell FTP Account** - Locate the installation bundle at Endpoint-Security-Suite-1.x.x.xxx.zip and then [Extract the Child Installers from the Master Installer](#). After extraction, locate the file at **C:\extracted\Encryption Management Agent** and **C:\extracted\Advanced Authentication\<x64/x86>**.

- The Encryption client installer can be located at:

- **From Your Dell FTP Account** - Locate the installation bundle at Endpoint-Security-Suite-1.x.x.xxx.zip and then [Extract the Child Installers from the Master Installer](#). After extraction, locate the file at **C:\extracted\Encryption**.

- The Threat Protection client installers can be located at:

- **From Your Dell FTP Account** - Locate the installation bundle at Endpoint-Security-Suite-1.x.x.xxx.zip and then [Extract the Child Installers from the Master Installer](#). After extraction, locate the file at **C:\extracted\Threat Protection**.




Command Line Installation

- The following table details the parameters available for the **EnsMgmtSdkInstaller.exe** file.

Parameters	Description
LoadCert	Load the certificate at the specified directory.

- The following table details the parameters available for the **EPsetup.exe** file.

Parameters	Description
ADDLOCAL="tp,fw,wc"	Identifies the modules to install: tp=Threat Protection fw=Client Firewall wc=Web Protection  NOTE: All three modules must be installed.
override "hips"	Do not install Host Intrusion Prevention
INSTALLDIR	Non-default installation location
nocontentupdate	Tells the installer not to update content files automatically as part of the installation process. Dell recommends scheduling an update as soon as installation has completed.
nopreservesettings	Do not save settings.

- The following table details the parameters available for the **DellThreatProtection.msi** file.

Parameters	Description
Reboot=ReallySuppress	Suppresses the reboot.
ARP	0=No entry in Add/Remove Programs 1=Entry in Add/Remove Programs

- The following table details the parameters available for the **EnsMgmtSdkInstaller.exe** file.

Parameters	Description
ProtectProcesses	Specify the file name and location of processes to protect.
InstallSDK	Installs the SDK at the specified location.
RemoveRightClick	Removes the right-click menu option for end users.
RemoveMcTray	Removes the system tray.

Example Command Line

\Threat Protection\SDK

- The following command line loads the certificate default parameters.



```
"Threat Protection\SDK\EnsMgmtSdkInstaller.exe" -LoadCert >"C:\ProgramData\Dell\Dell Data Protection\Installer Logs\McAfeeSDKInstallerBeforeEndPoint.log"
```

NOTE:

This installer can be skipped if upgrading.

Then:

\Threat Protection\EndPointSecurity

- The following example installs the Threat Protection, Web Protection, and Client Firewall with default parameters (silent mode, install Threat Protection, Client Firewall, and Web Protection, override the Host Intrusion Prevention, no content update, no settings saved).

```
"Threat Protection\EndPointSecurity\EPsetup.exe" ADDLOCAL="tp, fw, wc" /override"hips" /nocontentupdate /nopreservesettings /qn
```

Then:

\Threat Protection\ThreatProtection\WinXXR

- The following example installs the client with default parameters (suppress the reboot, no dialogue, no progress bar, no entry in the Control Panel Programs list).

```
"Threat Protection\ThreatProtection\WinXXR\DellThreatProtection.msi" /qn REBOOT=ReallySuppress ARPSYSTEMCOMPONENT=1
```

\Threat Protection\SDK

- The following example installs the Threat Protection SDK.

```
"Threat Protection\SDK\EnsMgmtSdkInstaller.exe" -ProtectProcesses "C:\Program Files\Dell\Dell Data Protection\Threat Protection\DellAVAgent.exe" -InstallSDK -RemoveRightClick -RemoveMcTray >"C:\ProgramData\Dell\Dell Data Protection\Installer Logs\McAfeeSDKInstallerAfterEndPoint.log"
```

Install SED Management and Advanced Authentication Clients

- The SED client is required for Advanced Authentication in v8.x.
- Review [SED Client Requirements](#) if your organization is using a certificate signed by a root authority, such as EnTrust or Verisign. A registry setting change is needed on the client computer to enable SSL/TLS trust validation.
- Users log in to the PBA using their Windows credentials.
- The SED and Advanced Authentication client installers can be located at:
 - **From Your Dell FTP Account** - Locate the installation bundle at Endpoint-Security-Suite-1.x.x.xxx.zip and then [Extract the Child Installers from the Master Installer](#). After extraction, locate the file at **C:\extracted\Encryption Management Agent** and **C:\extracted\Advanced Authentication\<x64/x86>**.

Command Line Installation

- The following table details the parameters available for the installation.

Parameters

CM_EDITION=1 <remote management>

INSTALLDIR=<change the installation destination>

SERVERHOST=<securityserver.organization.com>

SERVERPORT=8888



Parameters

SECURITYSERVERHOST=<securityserver.organization.com>

SECURITYSERVERPORT=8443

ARPSYSTEMCOMPONENT=1 <no entry in the Control Panel Programs list>

For a list of basic .msi switches and display options that can be used in command lines, refer to [Install Using the Child Installers](#).

Example Command Line

\Encryption Management Agent

- The following example installs remotely managed SED (silent installation, no reboot, no entry in the Control Panel Programs list, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
EMAgent_XXbit_setup.exe /s /v"CM_EDITION=1 SERVERHOST=server.organization.com SERVERPORT=8888  
SECURITYSERVERHOST=server.organization.com SECURITYSERVERPORT=8443 ARPSYSTEMCOMPONENT=1 /  
norestart /qn"
```

Then:

\Advanced Authentication\<x64/x86>

- The following example installs Advanced Authentication (silent installation, no reboot)

```
setup.exe /s /v"/norestart /qn ARPSYSTEMCOMPONENT=1"
```

Install BitLocker Manager Client

- Review [BitLocker Manager Client Requirements](#) if your organization is using a certificate signed by a root authority, such as EnTrust or Verisign. A registry setting change is needed on the client computer to enable SSL/TLS trust validation.
- The BitLocker Manager client installers can be located at:
 - From Your Dell FTP Account** - Locate the installation bundle at Endpoint-Security-Suite-1.x.x.xxx.zip and then [Extract the Child Installers from the Master Installer](#). After extraction, locate the file at **C:\extracted\Encryption Management Agent**.

Command Line Installation

- The following table details the parameters available for the installation.

Parameters

CM_EDITION=1 <remote management>

INSTALLDIR=<change the installation destination>

SERVERHOST=<securityserver.organization.com>

SERVERPORT=8888

SECURITYSERVERHOST=<securityserver.organization.com>

SECURITYSERVERPORT=8443

FEATURE=BLM <install BitLocker Manager only>

FEATURE=BLM,SED <install BitLocker Manager with SED>

Parameters

ARPSYSTEMCOMPONENT=1 <no entry in the Control Panel Programs list>

For a list of basic .msi switches and display options that can be used in command lines, refer to [Install Using the Child Installers](#).

Example Command Line

- The following example installs BitLocker Manager only (silent installation, no reboot, no entry in the Control Panel Programs list, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**)

```
EMAgent_XXbit_setup.exe /s /v"CM_EDITION=1 SERVERHOST=server.organization.com SERVERPORT=8888  
SECURITYSERVERHOST=server.organization.com SECURITYSERVERPORT=8443 FEATURE=BLM /norestart /qn"
```

- The following example installs BitLocker Manager with SED (silent installation, no reboot, no entry in the Control Panel Programs list, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**)

```
EMAgent_XXbit_setup.exe /s /v"CM_EDITION=1 SERVERHOST=server.organization.com SERVERPORT=8888  
SECURITYSERVERHOST=server.organization.com SECURITYSERVERPORT=8443 FEATURE=BLM, SED /  
norestart /qn"
```



Uninstall Using the Child Installers

- To uninstall each client individually, the child executable files must first be extracted from the Endpoint Security Suite Pro master installer, as shown in [Extract the Child Installers from the Master Installer](#). Alternatively, run an administrative installation to extract the .msi.
- Ensure that the same versions of client are used for uninstallation as installation.
- Command line switches and parameters are case-sensitive.
- Be sure to enclose a value that contains one or more special characters, such as a blank space in the command line, in escaped quotation marks. Command line parameters are case-sensitive.
- Use these installers to uninstall the clients using a scripted installation, batch files, or any other push technology available to your organization.
- Log files - Windows creates unique child installer uninstallation log files for the logged in user at %temp%, located at **C:\Users\<UserName>\AppData\Local\Temp**.

If you decide to add separate a log file when you run the installer, ensure that the log file has a unique name, as child installer log files do not append. The standard .msi command can be used to create a log file by using `/l C:\<any directory>\<any log file name>.log`. Dell does not recommend using `"/l*v"` (verbose logging) in a command line uninstallation, as the username/password is recorded in the log file.

- All child installers use the same basic .msi switches and display options, except where noted, for command line uninstallations. The switches must be specified first. The `/v` switch is required and takes an argument. Other parameters go inside an argument that is passed to the `/v` switch.

Display options can be specified at the end of the argument passed to the `/v` switch to achieve the expected behavior. Do not use both `/q` and `/qn` in the same command line. Only use `!` and `-` after `/qb`.

Switch	Meaning
<code>/v</code>	Pass variables to the .msi inside the setup.exe. The content must always be enclosed in plain-text quotes.
<code>/s</code>	Silent mode
<code>/x</code>	Uninstall mode
<code>/a</code>	Administrative install (will copy all files inside the .msi)

NOTE:

With `/v`, the Microsoft default options are available. For a list of options, see [https://msdn.microsoft.com/en-us/library/windows/desktop/aa367988\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/windows/desktop/aa367988(v=vs.85).aspx).

Option	Meaning
<code>/q</code>	No Progress dialog, restarts itself after process completion
<code>/qb</code>	Progress dialog with Cancel button, prompts for restart
<code>/qb-</code>	Progress dialog with Cancel button, restarts itself after process completion
<code>/qb!</code>	Progress dialog without Cancel button, prompts for restart

Option	Meaning
/qb!-	Progress dialog without Cancel button, restarts itself after process completion
/qn	No user interface

Uninstall Threat Protection Clients

Command Line Uninstallation

- Once extracted from the Endpoint Security Suite Pro master installer, the Threat Protection client installer can be located at **C:\extracted\Threat Protection\ThreatProtection\WinXXR\DellThreatProtection.msi**.
- Go to Add/Remove Programs in the Control Panel and uninstall the following components in this order.
 - McAfee Endpoint Security Firewall
 - McAfee Endpoint Security Threat Prevention
 - McAfee Endpoint Security Web Control
 - McAfee Agent
- Then:
- The following example uninstalls the Threat Protection client .

```
MSIEXEC.EXE /x "DellThreatProtection.msi"
```

Uninstall Encryption Client

- To reduce decryption time, run the Windows Disk Cleanup Wizard to remove temporary files and other unneeded data.
- Plan to decrypt overnight, if possible.
- Turn off sleep mode to prevent an unattended computer from going to sleep. Decryption cannot occur on a sleeping computer.
- Shut down all processes and applications to minimize decryption failures because of locked files.
- Once the uninstall is complete and decryption is in progress, disable all network connectivity. Otherwise, new policies may be acquired that re-enable encryption.
- Follow your existing process for decrypting data, such as issuing a policy update.
- Windows Encryption clients update the Security Management Server/Security Management Server Virtual to change the status to *Unprotected* at the beginning of a Encryption client uninstall process. However, in the event that the client cannot contact the Security Management Server/Security Management Server Virtual, regardless of the reason, the status cannot be updated. In this case, you will need to manually *Remove Endpoint* in the Remote Management Console. If your organization uses this workflow for compliance purposes, Dell recommends that you verify that *Unprotected* has been set as expected, either in the Remote Management Console or Compliance Reporter.

Process

- Before beginning the uninstall process**, see [\(Optional\) Create an Encryption Removal Agent Log File](#). This log file is useful for troubleshooting an uninstall/decryption operation. If you do not intend to decrypt files during the uninstall process, you do not need to create an Encryption Removal Agent log file.
- The Key Server (and Security Management Server) must be configured prior to uninstallation if using the **Encryption Removal Agent's Download Keys from Server** option. See [Configure Key Server for Uninstallation of Encryption Client Activated Against Security Management Server](#) for instructions. No prior action is needed if the client to uninstall is activated against a Security Management Server Virtual, as Security Management Server Virtual does not use the Key Server.
- You must use the Dell Administrative Utility (CMGAd) prior launching the Encryption Removal Agent if using the **Encryption Removal Agent's Import Keys from a file** option. This utility is used to obtain the encryption key bundle. See [Use the Administrative Download Utility \(CMGAd\)](#) for instructions. The utility can be located in the Dell installation media.



- Run WSScan to ensure that all data is decrypted after uninstallation is complete, but before restarting the computer. See [Use WSScan](#) for instructions.
- Periodically [Check Encryption Removal Agent Status](#). Data decryption is still in process if the Encryption Removal Agent Service still exists in the Services panel.

Command Line Uninstallation

- Once extracted from the Endpoint Security Suite Pro master installer, the Encryption client installer can be located at **C:\extracted\Encryption\DDPE_XXbit_setup.exe**.
- The following table details the parameters available for the uninstallation.

Parameter	Selection
CMG_DECRYPT	Property for selecting the type of Encryption Removal Agent installation: 3 - Use LSARecovery bundle 2 - Use previously downloaded forensics key material 1 - Download keys from the Dell Server 0 - Do not install Encryption Removal Agent
CMGSILENTMODE	Property for silent uninstallation: 1 - Silent 0 - Not Silent
Required Properties	
DA_SERVER	FQHN for the Security Management Server hosting the negotiate session.
DA_PORT	Port on the Security Management Server for request (default is 8050).
SVCPN	Username in UPN format that the Key Server Service is logged on as on the Security Management Server.
DA_RUNAS	Username in SAM compatible format under whose context the key fetch request will be made. This user must be in the Key Server list in the Security Management Server.
DA_RUNASPWD	Password for the runas user.
FORENSIC_ADMIN	The Forensic Administrator account on the Dell Server, which can be used for forensic requests for uninstalls or keys.
FORENSIC_ADMIN_PWD	The password for the Forensic Administrator account.
Optional Properties	
SVCLOGONUN	Username in UPN format for Encryption Removal Agent Service log on as parameter.
SVCLOGONPWD	Password for log on as user.



- The following example silently uninstalls the Encryption client and downloads the encryption keys from the Security Management Server.

```
DDPE_XXbit_setup.exe /s /x /v"CMG_DECRYPT=1 CMGSILENTMODE=1 DA_SERVER=server.organization.com
DA_PORT=8050 SVC PN=administrator@organization.com DA_RUNAS=domain\username
DA_RUNASPWD=password /qn"
```

MSI Command:

```
msiexec.exe /s /x "Dell Data Protection Encryption.msi" /qn REBOOT="ReallySuppress"
CMG_DECRYPT="1" CMGSILENTMODE="1" DA_SERVER="server.organization.com" DA_PORT="8050"
SVC PN="administrator@domain.com" DA_RUNAS="domain\username" DA_RUNASPWD="password" /qn
```

Reboot the computer when finished.

- The following example silently uninstalls the Encryption client and downloads the encryption keys using a Forensic Administrator account.

```
DDPE_XXbit_setup.exe /s /x /v"CMG_DECRYPT=1 CMGSILENTMODE=1
FORENSIC_ADMIN=forensicadmin@organization.com FORENSIC_ADMIN_PWD=tempchangeit /qn"
```

MSI Command:

```
msiexec.exe /s /x "Dell Data Protection Encryption.msi" /qn CMG_DECRYPT=1 CMGSILENTMODE=1
FORENSIC_ADMIN=forensicadmin@organization.com FORENSIC_ADMIN_PWD=tempchangeit
REBOOT=REALLYSUPPRESS
```

Reboot the computer when finished.

❗ IMPORTANT:

Dell recommends the following actions when using a Forensic Administrator password on the command line:

- 1 Create a Forensic Administrator account in the Remote Management Console for the purpose of performing the silent uninstallation.
- 2 Use a temporary password for that account that is unique to that account and time period.
- 3 After the silent uninstallation has been completed, remove the temporary account from the list of administrators or change its password.

❗ NOTE:

Some older clients may require escape characters of \ around the values of parameters. For example:

```
DDPE_XXbit_setup.exe /x /v"CMG_DECRYPT=\"1\" CMGSILENTMODE=\"1\" DA_SERVER=
\"server.organization.com\" DA_PORT=\"8050\" SVC PN=\"administrator@organization.com\"
DA_RUNAS=\"domain\username\" DA_RUNASPWD=\"password\" /qn"
```

Uninstall SED and Advanced Authentication Clients

- Network connection to the Security Management Server/Security Management Server Virtual is required for PBA deactivation.

Process

- Deactivate the PBA, which removes all PBA data from the computer and unlocks the SED keys.
- Uninstall the SED client.
- Uninstall the Advanced Authentication client.

Deactivate the PBA

- 1 As a Dell administrator, log in to the Remote Management Console.



- 2 In the left pane, click **Protect & Manage > Endpoints**.
- 3 Select the appropriate Endpoint Type.
- 4 Select Show > *Visible, Hidden, or All*.
- 5 If you know the Hostname of the computer, enter it in the Hostname field (wildcards are supported). You may leave the field blank to display all computers. Click **Search**.

If you do not know the Hostname, scroll through the list to locate the computer.

A computer or list of computers displays based on your search filter.

- 6 Select the **Details** icon of the desired computer.
- 7 Click **Security Policies** on the top menu.
- 8 Select **Self-Encrypting Drives** from the **Policy Category** drop-down menu.
- 9 Expand the **SED Administration** area and change the **Enable SED Management** and **Activate PBA** policies from *True* to *False*.
- 10 Click **Save**.
- 11 In the left pane, click **Actions > Commit Policies**.
- 12 Click **Apply Changes**.

Wait for the policy to propagate from the Security Management Server/Security Management Server Virtual to the computer targeted for deactivation.

Uninstall the SED and Authentication clients after the PBA is deactivated.

Uninstall SED Client and Advanced Authentication Clients

Command Line Uninstallation

- Once extracted from the master installer, the SED client installer can be located at `C:\extracted\Advanced Authentication\<x64/x86>\setup.exe`.
- The following example silently uninstalls the Advanced Authentication client.

```
setup.exe /x /s /v" /qn"
```

Shut down and restart the computer when finished.

- Once extracted from the master installer, the SED client installer can be located at `C:\extracted\Encryption Management Agent\EMAgent_XXbit_setup.exe`.
- The following example silently uninstalls the SED client.

```
EMAgent_XXbit_setup.exe /x /s /v" /qn"
```

Shut down and restart the computer when finished.

Uninstall BitLocker Manager Client

Command Line Uninstallation

- Once extracted from the Endpoint Security Suite Pro master installer, the BitLocker client installer can be located at `C:\extracted\Encryption Management Agent\EMAgent_XXbit_setup.exe`.
- The following example silently uninstalls the BitLocker Manager client.

```
EMAgent_XXbit_setup.exe /x /s /v" /qn"
```

Reboot the computer when finished.



Commonly Used Scenarios

- To install each client individually, the child executable files must first be extracted from the Endpoint Security Suite Pro master installer, as shown in [Extract the Child Installers from the Master Installer](#).
- The SED client is required for Advanced Authentication in v8.x, which is why it is part of the command line in the following examples.
- Command line switches and parameters are case-sensitive.
- Be sure to enclose a value that contains one or more special characters, such as a blank space in the command line, in escaped quotation marks.
- Use these installers to install the clients using a scripted installation, batch files, or any other push technology available to your organization.
- The reboot has been suppressed in the command line examples. However, an eventual reboot is required. Encryption cannot begin until the computer has rebooted.
- Log files - Windows creates unique child installer installation log files for the logged in user at %temp%, located at **C:\Users \<UserName>\AppData\Local\Temp**.

If you decide to add separate a log file when you run the installer, ensure that the log file has a unique name, as child installer log files do not append. The standard .msi command can be used to create a log file by using `/*v C:\<any directory>\<any log file name>.log`.

- All child installers use the same basic .msi switches and display options, except where noted, for command line installations. The switches must be specified first. The `/v` switch is required and takes an argument. Other parameters go inside an argument that is passed to the `/v` switch.

Display options can be specified at the end of the argument passed to the `/v` switch to achieve the expected behavior. Do not use both `/q` and `/qn` in the same command line. Only use `!` and `-` after `/qb`.

Switch	Meaning
<code>/v</code>	Pass variables to the .msi inside the *.exe
<code>/s</code>	Silent mode
<code>/i</code>	Install mode

Option	Meaning
<code>/q</code>	No Progress dialog, restarts itself after process completion
<code>/qb</code>	Progress dialog with Cancel button, prompts for restart
<code>/qb-</code>	Progress dialog with Cancel button, restarts itself after process completion
<code>/qb!</code>	Progress dialog without Cancel button, prompts for restart
<code>/qb!-</code>	Progress dialog without Cancel button, restarts itself after process completion
<code>/qn</code>	No user interface

- Instruct users to see the following document and help files for application assistance:
 - See the *Dell Encrypt Help* to learn how to use the feature of the Encryption client. Access the help from **<Install dir>\Program Files \Dell\Dell Data Protection\Encryption\Help**.
 - See the *Encryption External Media Help* to learn how the features of Encryption External Media. Access the help from **<Install dir>:\Program Files\Dell\Dell Data Protection\Encryption\EMS**



- See the *Endpoint Security Suite Pro Help* to learn how to use the features of Advanced Authentication and Threat Protection. Access the help from <Install dir>:\Program Files\Dell\Dell Data Protection\Endpoint Security Suite\Threat Protection\Help.

Encryption Client, Threat Protection, and Advanced Authentication

- The following example installs remotely managed SED (silent installation, no reboot, no entry in the Control Panel Programs list, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
EMAgent_XXbit_setup.exe /s /v"CM_EDITION=1 SERVERHOST=server.organization.com SERVERPORT=8888 SECURITYSERVERHOST=server.organization.com SECURITYSERVERPORT=8443 ARPSYSTEMCOMPONENT=1 /norestart /qn"
```

Then:

- The following example installs Advanced Authentication (silent installation, no reboot, installed in the default location of **C:\Program Files\Dell\Dell Data Protection\Authentication**).

```
setup.exe /s /v"/norestart /qn ARPSYSTEMCOMPONENT=1"
```

- The following example installs the Encryption client with default parameters (Encryption client and Encrypt for Sharing, no dialogue, no progress bar, no restart, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
DDPE_XXbit_setup.exe /s /v"SERVERHOSTNAME=server.organization.com POLICYPROXYHOSTNAME=rgk.organization.com MANAGEDDOMAIN=ORGANIZATION DEVICESERVERURL=https://server.organization.com:8443/xapi/ /norestart /qn"
```

\Threat Protection\SDK

The following command line loads the certificate default parameters.

```
EnsMgmtSdkInstaller.exe -LoadCert >"C:\ProgramData\Dell\Dell Data Protection\Installer Logs\McAfeeSDKInstallerBeforeEndPoint.log"
```

NOTE:

This installer can be skipped if upgrading.

Then:

\Threat Protection\EndPointSecurity

- The following example installs the Threat Protection with default parameters (silent mode, install Threat Protection, Client Firewall, and Web Protection, override the Host Intrusion Prevention, no content update, no settings saved).

```
EPsetup.exe /qn ADDLOCAL="tp, fw, wc" /override"hips" /nocontentupdate /nopreservesettings /qn
```

Then:

\Threat Protection\ThreatProtection\WinXXR

- The following example installs the client with default parameters (suppress the reboot, no dialogue, no progress bar, no entry in the Control Panel Programs list).

```
"DellThreatProtection.msi" /qn REBOOT=ReallySuppress ARPSYSTEMCOMPONENT=1
```

\Threat Protection\SDK

- The following example installs the Threat Protection SDK.

```
EnsMgmtSdkInstaller.exe -ProtectProcesses "C:\Program Files\Dell\Dell Data Protection\Threat Protection\DellAVAgent.exe" -InstallSDK -RemoveRightClick -RemoveMcTray >"C:\ProgramData\Dell\Dell Data Protection\Installer Logs\McAfeeSDKInstallerAfterEndPoint.log"
```



Encryption Client and Threat Protection

- The following example installs drivers for Trusted Software Stack (TSS) for the TPM and Microsoft hotfixes at the specified location, does not create an entry in the Control Panel Programs list, and suppresses the reboot.

These drivers must be installed when installing the Encryption client.

```
setup.exe /S /z "\"InstallPath=<c:\location>, ARPSYSTEMCOMPONENT=1, SUPPRESSREBOOT=1\""
```

Then:

- The following example installs the Encryption client with default parameters (Encryption client and Encrypt for Sharing, no dialogue, no progress bar, no restart, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
DDPE_XXbit_setup.exe /s /v"SERVERHOSTNAME=server.organization.com  
POLICYPROXYHOSTNAME=rgk.organization.com MANAGEDDOMAIN=ORGANIZATION DEVICESERVERURL=https://  
server.organization.com:8443/xapi/ /norestart /qn"
```

Then:

- The following example installs the Threat Protection client with default parameters (silent mode, install Threat Protection, Client Firewall, and Web Protection, overrides the Host Intrusion Prevention, no content update, no settings saved).

```
EPsetup.exe /qn ADDLOCAL="tp,fw,wc" /override"hps" /nocontentupdate /nopreservesettings
```

Then:

- The following example installs the Threat Protection client with default parameters (suppress the reboot, no dialogue, no progress bar, install at the specified location **C:\Program Files\Dell\Dell Data Protection**, no entry in the Control Panel Programs list).

```
MSIEXEC.EXE /I "DellThreatProtection.msi" /qn REBOOT=ReallySuppress INSTALLDIR="C:\Program  
Files\Dell\Dell Data Protection\" ARPSYSTEMCOMPONENT=1 "
```

Then:

- The following example installs the Threat Protection client with default parameters.

```
EnsMgmtSDKInstaller.exe -LoadCert -ProtectProcesses "C:\Program Files\Dell\Dell Data  
Protection\Threat Protection\DellAVAgent.exe" -InstallSDK -RemoveRightClick -RemoveMcTray >  
"C:\ProgramData\Dell\Dell Data Protection\Installer Logs\SDKInstaller.log"
```

SED Client (including Advanced Authentication) and Encryption External Media

- The following example installs remotely managed SED (silent installation, no reboot, no entry in the Control Panel Programs list, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
EMAgent_XXbit_setup.exe /s /v"CM_EDITION=1 SERVERHOST=server.organization.com SERVERPORT=8888  
SECURITYSERVERHOST=server.organization.com SECURITYSERVERPORT=8443 ARPSYSTEMCOMPONENT=1 /  
norestart /qn"
```

Then:

- The following example installs Advanced Authentication (silent installation, no reboot, installed in the default location of **C:\Program Files\Dell\Dell Data Protection\Authentication**).

```
setup.exe /s /v"/norestart /qn ARPSYSTEMCOMPONENT=1"
```

Then:

- The following example installs Encryption External Media only (silent installation, no reboot, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
DDPE_XXbit_setup.exe /s /v"EME=1 SERVERHOSTNAME=server.organization.com  
POLICYPROXYHOSTNAME=rgk.organization.com DEVICESERVERURL=https://server.organization.com:8443/  
xapi/ MANAGEDDOMAIN=ORGANIZATION /norestart /qn"
```



BitLocker Manager and Encryption External Media

- The following example installs BitLocker Manager (silent installation, no reboot, no entry in the Control Panel Programs list, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
EMAgent_XXbit_setup.exe /s /v"CM_EDITION=1 SERVERHOST=server.organization.com SERVERPORT=8888  
SECURITYSERVERHOST=server.organization.com SECURITYSERVERPORT=8443 FEATURE=BLM /norestart /qn"
```

Then:

- The following example installs Encryption External Media only (silent installation, no reboot, installed in the default location of **C:\Program Files\Dell\Dell Data Protection**).

```
DDPE_XXbit_setup.exe /s /v"EME=1 SERVERHOSTNAME=server.organization.com  
POLICYPROXYHOSTNAME=rgk.organization.com DEVICESERVERURL=https://server.organization.com:8443/  
xapi/ MANAGEDDOMAIN=ORGANIZATION /norestart /qn"
```



Pre-Installation Configuration for SED UEFI, and BitLocker Manager

Initialize the TPM

- You must be a member of the local Administrators group, or equivalent.
- The computer must be equipped with a compatible BIOS and a TPM.
- Follow the instructions located at <http://technet.microsoft.com/en-us/library/cc753140.aspx>.

Pre-Installation Configuration for UEFI Computers

Enable Network Connectivity During UEFI Preboot Authentication

In order for preboot authentication to succeed on a computer with UEFI firmware, the PBA must have network connectivity. By default, computers with UEFI firmware do not have network connectivity until the operating system is loaded, which occurs after PBA mode.

The following procedure enables network connectivity during PBA for UEFI-enabled computers. Because the configuration steps vary from one UEFI computer model to the next, the following procedure is only an example.


- 1 Boot into the UEFI firmware configuration.
- 2 Press F2 continuously during boot until you see a message in the upper right screen similar to "preparing one-time boot menu."
- 3 Enter the BIOS administrator password, if prompted.



NOTE:

Typically, you will not see this prompt if this is a new computer since the BIOS password has not yet been configured.

- 4 Select **System Configuration**.
- 5 Select **Integrated NIC**.
- 6 Select the **Enable UEFI Network Stack** check box.
- 7 Select either **Enabled** or **Enabled w/PXE**.



- 8 Select **Apply**



**NOTE:**

Computers *without* UEFI firmware do not require configuration.

Disable Legacy Option ROMs

Ensure that the **Enable Legacy Option ROMs** setting is disabled in the BIOS.

- 1 Restart the computer.
- 2 As it is restarting, press **F12** repeatedly to bring up the UEFI computer's boot settings.
- 3 Press the down arrow, highlight the **BIOS Settings** option, and press **Enter**.
- 4 Select **Settings > General > Advanced Boot Options**.
- 5 Clear the **Enable Legacy Option ROMs** check box and click **Apply**.

Pre-Installation Configuration to Set Up a BitLocker PBA Partition

- You must create the PBA partition **before** installing BitLocker Manager.
- Turn on and activate the TPM **before** installing BitLocker Manager. BitLocker Manager will take ownership of the TPM (a reboot will not be required). However, if the TPM's ownership already exists, BitLocker Manager will begin the encryption setup process. The point is that the TPM must be "owned".
- You may need to partition the disk manually. See Microsoft's description of the BitLocker Drive Preparation Tool for further information.
- Use the BdeHdCfg.exe command to create the PBA partition. The default parameter indicates that the command line tool will follow the same process as the BitLocker Setup Wizard.

```
BdeHdCfg -target default
```

**TIP:**

For more options available for the BdeHdCfg command, see [Microsoft's BdeHdCfg.exe Parameter Reference](#).




Set GPO on Domain Controller to Enable Entitlements

- If your clients will be entitled from Dell Digital Delivery (DDD), follow these instructions to set the GPO on the domain controller to enable entitlements (this may not be the same server running the Security Management Server/Security Management Server Virtual).
- The workstation must be a member of the OU where the GPO is applied.


NOTE:

Ensure that outbound port 443 is available to communicate with the Security Management Server/Security Management Server Virtual. If port 443 is blocked (for any reason), the entitlement functionality will not work.

- 1 On the Domain Controller to manage the clients, click **Start > Administrative Tools > Group Policy Management**.
- 2 Right-click the OU where the policy should be applied and select **Create a GPO in this domain**, and **Link it here....**
- 3 Enter a name for the new GPO, select (none) for Source Starter GPO, and click **OK**.




- 4 Right-click the GPO that was created and select **Edit**.



- 5 The Group Policy Management Editor loads. Access **Computer Configuration > Preferences > Windows Settings > Registry**.





6 Right-click the Registry and select **New > Registry Item**. Complete the following.

Action: Create

Hive: HKEY_LOCAL_MACHINE


Key Path: SOFTWARE\Dell\Dell Data Protection

Value name: Server

Value type: REG_SZ

Value data: <IP address of the Security Management Server/Security Management Server Virtual>

7 Click **OK**.



8 Log out and then back into the workstation, or run **gpupdate /force** to apply the group policy.



Extract the Child Installers from the Endpoint Security Suite Pro Master Installer

- To install each client individually, extract the child executable files from the installer.
- The master installer is not a master *uninstaller*. Each client must be uninstalled individually, followed by uninstallation of the master installer. Use this process to extract the clients from the master installer so that they can be used for uninstallation.


- 1 From the Dell installation media, copy the **DDSSuite.exe** file to the local computer.
- 2 Open a command prompt in the same location as the **DDSSuite.exe** file and enter:

```
DDSSuite.exe /z "\"EXTRACT_INSTALLERS=C:\extracted\""
```

The extraction path cannot exceed 63 characters.

Before you begin installation, ensure that all prerequisites have been met and all required software has been installed for each child installer that you plan to install. Refer to [Requirements](#) for details.

The extracted child installers are located at **C:\extracted**.



Configure Key Server for Uninstallation of Encryption Client Activated Against Security Management Server

- This section explains how to configure components for use with Kerberos Authentication/Authorization when using an Security Management Server. The Security Management Server Virtual does not use the Key Server.


The Key Server is a Service that listens for clients to connect on a socket. Once a client connects, a secure connection is negotiated, authenticated, and encrypted using Kerberos APIs (if a secure connection cannot be negotiated, the client is disconnected).

The Key Server then checks with the Security Server (formerly the Device Server) to see if the user running the client is allowed to access keys. This access is granted on the Remote Management Console via individual domains.

- If Kerberos Authentication/Authorization is to be used, then the server that contains the Key Server component will need to be part of the affected domain.
- Because the Security Management Server Virtual does not use the Key Server, typical uninstallation is affected. When an Encryption client that is activated against a Security Management Server Virtual is uninstalled, standard forensic key retrieval through the Security Server is used, instead of the Key Server's Kerberos method. See [Command Line Uninstallation](#) for more information.

Services Panel - Add Domain Account User

- 1 On the Security Management Server, navigate to the Services panel (Start > Run... > services.msc > OK).
- 2 Right-click Key Server and select **Properties**.




- 3 Select the Log On tab and select the **This account:** option.

In the *This account:* field, add the domain account user. This domain user must have at least local administrator rights to the Key Server folder (must be able to write to the Key Server config file, as well as the ability to write to the log.txt file).

Enter and confirm the password for the domain user.

Click **OK**.





- 4 Restart the Key Server Service (leave the Services panel open for further operation).
- 5 Navigate to <Key Server install dir> log.txt to verify that the Service started properly.

Key Server Config File - Add User for Security Management Server Communication

- 1 Navigate to <Key Server install dir>.
- 2 Open **Credant.KeyServer.exe.config** with a text editor.
- 3 Go to <add key="user" value="superadmin" /> and change the "superadmin" value to the name of the appropriate user (you may also leave as "superadmin").

The "superadmin" format can be any method that can authenticate to the Security Management Server. The SAM account name, UPN, or domain\username is acceptable. Any method that can authenticate to the Security Management Server is acceptable because validation is required for that user account for authorization against Active Directory.

For example, in a multi-domain environment, only entering a SAM account name such as "jdoe" will likely fail because the Security Management Server will not be able to authenticate "jdoe" because it cannot find "jdoe". In a multi-domain environment, the UPN is recommended, although the domain\username format is acceptable. In a single domain environment, the SAM account name is acceptable.

- 4 Go to <add key="epw" value="<encrypted value of the password>" /> and change "epw" to "password". Then change "<encrypted value of the password>" to the password of the user from Step 3. This password is re-encrypted when the Security Management Server restarts.

If using "superadmin" in Step 3, and the superadmin password is not "changeit", it must be changed here. Save and close the file.

Sample Configuration File

```
<?xml version="1.0" encoding="utf-8" ?>

<configuration>

  <appSettings>

    <add key="port" value="8050" /> [TCP port the Key Server will listen to. Default is 8050.]

    <add key="maxConnections" value="2000" /> [number of active socket connections the Key Server will allow]

    <add key="url" value="https://keyserver.domain.com:8443/xapi/" /> [Security Server (formerly Device Server) URL (the format is 8081/xapi for a pre-v7.7 Security Management Server)]

    <add key="verifyCertificate" value="false" /> [true verifies certs/set to false to not verify or if using self-signed certs]

<add key="user" value="superadmin" /> [User name used to communicate with the Security Server. This user must have the administrator role selected in the Remote Management Console. The "superadmin" format can be any method that can authenticate to the Security Management Server. The SAM account name, UPN, or domain\username is acceptable. Any method that can authenticate to the Security Management Server is acceptable because validation is required for that user account for authorization against Active Directory. For example, in a multi-domain environment, only entering a SAM account name such as "jdoe" will likely fail because the Security Management Server will not be able to authenticate "jdoe" because it cannot find "jdoe". In a multi-domain environment, the UPN is recommended, although the domain\username format is acceptable. In a single domain environment, the SAM account name is acceptable.]

    <add key="cacheExpiration" value="30" /> [How often (in seconds) the Service should check to see who is allowed to ask for keys. The Service keeps a cache and keeps track of how old it is. Once the cache is older than the value, it gets a new list. When a user connects, the Key Server needs to download authorized users from the Security Server. If there is no cache of these users, or the list has not been downloaded in the last "x" seconds, it will be downloaded again. There is no polling, but this value configures how stale the list can become before it is refreshed when it is needed.]

    <add key="epw" value="encrypted value of the password" /> [Password used to communicate with the Security Server. If the superadmin password has been changed, it must be changed here.]

  </appSettings>

</configuration>
```

Services Panel - Restart Key Server Service


- 1 Go back to the Services panel (Start > Run... > services.msc > OK).
- 2 Restart the Key Server Service.
- 3 Navigate to <Key Server install dir> log.txt to verify that the Service started properly.
- 4 Close the Services panel.

Remote Management Console - Add Forensic Administrator

- 1 If needed, log on to the Remote Management Console.
- 2 Click **Populations > Domains**.
- 3 Select the appropriate Domain.
- 4 Click the **Key Server** tab.



- 5 In the Account field, add the user that will be performing the administrator activities. The format is DOMAIN\UserName. Click **Add Account**.



- 6 Click **Users** in the left menu. In the search box, search for the username added in Step 5. Click **Search**.
- 7 Once the correct user is located, click the **Admin** tab.
- 8 Select **Forensic Administrator** and click **Update**.
- The components are now configured for Kerberos Authentication/Authorization.

Use the Administrative Download Utility (CMGAd)

- This utility allows the download of a key material bundle for use on a computer that is not connected to an Security Management Server/Security Management Server Virtual.
- This utility uses one of the following methods to download a key bundle, depending on the command line parameter passed to the application:
 - Forensic Mode - Used if `-f` is passed on the command line or if no command line parameter is used.
 - Admin Mode - Used if `-a` is passed on the command line.

Log files can be located at `C:\ProgramData\CmgAdmin.log`

Use the Administrative Download Utility in Forensic Mode

- 1 Double-click **cmgad.exe** to launch the utility or open a command prompt where CMGAd is located and type **cmgad.exe -f** (or **cmgad.exe**).
- 2 Enter the following information (some fields may be pre-populated).

Device Server URL: Fully qualified Security Server (Device Server) URL. The format is `https://securityserver.domain.com:8443/xapi/`.

Dell Admin: Name of the administrator with forensic administrator credentials (enabled in the Remote Management Console), such as `jdoe`

Password: Forensic administrator password

MCID: Machine ID, such as `machineID.domain.com`


DCID: First eight digits of the 16-digit Shield ID

TIP:

Usually, specifying either the MCID or DCID are sufficient. However, if both are known, it is helpful to enter both. Each parameter contains different information about the client and client computer.


Click **Next**.





- 3 In the Passphrase: field, type a passphrase to protect the download file. The passphrase must be at least eight characters long, and contain at least one alphabetic and one numeric character. Confirm the passphrase.
Either accept the default name and location of where the file will be saved to or click ... to select a different location.

Click **Next**.



A message displays, indicating that the key material was successfully unlocked. Files are now accessible.

- 4 Click **Finish** when complete.



Use the Administrative Download Utility in Admin Mode

The Security Management Server Virtual does not use the Key Server, so Admin mode cannot be used to obtain a key bundle from a Security Management Server Virtual. Use Forensic mode to obtain the key bundle if the client is activated against a Security Management Server Virtual.

- 1 Open a command prompt where CMGAd is located and type `cmgad.exe -a`.
- 2 Enter the following information (some fields may be pre-populated).
Server: Fully qualified hostname of the Key Server, such as keyserver.domain.com

Port Number: The default port is 8050

Server Account: The domain user the Key Server is running as. The format is domain\username. The domain user running the utility must be authorized to perform the download from the Key Server


MCID: Machine ID, such as machineID.domain.com

DCID: First eight digits of the 16-digit Shield ID

TIP:

Usually, specifying either the MCID or DCID are sufficient. However, if both are known, it is helpful to enter both. Each parameter contains different information about the client and client computer.

Click **Next**.




- 3 In the Passphrase: field, type a passphrase to protect the download file. The passphrase must be at least eight characters long, and contain at least one alphabetic and one numeric character.
Confirm the passphrase.

Either accept the default name and location of where the file will be saved or click ... to select a different location.



Click **Next**.



A message displays, indicating that the key material was successfully unlocked. Files are now accessible.

- 4 Click **Finish** when complete.



Configure Deferred Activation

The Encryption client with Deferred Activation differs from the Encryption client activation in two ways:

Device-based Encryption policies

The Encryption client policies are user-based; the Encryption client with Deferred Activation's encryption policies are device-based. User encryption is converted to Common encryption. This difference allows the user to bring a personal device to use within the organization's domain, while the organization maintains its security by centrally managing encryption policies.

Activation

With the Encryption client, activation is automatic. When Endpoint Security Suite Pro with Deferred Activation is installed, automatic activation is disabled. Instead, the user chooses whether to activate encryption, and when to activate it.

❗ IMPORTANT:

Before a user permanently leaves the organization and while his email address is still active, the user must run the Encryption Removal Agent and uninstall the Encryption client from his personal computer.

Deferred Activation Customization


These client-side tasks allow Deferred Activation customization.

- Add a disclaimer to the Activation Logon dialog box
- Disable automatic re-activation (optional)

Add a disclaimer to the Activation Logon dialog box

The Activation Logon dialog displays at these times:

- When an unmanaged user logs on.
- When the user decides to activate encryption and selects Activate Encryption from the system tray Encryption icon menu.



Prepare the Computer for Installation

If the data is encrypted with a non-Dell encryption product, before installing the Encryption client, decrypt data using the existing encryption software, and then uninstall the existing encryption software. If the computer does not restart automatically, restart the computer.

Create a Windows Password

Dell highly recommends that a Windows password be created (if one does not already exist) to protect access to the encrypted data. Creating a password for the computer prevents others from logging on to your user account without your password.

Uninstall Previous Versions of the Encryption Client

Before uninstalling a previous version of the Encryption client, stop or pause an encryption sweep, if necessary.

If the computer is running a version of Dell Encryption earlier than v8.6, uninstall the Encryption client from the command line. For instructions, see *Uninstall Encryption and Server Encryption Client*.

NOTE:

If you plan to install the latest version of the Encryption client immediately after uninstallation, it is not necessary to run the Encryption Removal Agent to decrypt the files.

To upgrade a previous version of the Encryption client installed with Deferred Activation, use the Control Panel/Uninstall a Program utility. This uninstallation method is possible even if OPTIN is disabled.

NOTE:

If no users were previously activated, the Encryption client clears the OPTIN setting from the SDE vault since the setting is left-over from a previous installation. The Encryption client blocks Deferred Activations if users previously activated but the OPTIN flag is not set in the SDE vault.

Install the Encryption Client with Deferred Activation

To install the Encryption client with Deferred Activation, install the Encryption client with the OPTIN=1 parameter. For more information about client installation with the OPTIN=1 parameter, see [Install Encryption Client](#).

Activate the Encryption Client with Deferred Activation


- Activation associates a domain user with a local user account and a specific computer.
- Multiple users can activate on the same computer, provided they use unique local accounts and have unique domain email addresses.
- A user can activate the Encryption client only once per domain account.

Before you activate the Encryption client:

- Log in to the local account that you use the most often. The data associated with this account is the data that will be encrypted.
- Connect to your organization's network.

- 1 Log on to the workstation or server.
- 2 Enter the domain email address and password and click **Activate**.






NOTE:

Non-domain or personal email addresses cannot be used for activation.

- 3 Click **Close**.



The Dell Server combines the encryption key bundle with the user's credentials and with the computer's unique ID (machine ID), creating an unbreakable relationship between the key bundle, the specific computer, and the user.

- 4 Restart the computer to begin the encryption sweep.



NOTE:

The Local Management Console, accessible from the system tray icon, shows the policies sent by the Server, not the effective policy.

Troubleshoot Deferred Activation

Troubleshoot Activation

Problem: Cannot access certain files and folders

Inability to access certain files and folders is a symptom of being logged in with a different account than the one under which the user activated.

The Activation Logon dialog automatically displays even though the user has previously activated.

Possible Solution



Log out and log back in with the credentials of the activated account and try to access the files again.

In the rare event that the Encryption client cannot authenticate the user, the Activation Logon dialog prompts the user for credentials to authenticate and access encryption keys. To use the automatic re-activation feature, the *AutoReactivation* and *AutoPromptForActivation* registry keys must BOTH be enabled. Although the feature is enabled by default, it can be manually disabled. For more information, see [Disable Automatic Re-activation](#).

Error Message: Server Authentication Failed

The Server was not able to authenticate the email address and password.

Possible Solutions

- Use the email address associated with the organization. Personal email addresses cannot be used for activation.
- Re-enter the email address and password and ensure there are no typographical errors.
- Ask the administrator to verify that the email account is active and is not locked.
- Ask the administrator to reset the user's domain password.

Error Message: Network connection error

The Encryption client could not communicate with the Dell Server.

Possible Solutions

- Connect directly to the organization's network and try to activate again.
- If VPN access is required to connect to the network, check the VPN connection and try again.
- Check the Dell Server URL to ensure it matches the URL provided by the administrator.

The URL and other data that the user entered into the installer are stored in the registry. Check the accuracy of the data under [HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield] and [HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield\Servlet]

- Disconnect and reconnect:

Disconnect the computer from the network.

Reconnect to the network.

Restart the computer.

Try to connect to the network again.

Error Message: Legacy Server Not Supported

Encryption cannot be activated against a legacy server; the Dell Server must be v9.1 or higher.

Possible Solution

- Check the Dell Server URL to ensure it matches the URL provided by the administrator.

The URL and other data that the user entered into the installer are stored in the registry.

- Check the accuracy of the data under [HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield] and [HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon\CMGShield\Servlet]

Error Message: Domain User Already Activated

A second user has logged on to the local computer and tried to activate against a domain account that has already been activated.

A user can activate the Encryption client only once per domain account.

Possible Solution



Decrypt and uninstall the Encryption client while logged in as the second activated user.

Error Message: Server Error General

An error has occurred on the Server.

Possible Solution

The administrator should check the Server logs to ensure services are running.

The user should try to activate later.

Tools

CMGAd

Use the CMGAd utility prior to launching the Encryption Removal Agent to obtain the encryption key bundle. The CMGAd utility and its instructions are located in the Dell installation media (Dell-Offline-Admin-XXbit)

Log Files

In `C:\ProgramData\Del\Del Data Protection\Encryption`, look for the log file called **CmgSysTray**.

Search for the phrase "Manual activation result".

The error code is on the same line, followed by " status = "; the status indicates what went wrong.



Troubleshooting

All Clients - Troubleshooting

- **Endpoint Security Suite Pro master installer log files** are located at C:\ProgramData\Dell\Dell Data Protection\Installer.
- Windows creates unique **child installer installation log files** for the logged in user at %temp%, located at C:\Users\<<UserName>\AppData\Local\Temp.
- Windows creates log files for client prerequisites, such as Visual C++, for the logged in user at %temp%, located at C:\Users\<<UserName>\AppData\Local\Temp. For example, C:\Users\<<UserName>\AppData\Local\Temp\dd_vcristist_amd64_20160109003943.log
- Follow the instructions at <http://msdn.microsoft.com> to verify the version of Microsoft .Net that is installed on the computer targeted for installation.

Go to <https://www.microsoft.com/en-us/download/details.aspx?id=30653> to download the full version of Microsoft .Net Framework 4.5.2 or later.

- See [this document](#) if the computer targeted for installation has (or has had in the past) Dell Access installed. DDP|A is not compatible with this suite of products.

All Clients - Protection Status

A new method for deriving a device's protected status has been implemented in the Dell Security Management Server v9.8.2. Previously, the Endpoint Protected Status area in the management console's Dashboard would only denote the state of Encryption per device.

Protected status is now denoted if any of the following criteria have been met:

- Advanced Threat Prevention is installed and enabled.
- Dell Data Guardian is installed and enabled.
- Self-Encrypting Drive Management is installed, enabled, and the Pre-Boot Authentication (PBA) is enabled.
- BitLocker Manager is installed, enabled, and encryption has completed.
- Dell Encryption (Mac) is installed and enabled, and policy-based encryption has been enforced.
- Dell Encryption (Windows) is installed, enabled, Policy-Based Encryption has been set for the endpoint, and the most recent policy has been applied for the last logged on user.

Encryption Client Troubleshooting

Upgrade to the Windows 10 Creators Update

To upgrade to the Windows 10 Creators Update version, follow the instructions in the following article: <http://www.dell.com/support/article/us/en/19/SLN298382>.

(Optional) Create an Encryption Removal Agent Log File

- Before beginning the uninstall process, you can optionally create an Encryption Removal Agent log file. This log file is useful for troubleshooting an uninstall/decryption operation. If you do not intend to decrypt files during the uninstall process, you do not need to create this log file.

- The Encryption Removal Agent log file is not created until after the Encryption Removal Agent Service runs, which does not happen until the computer is restarted. Once the client is successfully uninstalled and the computer is fully decrypted, the log file is permanently deleted.
- The log file path is **C:\ProgramData\Dell\Dell Data Protection\Encryption**.
- Create the following registry entry on the computer targeted for decryption.

[HKLM\Software\Credant\DecryptionAgent]

"LogVerbosity"=DWORD:2

0: no logging

1: logs errors that prevent the Service from running

2: logs errors that prevent complete data decryption (recommended level)

3: logs information about all decrypting volumes and files

5: logs debugging information

Find TSS Version

- TSS is a component that interfaces with the TPM. To find the TSS version, go to (default location) **C:\Program Files\Dell\Dell Data Protection\Drivers\TSS\bin > tcasd_win32.exe**. Right-click the file and select **Properties**. Verify the file version on the **Details** tab.

Encryption External Media and PCS Interactions

To Ensure Media is Not Read-Only and the Port is Not Blocked

The Encryption External Media Access to unShielded Media policy interacts with Port Control System - Storage Class: External Drive Control policy. If you intend to set the Encryption External Media Access to unShielded Media policy to *Full Access*, ensure that the Storage Class: External Drive Control policy is also set to *Full Access* to ensure that the media is not set to read-only and the port is not blocked.

To Encrypt Data Written to CD/DVD

- Set Windows Media Encryption = On.
- Set EMS Exclude CD/DVD Encryption = not selected.
- Set Subclass Storage: Optical Drive Control = UDF Only.

Use WSScan

- WSScan allows you to ensure that all data is decrypted when uninstalling the Encryption client as well as view encryption status and identify unencrypted files that should be encrypted.
- Administrator privileges are required to run this utility.


Run WSScan

- 1 From the Dell installation media, copy WSScan.exe to the Windows computer to scan.
- 2 Launch a command line at the location above and enter **wsscan.exe** at the command prompt. WSScan launches.
- 3 Click **Advanced**.
- 4 Select the type of drive to scan from the drop-down menu: *All Drives, Fixed Drives, Removable Drives, or CDROMs/ DVDROMs*.
- 5 Select the desired Encryption Report Type from the drop-down menu: *Encrypted Files, Unencrypted Files, All Files, or Unencrypted Files in Violation*:



- *Encrypted Files* - To ensure that all data is decrypted when uninstalling the Encryption client. Follow your existing process for decrypting data, such as issuing a decryption policy update. After decrypting data, but before performing a restart in preparation for uninstall, run WSScan to ensure that all data is decrypted.
- *Unencrypted Files* - To identify files that are not encrypted, with an indication of whether the files should be encrypted (Y/N).
- *All Files* - To list all encrypted and unencrypted files, with an indication of whether the files should be encrypted (Y/N).
- *Unencrypted Files in Violation* - To identify files that are not encrypted that should be encrypted.


6 Click **Search**.



OR

- 1 Click **Advanced** to toggle the view to **Simple** to scan a particular folder.
- 2 Go to Scan Settings and enter the folder path in the **Search Path** field. If this field is used, the selection in the drop-down box is ignored.
- 3 If you do not want to write WSScan output to a file, clear the **Output to File** check box.
- 4 Change the default path and filename in *Path*, if desired.
- 5 Select **Add to Existing File** if you do not want to overwrite any existing WSScan output files.
- 6 Choose the output format:
 - Select Report Format for a report style list of scanned output. This is the default format.
 - Select Value Delimited File for output that can be imported into a spreadsheet application. The default delimiter is "|", although it can be changed to up to 9 alphanumeric, space, or keyboard punctuation characters.
 - Select the Quoted Values option to enclose each value in double quotation marks.
 - Select Fixed Width File for non-delimited output containing a continuous line of fixed-length information about each encrypted file.
- 7 Click **Search**.

Click **Stop Searching** to stop your search. Click **Clear** to clear displayed messages.



WSScan Command Line Usage

WSScan [-ta] [-tf] [-tr] [-tc] [drive] [-s] [-o<filepath>] [-a] [-f<format specifier>] [-r] [-u[a] [-v]] [-d<delimiter>] [-q] [-e] [-x<exclusion directory>] [-y<sleep time>]

Switch	Meaning
Drive	Drive to scan. If not specified, the default is all local fixed hard drives. Can be a mapped network drive.
-ta	Scan all drives
-tf	Scan fixed drives (default)
-tr	Scan removable drives



Switch	Meaning
-tc	Scan CDRROMs/DVDROMs
-s	Silent operation
-o	Output file path
-a	Append to output file. The default behavior truncates the output file.
-f	Report format specifier (Report, Fixed, Delimited)
-r	Run WSScan without administrator privileges. Some files may not be visible if this mode is used.
-u	Include unencrypted files in output file. This switch is sensitive to order: "u" must be first, "a" must be second (or omitted), "-" or "v" must be last.
-u-	Only include unencrypted files in output file
-ua	Report unencrypted files also, but use all user policies to display the "should" field.
-ua-	Report unencrypted files only, but use all user policies to display the "should" field.
-uv	Report unencrypted files that violate policy only (Is=No / Should=Y)
-uav	Report unencrypted files that violate policy only (Is=No / Should=Y), using all user policies.
-d	Specifies what to use as a value separator for delimited output
-q	Specifies the values that should be enclosed in quotes for delimited output
-e	Include extended encryption fields in delimited output
-x	Exclude directory from scan. Multiple exclusions are allowed.
-y	Sleep time (in milliseconds) between directories. This switch results in slower scans, but potentially a more responsive CPU.

WSScan Output

WSScan information about encrypted files contains the following information.

Example Output:

```
[2015-07-28 07:52:33] SysData.7vdlxrsb._SDENCR_: "c:\temp\Dell - test.log" is still AES256 encrypted
```

Output	Meaning
Date/time stamp	The date and time the file was scanned.
Encryption type	The type of encryption used to encrypt the file. SysData: SDE Encryption Key. User: User Encryption Key. Common: Common Encryption Key.



Output	Meaning
	WSScan does not report files encrypted using Encrypt for Sharing.
KCID	<p>The Key Computer ID.</p> <p>As shown in the example above, "7vdlxrsb"</p> <p>If you are scanning a mapped network drive, the scanning report does not return a KCID.</p>
UCID	<p>The User ID.</p> <p>As shown in the example above, "_SDENCR_"</p> <p>The UCID is shared by all the users of that computer.</p>
File	<p>The path of the encrypted file.</p> <p>As shown in the example above, "c:\temp\Dell - test.log"</p>
Algorithm	<p>The encryption algorithm being used to encrypt the file.</p> <p>As shown in the example above, "is still AES256 encrypted"</p> <p>RIJNDAEL 128</p> <p>RIJNDAEL 256</p> <p>AES 128</p> <p>AES 256</p> <p>3DES</p>

Use WSProbe

The Probing Utility is for use with all versions of the Encryption client, with the exception of Encryption External Media policies. Use the Probing Utility to:

- Scan or schedule scanning of an encrypted computer. The Probing Utility observes your Workstation Scan Priority policy.
- Temporarily disable or re-enable the current user Application Data Encryption List.
- Add or remove process names on the privileged list.
- Troubleshoot as instructed by Dell ProSupport.

Approaches to Data Encryption

If you specify policies to encrypt data on Windows devices, you can use any of the following approaches:

- The first approach is to accept the default behavior of the client. If you specify folders in Common Encrypted Folders or User Encrypted Folders, or set Encrypt "My Documents", Encrypt Outlook Personal Folders, Encrypt Temporary Files, Encrypt Temporary Internet Files, or Encrypt Windows Paging File to selected, affected files are encrypted either when they are created, or (after being created by an unmanaged user) when a managed user logs on. The client also scans folders specified in or related to these policies for possible encryption/decryption when a folder is renamed, or when the client receives changes to these policies.
- You can also set Scan Workstation on Logon to Selected. If Scan Workstation on Logon is Selected, when a user logs on, the client compares how files in currently- and previously-encrypted folders are encrypted to the user policies, and makes any necessary changes.
- To encrypt files that meet your encryption criteria but were created prior to your encryption policies going into effect, but do not want the performance impact of frequent scanning, you can use this utility to scan or schedule scanning of the computer.



Prerequisites

- The Windows device you want to work with must be encrypted.
- The user you want to work with must be logged on.

Use the Probing Utility

WSProbe.exe is located in the installation media.

Syntax

```
wsprobe [path]
```

```
wsprobe [-h]
```

```
wsprobe [-f path]
```

```
wsprobe [-u n] [-x process_names] [-i process_names]
```

Parameters


Parameter	To
path	Optionally specify a particular path on the device that you want to scan for possible encryption/ decryption. If you do not specify a path, this utility scans all folders related to your encryption policies.
-h	View command line Help.
-f	Troubleshoot as instructed by Dell ProSupport
-u	Temporarily disable or re-enable the user Application Data Encryption List. This list is only effective if Encryption Enabled is selected for the current user. Specify 0 to disable or 1 to re-enable. The current policy in force for the user is reinstated at the next logon.
-x	Add process names to the privileged list. The computer and installer process names on this list, plus those you add using this parameter or HKLM\Software\CREDANT\CMGShield\EUWPrivilegedList, are ignored if specified in the Application Data Encryption List. Separate process names with commas. If your list includes one or more spaces, enclose the list in double quotes.
-i	Remove process names previously added to the privileged list (you cannot remove hard-coded process names). Separate process names with commas. If your list includes one or more spaces, enclose the list in double quotes.

Check Encryption Removal Agent Status

The Encryption Removal Agent displays its status in the description area of the Services panel (Start > Run... > services.msc > OK) as follows. Periodically refresh the Service (highlight the Service > right-click > Refresh) to update its status.

- **Waiting for SDE Deactivation** - The Encryption client is still installed, is still configured, or both. Decryption does not start until the Encryption client is uninstalled.
- **Initial sweep** - The Service is making an initial sweep, calculating the number of encrypted files and bytes. The initial sweep occurs one time.
- **Decryption sweep** - The Service is decrypting files and possibly requesting to decrypt locked files.
- **Decrypt on Reboot (partial)** - The decryption sweep is complete and some locked files (but not all) are to be decrypted on the next restart.
- **Decrypt on Reboot** - The decryption sweep is complete and all locked files are to be decrypted on the next restart.

- **All files could not be decrypted** - The decryption sweep is complete, but all files could not be decrypted. This status means one of the following occurred:
 - The locked files could not be scheduled for decryption because they were too big, or an error occurred while making the request to unlock them.
 - An input/output error occurred while decrypting files.
 - The files could not be decrypted by policy.
 - The files are marked as should be encrypted.
 - An error occurred during the decryption sweep.
 - In all cases, a log file is created (if logging is configured) when LogVerbosity=2 (or higher) is set. To troubleshoot, set the log verbosity to 2 and restart the Encryption Removal Agent Service to force another decryption sweep. See [\(Optional\) Create an Encryption Removal Agent Log File](#) for instructions.
- **Complete** - The decryption sweep is complete. The Service, the executable, the driver, and the driver executable are all scheduled for deletion on the next restart.



SED Client Troubleshooting

Use the Initial Access Code Policy

- This policy is used to log on to a computer when network access is unavailable. Meaning, access to the Security Management Server/Security Management Server Virtual and AD are both unavailable. Only use the *Initial Access Code* policy if absolutely necessary. Dell does not recommend this method to log in. Using the *Initial Access Code* policy does not provide the same level of security as the usual method of logging in using username, domain, and password.

In addition to being a less secure method of logging in, if an end user is activated using the *Initial Access Code*, then there is no record on the Security Management Server/Security Management Server Virtual of that user activating on this computer. In turn, there is no way to generate a Response Code from the Security Management Server/Security Management Server Virtual for the end user if they fail password and self help questions.

- The *Initial Access Code* can only be used **one** time, immediately after activation. After an end user has logged in, the *Initial Access Code* will not be available again. The first domain login that occurs after the *Initial Access Code* is entered will be cached, and the *Initial Access Code* entry field will not be displayed again.
- The *Initial Access Code* will **only** display under the following circumstances:
 - A user has never activated inside the PBA.
 - The client has no connectivity to the network or Security Management Server/Security Management Server Virtual.



Use Initial Access Code

- 1 Set a value for the **Initial Access Code** policy in the Remote Management Console.
- 2 Save and commit the policy.
- 3 Start the local computer.
- 4 Enter the **Initial Access Code** when the Access Code screen displays.
- 5 Click the **blue arrow**.
- 6 Click **OK** when the Legal Notice screen displays.
- 7 Log in to Windows with the user credentials for this computer. These credentials must be part of the domain.
- 8 After logging in, open the Data Security Console and verify that the PBA user was successfully created.

Click **Log** in the top menu and look for the message *Created PBA user for <domain\username>*, which indicates the process was successful.

- 9 Shut down and restart the computer.
- 10 At the login screen, enter the username, domain, and password that was previously used to log in to Windows.

You must match the username format that was used when creating the PBA user. Thus, if you used the format domain/username, you must enter domain/username for the Username.

- 11 (Credant Manager only) Respond to the Question and Answer prompts.

Click the **blue arrow**.

- 12 Click **Login** when the Legal Notice screen displays.

Windows now launches and the computer can be used as usual.

Create a PBA Log File for Troubleshooting

- There may be cases when a PBA log file is needed for troubleshooting PBA issues, such as:
 - You are unable to see the network connection icon, yet you know there is network connectivity. The log file contains DHCP information to resolve the issue.
 - You are unable to see the Security Management Server/Security Management Server Virtual connection icon. The log file contains information to help diagnose Security Management Server/Security Management Server Virtual connectivity issues.
 - Authentication fails even when entering correct credentials. The log file used with the Security Management Server/Security Management Server Virtual Server logs can help diagnose the issue.

Capture Logs When Booting Into the PBA (Legacy PBA)

- 1 Create a folder on a USB drive and name it **\CredantSED**, at the root level of the USB drive.
- 2 Create a file named actions.txt and place it in the **\CredantSED** folder.
- 3 In actions.txt, add the line:

```
get logs
```

- 4 Save and close the file.

Do not insert the USB drive when the computer is powered down. If the USB drive is already inserted during the shutdown state, remove the USB drive.

- 5 Power on the computer and log in to the PBA. Insert the USB drive into the computer that the logs are to be collected from during this step.
- 6 After inserting the USB drive, wait for 5-10 seconds, then remove the drive.

A credpbaenv.tgz file is created in the **\CredantSED** folder that contains the needed log files.

Capture Logs When Booting Into the PBA (UEFI PBA)



- 1 Create a file called **PBAErr.log** at the root level of the USB drive.
- 2 Insert the USB drive **before** powering on the computer.
- 3 Remove the USB drive **after** reproducing the issue requiring the logs.

The PBAErr.log file will be updated and written in real-time.


Dell ControlVault Drivers

Update Dell ControlVault Drivers and Firmware

- Dell ControlVault drivers and firmware that are installed on Dell computers at the factory are outdated and should be updated by following this procedure, in this order.
- If an error message is received during client installation prompting you to exit the installer to update Dell ControlVault drivers, the message may be safely dismissed to continue with the installation of the client. The Dell ControlVault drivers (and firmware) can be updated after the client installation is complete.


Download Latest Drivers

- 1 Go to support.dell.com.




- 2 Select your computer model.






3 Select **Drivers & Downloads**.






4 Select the **Operating System** of the target computer.




5 Expand the **Security** category.






6 Download and save the Dell ControlVault Drivers.




7 Download and save the Dell ControlVault Firmware.



- 8 Copy the drivers and firmware to the target computers, if needed.

Install Dell ControlVault Driver

- 1 Navigate to the folder which you downloaded the driver installation file.



- 2 Double-click the Dell ControlVault driver to launch the self-extracting executable file.

TIP:


Be sure to install the driver first. The filename of the driver *at the time of this document creation* is ControlVault_Setup_2MYJC_A37_ZPE.exe.

- 3 Click **Continue** to begin.







- 4 Click **Ok** to unzip the driver files in the default location of C:\Dell\Drivers\




- 5 Click **Yes** to allow the creation of a new folder.



- 6 Click **Ok** when the successfully unzipped message displays.



- 7 The folder which contains the files should display after extraction. If not, navigate to the folder to which you extracted the files. In this case, the folder is **JW22F**.




- 8 Double-click **CVHCI64.MSI** to launch the driver installer. [this example is **CVHCI64.MSI** in this example (CVHCI for a 32-bit computer)].
- 9 Click **Next** at the Welcome screen.




- 10 Click **Next** to install the drivers in the default location of `C:\Program Files\Broadcom Corporation\Broadcom USH Host Components\`.







11 Select the **Complete** option and click **Next**.



12 Click **Install** to begin the installation of the drivers.



13 Optionally check the box to display the installer log file. Click **Finish** to exit the wizard.




Verify Driver Installation

- The Device Manager will have a Dell ControlVault device (and other devices) depending on the operating system and hardware configuration.

Install Dell ControlVault Firmware




- 1 Navigate to the folder which you downloaded the firmware installation file.




- 2 Double-click the Dell ControlVault firmware to launch the self-extracting executable file.
- 3 Click **Continue** to begin.




- 4 Click **Ok** to unzip the driver files in the default location of `C:\Dell\Drivers\<New Folder>`.





- 5 Click **Yes** to allow the creation of a new folder.



- 6 Click **Ok** when the successfully unzipped message displays.




- 7 The folder which contains the files should display after extraction. If not, navigate to the folder to which you extracted the files. Select the **firmware** folder.



- 8 Double-click **ushupgrade.exe** to launch the firmware installer.
- 9 Click **Start** to begin the firmware upgrade.









IMPORTANT:

You may be asked to enter the admin password if upgrading from an older version of firmware. Enter **Broadcom** as the password and click **Enter** if presented with this dialog.


Several status messages display.







10 Click **Restart** to complete the firmware upgrade.



The update of the Dell ControlVault drivers and firmware is complete.



UEFI Computers

Troubleshoot Network Connection

- In order for preboot authentication to succeed on a computer with UEFI firmware, the PBA mode must have network connectivity. By default, computers with UEFI firmware do not have network connectivity until the operating system is loaded, which occurs after PBA mode. If the computer procedure outlined in [Pre-Installation Configuration for UEFI Computers](#) is successful and is configured properly, the network connection icon displays on the preboot authentication screen when the computer is connected to the network.



- Check the network cable to ensure it is connected to the computer if the network connection icon still does not display during preboot authentication. Restart the computer to restart PBA mode if it was not connected or was loose.

TPM and BitLocker

TPM and BitLocker Error Codes

Constant/Value	Description
TPM_E_ERROR_MASK 0x80280000	This is an error mask to convert TPM hardware errors to win errors.
TPM_E_AUTHFAIL 0x80280001	Authentication failed.
TPM_E_BADINDEX 0x80280002	The index to a PCR, DIR or other register is incorrect.
TPM_E_BAD_PARAMETER 0x80280003	One or more parameters is bad.
TPM_E_AUDITFAILURE 0x80280004	An operation completed successfully but the auditing of that operation failed.
TPM_E_CLEAR_DISABLED 0x80280005	The clear disable flag is set and all clear operations now require physical access.
TPM_E_DEACTIVATED 0x80280006	Activate the TPM.
TPM_E_DISABLED 0x80280007	Enable the TPM.
TPM_E_DISABLED_CMD	The target command has been disabled.



Constant/Value	Description
0x80280008	
TPM_E_FAIL	The operation failed.
0x80280009	
TPM_E_BAD_ORDINAL	The ordinal was unknown or inconsistent.
0x8028000A	
TPM_E_INSTALL_DISABLED	The ability to install an owner is disabled.
0x8028000B	
TPM_E_INVALID_KEYHANDLE	The key handle cannot be interpreted.
0x8028000C	
TPM_E_KEYNOTFOUND	The key handle points to an invalid key.
0x8028000D	
TPM_E_INAPPROPRIATE_ENC	Unacceptable encryption scheme.
0x8028000E	
TPM_E_MIGRATEFAIL	Migration authorization failed.
0x8028000F	
TPM_E_INVALID_PCR_INFO	PCR information could not be interpreted.
0x80280010	
TPM_E_NOSPACE	No room to load key.
0x80280011	
TPM_E_NOSRK	There is no Storage Root Key (SRK) set.
0x80280012	
TPM_E_NOTSEALED_BLOB	An encrypted blob is invalid or was not created by this TPM.
0x80280013	
TPM_E_OWNER_SET	The TPM already has an owner.
0x80280014	
TPM_E_RESOURCES	The TPM has insufficient internal resources to perform the requested action.
0x80280015	
TPM_E_SHORTRANDOM	A random string was too short.
0x80280016	
TPM_E_SIZE	The TPM does not have the space to perform the operation.



Constant/Value	Description
0x80280017	
TPM_E_WRONGPCRVAL	The named PCR value does not match the current PCR value.
0x80280018	
TPM_E_BAD_PARAM_SIZE	The paramSize argument to the command has the incorrect value
0x80280019	
TPM_E_SHA_THREAD	There is no existing SHA-1 thread.
0x8028001A	
TPM_E_SHA_ERROR	The calculation is unable to proceed because the existing SHA-1 thread has already encountered an error.
0x8028001B	
TPM_E_FAILEDSELFTEST	The TPM hardware device reported a failure during its internal self test. Try restarting the computer to resolve the problem. If the problem continues, you might need to replace your TPM hardware or motherboard.
0x8028001C	
TPM_E_AUTH2FAIL	The authorization for the second key in a 2 key function failed authorization.
0x8028001D	
TPM_E_BADTAG	The tag value sent to for a command is invalid.
0x8028001E	
TPM_E_IOERROR	An IO error occurred transmitting information to the TPM.
0x8028001F	
TPM_E_ENCRYPT_ERROR	The encryption process had a problem.
0x80280020	
TPM_E_DECRYPT_ERROR	The decryption process did not complete.
0x80280021	
TPM_E_INVALID_AUTHHANDLE	An invalid handle was used.
0x80280022	
TPM_E_NO_ENDORSEMENT	The TPM does not have an Endorsement Key (EK) installed.
0x80280023	
TPM_E_INVALID_KEYUSAGE	The usage of a key is not allowed.
0x80280024	
TPM_E_WRONG_ENTITYTYPE	The submitted entity type is not allowed.
0x80280025	



Constant/Value	Description
TPM_E_INVALID_POSTINIT 0x80280026	The command was received in the wrong sequence relative to TPM_Init and a subsequent TPM_Startup.
TPM_E_INAPPROPRIATE_SIG 0x80280027	Signed data cannot include additional DER information.
TPM_E_BAD_KEY_PROPERTY 0x80280028	The key properties in TPM_KEY_PARMs are not supported by this TPM.
TPM_E_BAD_MIGRATION 0x80280029	The migration properties of this key are incorrect.
TPM_E_BAD_SCHEME 0x8028002A	The signature or encryption scheme for this key is incorrect or not permitted in this situation.
TPM_E_BAD_DATASIZE 0x8028002B	The size of the data (or blob) parameter is bad or inconsistent with the referenced key.
TPM_E_BAD_MODE 0x8028002C	A mode parameter is bad, such as capArea or subCapArea for TPM_GetCapability, physicalPresence parameter for TPM_PhysicalPresence, or migrationType for TPM_CreateMigrationBlob.
TPM_E_BAD_PRESENCE 0x8028002D	Either the physicalPresence or physicalPresenceLock bits have the wrong value.
TPM_E_BAD_VERSION 0x8028002E	The TPM cannot perform this version of the capability.
TPM_E_NO_WRAP_TRANSPORT 0x8028002F	The TPM does not allow for wrapped transport sessions.
TPM_E_AUDITFAIL_UNSUCCESSFUL 0x80280030	TPM audit construction failed and the underlying command was returning a failure code also.
TPM_E_AUDITFAIL_SUCCESSFUL 0x80280031	TPM audit construction failed and the underlying command was returning success.
TPM_E_NOTRESETABLE 0x80280032	Attempt to reset a PCR register that does not have the resettable attribute.
TPM_E_NOTLOCAL 0x80280033	Attempt to reset a PCR register that requires locality and locality modifier not part of command transport.
TPM_E_BAD_TYPE 0x80280034	Make identity blob not properly typed.



Constant/Value	Description
TPM_E_INVALID_RESOURCE 0x80280035	When saving context identified resource type does not match actual resource.
TPM_E_NOTFIPS 0x80280036	The TPM is attempting to execute a command only available when in FIPS mode.
TPM_E_INVALID_FAMILY 0x80280037	The command is attempting to use an invalid family ID.
TPM_E_NO_NV_PERMISSION 0x80280038	The permission to manipulate the NV storage is not available.
TPM_E_REQUIRES_SIGN 0x80280039	The operation requires a signed command.
TPM_E_KEY_NOTSUPPORTED 0x8028003A	Wrong operation to load an NV key.
TPM_E_AUTH_CONFLICT 0x8028003B	NV_LoadKey blob requires both owner and blob authorization.
TPM_E_AREA_LOCKED 0x8028003C	The NV area is locked and not writable.
TPM_E_BAD_LOCALITY 0x8028003D	The locality is incorrect for the attempted operation.
TPM_E_READ_ONLY 0x8028003E	The NV area is read only and cannot be written to.
TPM_E_PER_NOWRITE 0x8028003F	There is no protection on the write to the NV area.
TPM_E_FAMILYCOUNT 0x80280040	The family count value does not match.
TPM_E_WRITE_LOCKED 0x80280041	The NV area has already been written to.
TPM_E_BAD_ATTRIBUTES 0x80280042	The NV area attributes conflict.
TPM_E_INVALID_STRUCTURE 0x80280043	The structure tag and version are invalid or inconsistent.



Constant/Value	Description
TPM_E_KEY_OWNER_CONTROL 0x80280044	The key is under control of the TPM Owner and can only be evicted by the TPM Owner.
TPM_E_BAD_COUNTER 0x80280045	The counter handle is incorrect.
TPM_E_NOT_FULLWRITE 0x80280046	The write is not a complete write of the area.
TPM_E_CONTEXT_GAP 0x80280047	The gap between saved context counts is too large.
TPM_E_MAXNVWRITES 0x80280048	The maximum number of NV writes without an owner has been exceeded.
TPM_E_NOOPERATOR 0x80280049	No operator AuthData value is set.
TPM_E_RESOURCEMISSING 0x8028004A	The resource pointed to by context is not loaded.
TPM_E_DELEGATE_LOCK 0x8028004B	The delegate administration is locked.
TPM_E_DELEGATE_FAMILY 0x8028004C	Attempt to manage a family other than the delegated family.
TPM_E_DELEGATE_ADMIN 0x8028004D	Delegation table management not enabled.
TPM_E_TRANSPORT_NOTEXCLUSIVE 0x8028004E	There was a command executed outside of an exclusive transport session.
TPM_E_OWNER_CONTROL 0x8028004F	Attempt to context save a owner evict controlled key.
TPM_E_DAA_RESOURCES 0x80280050	The DAA command has no resources available to execute the command.
TPM_E_DAA_INPUT_DATA0 0x80280051	The consistency check on DAA parameter inputData0 has failed.
TPM_E_DAA_INPUT_DATA1 0x80280052	The consistency check on DAA parameter inputData1 has failed.



Constant/Value	Description
TPM_E_DAA_ISSUER_SETTINGS 0x80280053	The consistency check on DAA_issuerSettings has failed.
TPM_E_DAA_TPM_SETTINGS 0x80280054	The consistency check on DAA_tpmSpecific has failed.
TPM_E_DAA_STAGE 0x80280055	The atomic process indicated by the submitted DAA command is not the expected process.
TPM_E_DAA_ISSUER_VALIDITY 0x80280056	The issuer's validity check has detected an inconsistency.
TPM_E_DAA_WRONG_W 0x80280057	The consistency check on w has failed.
TPM_E_BAD_HANDLE 0x80280058	The handle is incorrect.
TPM_E_BAD_DELEGATE 0x80280059	Delegation is not correct.
TPM_E_BADCONTEXT 0x8028005A	The context blob is invalid.
TPM_E_TOOMANYCONTEXTS 0x8028005B	Too many contexts held by the TPM.
TPM_E_MA_TICKET_SIGNATURE 0x8028005C	Migration authority signature validation failure.
TPM_E_MA_DESTINATION 0x8028005D	Migration destination not authenticated.
TPM_E_MA_SOURCE 0x8028005E	Migration source incorrect.
TPM_E_MA_AUTHORITY 0x8028005F	Incorrect migration authority.
TPM_E_PERMANENTEK 0x80280061	Attempt to revoke the EK and the EK is not revocable.
TPM_E_BAD_SIGNATURE 0x80280062	Bad signature of CMK ticket.



Constant/Value	Description
TPM_E_NOCONTEXTSPACE 0x80280063	There is no room in the context list for additional contexts.
TPM_E_COMMAND_BLOCKED 0x80280400	The command was blocked.
TPM_E_INVALID_HANDLE 0x80280401	The specified handle was not found.
TPM_E_DUPLICATE_VHANDLE 0x80280402	The TPM returned a duplicate handle and the command needs to be resubmitted.
TPM_E_EMBEDDED_COMMAND_BLOCKED 0x80280403	The command within the transport was blocked.
TPM_E_EMBEDDED_COMMAND_UNSUPPORTED 0x80280404	The command within the transport is not supported.
TPM_E_RETRY 0x80280800	The TPM is too busy to respond to the command immediately, but the command could be resubmitted at a later time.
TPM_E_NEEDS_SELFTEST 0x80280801	SelfTestFull has not been run.
TPM_E_DOING_SELFTEST 0x80280802	The TPM is currently executing a full self test.
TPM_E_DEFEND_LOCK_RUNNING 0x80280803	The TPM is defending against dictionary attacks and is in a time-out period.
TBS_E_INTERNAL_ERROR 0x80284001	An internal software error has been detected.
TBS_E_BAD_PARAMETER 0x80284002	One or more input parameters is bad.
TBS_E_INVALID_OUTPUT_POINTER 0x80284003	A specified output pointer is bad.
TBS_E_INVALID_CONTEXT 0x80284004	The specified context handle does not refer to a valid context.
TBS_E_INSUFFICIENT_BUFFER 0x80284005	A specified output buffer is too small.



Constant/Value	Description
TBS_E_IOERROR 0x80284006	An error occurred while communicating with the TPM.
TBS_E_INVALID_CONTEXT_PARAM 0x80284007	One or more context parameters is invalid.
TBS_E_SERVICE_NOT_RUNNING 0x80284008	The TBS service is not running and could not be started.
TBS_E_TOO_MANY_TBS_CONTEXTS 0x80284009	A new context could not be created because there are too many open contexts.
TBS_E_TOO_MANY_RESOURCES 0x8028400A	A new virtual resource could not be created because there are too many open virtual resources.
TBS_E_SERVICE_START_PENDING 0x8028400B	The TBS service has been started but is not yet running.
TBS_E_PPI_NOT_SUPPORTED 0x8028400C	The physical presence interface is not supported.
TBS_E_COMMAND_CANCELED 0x8028400D	The command was canceled.
TBS_E_BUFFER_TOO_LARGE 0x8028400E	The input or output buffer is too large.
TBS_E_TPM_NOT_FOUND 0x8028400F	A compatible TPM Security Device cannot be found on this computer.
TBS_E_SERVICE_DISABLED 0x80284010	The TBS service has been disabled.
TBS_E_NO_EVENT_LOG 0x80284011	No TCG event log is available.
TBS_E_ACCESS_DENIED 0x80284012	The caller does not have the appropriate rights to perform the requested operation.
TBS_E_PROVISIONING_NOT_ALLOWED 0x80284013	The TPM provisioning action is not allowed by the specified flags. For provisioning to be successful, one of several actions may be required. The TPM management console (tpm.msc) action to make the TPM Ready may help. For further information, see the documentation for the Win32_Tpm WMI method 'Provision'. (The actions that may be required include importing the TPM Owner Authorization value into the system, calling the Win32_Tpm WMI method for provisioning the TPM and specifying TRUE for either 'ForceClear_Allowed' or 'PhysicalPresencePrompts_Allowed' (as



Constant/Value	Description
TBS_E_PPI_FUNCTION_UNSUPPORTED 0x80284014	indicated by the value returned in the Additional Information), or enabling the TPM in the system BIOS.) The Physical Presence Interface of this firmware does not support the requested method.
TBS_E_OWNERAUTH_NOT_FOUND 0x80284015	The requested TPM OwnerAuth value was not found.
TBS_E_PROVISIONING_INCOMPLETE 0x80284016	The TPM provisioning did not complete. For more information on completing the provisioning, call the Win32_Tpm WMI method for provisioning the TPM ('Provision') and check the returned Information.
TPMAPI_E_INVALID_STATE 0x80290100	The command buffer is not in the correct state.
TPMAPI_E_NOT_ENOUGH_DATA 0x80290101	The command buffer does not contain enough data to satisfy the request.
TPMAPI_E_TOO_MUCH_DATA 0x80290102	The command buffer cannot contain any more data.
TPMAPI_E_INVALID_OUTPUT_POINTER 0x80290103	One or more output parameters was NULL or invalid.
TPMAPI_E_INVALID_PARAMETER 0x80290104	One or more input parameters is invalid.
TPMAPI_E_OUT_OF_MEMORY 0x80290105	Not enough memory was available to satisfy the request.
TPMAPI_E_BUFFER_TOO_SMALL 0x80290106	The specified buffer was too small.
TPMAPI_E_INTERNAL_ERROR 0x80290107	An internal error was detected.
TPMAPI_E_ACCESS_DENIED 0x80290108	The caller does not have the appropriate rights to perform the requested operation.
TPMAPI_E_AUTHORIZATION_FAILED 0x80290109	The specified authorization information was invalid.
TPMAPI_E_INVALID_CONTEXT_HANDLE 0x8029010A	The specified context handle was not valid.



Constant/Value	Description
TPMAPI_E_TBS_COMMUNICATION_ERROR 0x8029010B	An error occurred while communicating with the TBS.
TPMAPI_E_TPM_COMMAND_ERROR 0x8029010C	The TPM returned an unexpected result.
TPMAPI_E_MESSAGE_TOO_LARGE 0x8029010D	The message was too large for the encoding scheme.
TPMAPI_E_INVALID_ENCODING 0x8029010E	The encoding in the blob was not recognized.
TPMAPI_E_INVALID_KEY_SIZE 0x8029010F	The key size is not valid.
TPMAPI_E_ENCRYPTION_FAILED 0x80290110	The encryption operation failed.
TPMAPI_E_INVALID_KEY_PARAMS 0x80290111	The key parameters structure was not valid
TPMAPI_E_INVALID_MIGRATION_AUTHORIZATION_BLOB 0x80290112	The requested supplied data does not appear to be a valid migration authorization blob.
TPMAPI_E_INVALID_PCR_INDEX 0x80290113	The specified PCR index was invalid
TPMAPI_E_INVALID_DELEGATE_BLOB 0x80290114	The data given does not appear to be a valid delegate blob.
TPMAPI_E_INVALID_CONTEXT_PARAMS 0x80290115	One or more of the specified context parameters was not valid.
TPMAPI_E_INVALID_KEY_BLOB 0x80290116	The data given does not appear to be a valid key blob
TPMAPI_E_INVALID_PCR_DATA 0x80290117	The specified PCR data was invalid.
TPMAPI_E_INVALID_OWNER_AUTH 0x80290118	The format of the owner auth data was invalid.
TPMAPI_E_FIPS_RNG_CHECK_FAILED 0x80290119	The random number generated did not pass FIPS RNG check.



Constant/Value	Description
TPMAPI_E_EMPTY_TCG_LOG 0x8029011A	The TCG Event Log does not contain any data.
TPMAPI_E_INVALID_TCG_LOG_ENTRY 0x8029011B	An entry in the TCG Event Log was invalid.
TPMAPI_E_TCG_SEPARATOR_ABSENT 0x8029011C	A TCG Separator was not found.
TPMAPI_E_TCG_INVALID_DIGEST_ENTRY 0x8029011D	A digest value in a TCG Log entry did not match hashed data.
TPMAPI_E_POLICY_DENIES_OPERATION 0x8029011E	The requested operation was blocked by current TPM policy. Please contact your system administrator for assistance.
TBSIMP_E_BUFFER_TOO_SMALL 0x80290200	The specified buffer was too small.
TBSIMP_E_CLEANUP_FAILED 0x80290201	The context could not be cleaned up.
TBSIMP_E_INVALID_CONTEXT_HANDLE 0x80290202	The specified context handle is invalid.
TBSIMP_E_INVALID_CONTEXT_PARAM 0x80290203	An invalid context parameter was specified.
TBSIMP_E_TPM_ERROR 0x80290204	An error occurred while communicating with the TPM
TBSIMP_E_HASH_BAD_KEY 0x80290205	No entry with the specified key was found.
TBSIMP_E_DUPLICATE_VHANDLE 0x80290206	The specified virtual handle matches a virtual handle already in use.
TBSIMP_E_INVALID_OUTPUT_POINTER 0x80290207	The pointer to the returned handle location was NULL or invalid
TBSIMP_E_INVALID_PARAMETER 0x80290208	One or more parameters is invalid
TBSIMP_E_RPC_INIT_FAILED 0x80290209	The RPC subsystem could not be initialized.



Constant/Value	Description
TBSIMP_E_SCHEDULER_NOT_RUNNING 0x8029020A	The TBS scheduler is not running.
TBSIMP_E_COMMAND_CANCELED 0x8029020B	The command was canceled.
TBSIMP_E_OUT_OF_MEMORY 0x8029020C	There was not enough memory to fulfill the request
TBSIMP_E_LIST_NO_MORE_ITEMS 0x8029020D	The specified list is empty, or the iteration has reached the end of the list.
TBSIMP_E_LIST_NOT_FOUND 0x8029020E	The specified item was not found in the list.
TBSIMP_E_NOT_ENOUGH_SPACE 0x8029020F	The TPM does not have enough space to load the requested resource.
TBSIMP_E_NOT_ENOUGH_TPM_CONTEXTS 0x80290210	There are too many TPM contexts in use.
TBSIMP_E_COMMAND_FAILED 0x80290211	The TPM command failed.
TBSIMP_E_UNKNOWN_ORDINAL 0x80290212	The TBS does not recognize the specified ordinal.
TBSIMP_E_RESOURCE_EXPIRED 0x80290213	The requested resource is no longer available.
TBSIMP_E_INVALID_RESOURCE 0x80290214	The resource type did not match.
TBSIMP_E_NOTHING_TO_UNLOAD 0x80290215	No resources can be unloaded.
TBSIMP_E_HASH_TABLE_FULL 0x80290216	No new entries can be added to the hash table.
TBSIMP_E_TOO_MANY_TBS_CONTEXTS 0x80290217	A new TBS context could not be created because there are too many open contexts.
TBSIMP_E_TOO_MANY_RESOURCES 0x80290218	A new virtual resource could not be created because there are too many open virtual resources.



Constant/Value	Description
TBSIMP_E_PPI_NOT_SUPPORTED 0x80290219	The physical presence interface is not supported.
TBSIMP_E_TPM_INCOMPATIBLE 0x8029021A	TBS is not compatible with the version of TPM found on the system.
TBSIMP_E_NO_EVENT_LOG 0x8029021B	No TCG event log is available.
TPM_E_PPI_ACPI_FAILURE 0x80290300	A general error was detected when attempting to acquire the BIOS's response to a Physical Presence command.
TPM_E_PPI_USER_ABORT 0x80290301	The user failed to confirm the TPM operation request.
TPM_E_PPI_BIOS_FAILURE 0x80290302	The BIOS failure prevented the successful execution of the requested TPM operation (e.g. invalid TPM operation request, BIOS communication error with the TPM).
TPM_E_PPI_NOT_SUPPORTED 0x80290303	The BIOS does not support the physical presence interface.
TPM_E_PPI_BLOCKED_IN_BIOS 0x80290304	The Physical Presence command was blocked by current BIOS settings. The system owner may be able to reconfigure the BIOS settings to allow the command.
TPM_E_PCP_ERROR_MASK 0x80290400	This is an error mask to convert Platform Crypto Provider errors to win errors.
TPM_E_PCP_DEVICE_NOT_READY 0x80290401	The Platform Crypto Device is currently not ready. It needs to be fully provisioned to be operational.
TPM_E_PCP_INVALID_HANDLE 0x80290402	The handle provided to the Platform Crypto Provider is invalid.
TPM_E_PCP_INVALID_PARAMETER 0x80290403	A parameter provided to the Platform Crypto Provider is invalid.
TPM_E_PCP_FLAG_NOT_SUPPORTED 0x80290404	A provided flag to the Platform Crypto Provider is not supported.
TPM_E_PCP_NOT_SUPPORTED 0x80290405	The requested operation is not supported by this Platform Crypto Provider.
TPM_E_PCP_BUFFER_TOO_SMALL 0x80290406	The buffer is too small to contain all data. No information has been written to the buffer.



Constant/Value	Description
TPM_E_PCP_INTERNAL_ERROR 0x80290407	An unexpected internal error has occurred in the Platform Crypto Provider.
TPM_E_PCP_AUTHENTICATION_FAILED 0x80290408	The authorization to use a provider object has failed.
TPM_E_PCP_AUTHENTICATION_IGNORED 0x80290409	The Platform Crypto Device has ignored the authorization for the provider object, to mitigate against a dictionary attack.
TPM_E_PCP_POLICY_NOT_FOUND 0x8029040A	The referenced policy was not found.
TPM_E_PCP_PROFILE_NOT_FOUND 0x8029040B	The referenced profile was not found.
TPM_E_PCP_VALIDATION_FAILED 0x8029040C	The validation was not successful.
PLA_E_DCS_NOT_FOUND 0x80300002	Data Collector Set was not found.
PLA_E_DCS_IN_USE 0x803000AA	The Data Collector Set or one of its dependencies is already in use.
PLA_E_TOO_MANY_FOLDERS 0x80300045	Unable to start Data Collector Set because there are too many folders.
PLA_E_NO_MIN_DISK 0x80300070	Not enough free disk space to start Data Collector Set.
PLA_E_DCS_ALREADY_EXISTS 0x803000B7	Data Collector Set already exists.
PLA_S_PROPERTY_IGNORED 0x00300100	Property value will be ignored.
PLA_E_PROPERTY_CONFLICT 0x80300101	Property value conflict.
PLA_E_DCS_SINGLETON_REQUIRED 0x80300102	The current configuration for this Data Collector Set requires that it contain exactly one Data Collector.
PLA_E_CREDENTIALS_REQUIRED 0x80300103	A user account is required in order to commit the current Data Collector Set properties.



Constant/Value	Description
PLA_E_DCS_NOT_RUNNING 0x80300104	Data Collector Set is not running.
PLA_E_CONFLICT_INCL_EXCL_API 0x80300105	A conflict was detected in the list of include/exclude APIs. Do not specify the same API in both the include list and the exclude list.
PLA_E_NETWORK_EXE_NOT_VALID 0x80300106	The executable path you have specified refers to a network share or UNC path.
PLA_E_EXE_ALREADY_CONFIGURED 0x80300107	The executable path you have specified is already configured for API tracing.
PLA_E_EXE_PATH_NOT_VALID 0x80300108	The executable path you have specified does not exist. Verify that the specified path is correct.
PLA_E_DC_ALREADY_EXISTS 0x80300109	Data Collector already exists.
PLA_E_DCS_START_WAIT_TIMEOUT 0x8030010A	The wait for the Data Collector Set start notification has timed out.
PLA_E_DC_START_WAIT_TIMEOUT 0x8030010B	The wait for the Data Collector to start has timed out.
PLA_E_REPORT_WAIT_TIMEOUT 0x8030010C	The wait for the report generation tool to finish has timed out.
PLA_E_NO_DUPLICATES 0x8030010D	Duplicate items are not allowed.
PLA_E_EXE_FULL_PATH_REQUIRED 0x8030010E	When specifying the executable that you want to trace, you must specify a full path to the executable and not just a filename.
PLA_E_INVALID_SESSION_NAME 0x8030010F	The session name provided is invalid.
PLA_E_PLA_CHANNEL_NOT_ENABLED 0x80300110	The Event Log channel Microsoft-Windows-Diagnosis-PLA/Operational must be enabled to perform this operation.
PLA_E_TASKSCHED_CHANNEL_NOT_ENABLED 0x80300111	The Event Log channel Microsoft-Windows-TaskScheduler must be enabled to perform this operation.
PLA_E_RULES_MANAGER_FAILED 0x80300112	The execution of the Rules Manager failed.



Constant/Value	Description
PLA_E_CABAPI_FAILURE 0x80300113	An error occurred while attempting to compress or extract the data.
FVE_E_LOCKED_VOLUME 0x80310000	This drive is locked by BitLocker Drive Encryption. You must unlock this drive from Control Panel.
FVE_E_NOT_ENCRYPTED 0x80310001	The drive is not encrypted.
FVE_E_NO_TPM_BIOS 0x80310002	The BIOS did not correctly communicate with the TPM. Contact the computer manufacturer for BIOS upgrade instructions.
FVE_E_NO_MBR_METRIC 0x80310003	The BIOS did not correctly communicate with the master boot record (MBR). Contact the computer manufacturer for BIOS upgrade instructions.
FVE_E_NO_BOOTSECTOR_METRIC 0x80310004	A required TPM measurement is missing. If there is a bootable CD or DVD in your computer, remove it, restart the computer, and turn on BitLocker again. If the problem persists, ensure the master boot record is up to date.
FVE_E_NO_BOOTMGR_METRIC 0x80310005	The boot sector of this drive is not compatible with BitLocker Drive Encryption. Use the Bootrec.exe tool in the Windows Recovery Environment to update or repair the boot manager (BOOTMGR).
FVE_E_WRONG_BOOTMGR 0x80310006	The boot manager of this operating system is not compatible with BitLocker Drive Encryption. Use the Bootrec.exe tool in the Windows Recovery Environment to update or repair the boot manager (BOOTMGR).
FVE_E_SECURE_KEY_REQUIRED 0x80310007	At least one secure key protector is required for this operation to be performed.
FVE_E_NOT_ACTIVATED 0x80310008	BitLocker Drive Encryption is not enabled on this drive. Turn on BitLocker.
FVE_E_ACTION_NOT_ALLOWED 0x80310009	BitLocker Drive Encryption cannot perform requested action. This condition may occur when two requests are issued at the same time. Wait a few moments and then try the action again.
FVE_E_AD_SCHEMA_NOT_INSTALLED 0x8031000A	The Active Directory Domain Services forest does not contain the required attributes and classes to host BitLocker Drive Encryption or TPM information. Contact your domain administrator to verify that any required BitLocker Active Directory schema extensions have been installed.
FVE_E_AD_INVALID_DATATYPE 0x8031000B	The type of the data obtained from Active Directory was not expected. The BitLocker recovery information may be missing or corrupted.
FVE_E_AD_INVALID_DATASIZE 0x8031000C	The size of the data obtained from Active Directory was not expected. The BitLocker recovery information may be missing or corrupted.



Constant/Value	Description
FVE_E_AD_NO_VALUES 0x8031000D	The attribute read from Active Directory does not contain any values. The BitLocker recovery information may be missing or corrupted.
FVE_E_AD_ATTR_NOT_SET 0x8031000E	The attribute was not set. Verify that you are logged on with a domain account that has the ability to write information to Active Directory objects.
FVE_E_AD_GUID_NOT_FOUND 0x8031000F	The specified attribute cannot be found in Active Directory Domain Services. Contact your domain administrator to verify that any required BitLocker Active Directory schema extensions have been installed.
FVE_E_BAD_INFORMATION 0x80310010	The BitLocker metadata for the encrypted drive is not valid. You can attempt to repair the drive to restore access.
FVE_E_TOO_SMALL 0x80310011	The drive cannot be encrypted because it does not have enough free space. Delete any unnecessary data on the drive to create additional free space and then try again.
FVE_E_SYSTEM_VOLUME 0x80310012	The drive cannot be encrypted because it contains system boot information. Create a separate partition for use as the system drive that contains the boot information and a second partition for use as the operating system drive and then encrypt the operating system drive.
FVE_E_FAILED_WRONG_FS 0x80310013	The drive cannot be encrypted because the file system is not supported.
FVE_E_BAD_PARTITION_SIZE 0x80310014	The file system size is larger than the partition size in the partition table. This drive may be corrupt or may have been tampered with. To use it with BitLocker, you must reformat the partition.
FVE_E_NOT_SUPPORTED 0x80310015	This drive cannot be encrypted.
FVE_E_BAD_DATA 0x80310016	The data is not valid.
FVE_E_VOLUME_NOT_BOUND 0x80310017	The data drive specified is not set to automatically unlock on the current computer and cannot be unlocked automatically.
FVE_E_TPM_NOT_OWNED 0x80310018	You must initialize the TPM before you can use BitLocker Drive Encryption.
FVE_E_NOT_DATA_VOLUME 0x80310019	The operation attempted cannot be performed on an operating system drive.
FVE_E_AD_INSUFFICIENT_BUFFER 0x8031001A	The buffer supplied to a function was insufficient to contain the returned data. Increase the buffer size before running the function again.
FVE_E_CONV_READ	A read operation failed while converting the drive. The drive was not converted. Please re-enable BitLocker.



Constant/Value	Description
0x8031001B	
FVE_E_CONV_WRITE	A write operation failed while converting the drive. The drive was not converted. Please re-enable BitLocker.
0x8031001C	
FVE_E_KEY_REQUIRED	One or more BitLocker key protectors are required. You cannot delete the last key on this drive.
0x8031001D	
FVE_E_CLUSTERING_NOT_SUPPORTED	Cluster configurations are not supported by BitLocker Drive Encryption.
0x8031001E	
FVE_E_VOLUME_BOUND_ALREADY	The drive specified is already configured to be automatically unlocked on the current computer.
0x8031001F	
FVE_E_OS_NOT_PROTECTED	The operating system drive is not protected by BitLocker Drive Encryption.
0x80310020	
FVE_E_PROTECTION_DISABLED	BitLocker Drive Encryption has been suspended on this drive. All BitLocker key protectors configured for this drive are effectively disabled, and the drive will be automatically unlocked using an unencrypted (clear) key.
0x80310021	
FVE_E_RECOVERY_KEY_REQUIRED	The drive you are attempting to lock does not have any key protectors available for encryption because BitLocker protection is currently suspended. Re-enable BitLocker to lock this drive.
0x80310022	
FVE_E_FOREIGN_VOLUME	BitLocker cannot use the TPM to protect a data drive. TPM protection can only be used with the operating system drive.
0x80310023	
FVE_E_OVERLAPPED_UPDATE	The BitLocker metadata for the encrypted drive cannot be updated because it was locked for updating by another process. Please try this process again.
0x80310024	
FVE_E_TPM_SRK_AUTH_NOT_ZERO	The authorization data for the storage root key (SRK) of the TPM is not zero and is therefore incompatible with BitLocker. Please initialize the TPM before attempting to use it with BitLocker.
0x80310025	
FVE_E_FAILED_SECTOR_SIZE	The drive encryption algorithm cannot be used on this sector size.
0x80310026	
FVE_E_FAILED_AUTHENTICATION	The drive cannot be unlocked with the key provided. Confirm that you have provided the correct key and try again.
0x80310027	
FVE_E_NOT_OS_VOLUME	The drive specified is not the operating system drive.
0x80310028	
FVE_E_AUTO_UNLOCK_ENABLED	BitLocker Drive Encryption cannot be turned off on the operating system drive until the auto unlock feature has been disabled for the fixed data drives and removable data drives associated with this computer.
0x80310029	



Constant/Value	Description
FVE_E_WRONG_BOOTSECTOR 0x8031002A	The system partition boot sector does not perform TPM measurements. Use the Bootrec.exe tool in the Windows Recovery Environment to update or repair the boot sector.
FVE_E_WRONG_SYSTEM_FS 0x8031002B	BitLocker Drive Encryption operating system drives must be formatted with the NTFS file system in order to be encrypted. Convert the drive to NTFS, and then turn on BitLocker.
FVE_E_POLICY_PASSWORD_REQUIRED 0x8031002C	Group Policy settings require that a recovery password be specified before encrypting the drive.
FVE_E_CANNOT_SET_FVEK_ENCRYPTED 0x8031002D	The drive encryption algorithm and key cannot be set on a previously encrypted drive. To encrypt this drive with BitLocker Drive Encryption, remove the previous encryption and then turn on BitLocker.
FVE_E_CANNOT_ENCRYPT_NO_KEY 0x8031002E	BitLocker Drive Encryption cannot encrypt the specified drive because an encryption key is not available. Add a key protector to encrypt this drive.
FVE_E_BOOTABLE_CDDVD 0x80310030	BitLocker Drive Encryption detected bootable media (CD or DVD) in the computer. Remove the media and restart the computer before configuring BitLocker.
FVE_E_PROTECTOR_EXISTS 0x80310031	This key protector cannot be added. Only one key protector of this type is allowed for this drive.
FVE_E_RELATIVE_PATH 0x80310032	The recovery password file was not found because a relative path was specified. Recovery passwords must be saved to a fully qualified path. Environment variables configured on the computer can be used in the path.
FVE_E_PROTECTOR_NOT_FOUND 0x80310033	The specified key protector was not found on the drive. Try another key protector.
FVE_E_INVALID_KEY_FORMAT 0x80310034	The recovery key provided is corrupt and cannot be used to access the drive. An alternative recovery method, such as recovery password, a data recovery agent, or a backup version of the recovery key must be used to recover access to the drive.
FVE_E_INVALID_PASSWORD_FORMAT 0x80310035	The format of the recovery password provided is invalid. BitLocker recovery passwords are 48 digits. Verify that the recovery password is in the correct format and then try again.
FVE_E_FIPS_RNG_CHECK_FAILED 0x80310036	The random number generator check test failed.
FVE_E_FIPS_PREVENTS_RECOVERY_PASSWORD 0x80310037	The Group Policy setting requiring FIPS compliance prevents a local recovery password from being generated or used by BitLocker Drive Encryption. When operating in FIPS-compliant mode, BitLocker recovery options can be either a recovery key stored on a USB drive or recovery through a data recovery agent.
FVE_E_FIPS_PREVENTS_EXTERNAL_KEY_EXPORT 0x80310038	The Group Policy setting requiring FIPS compliance prevents the recovery password from being saved to Active Directory. When operating in FIPS-compliant mode, BitLocker recovery options can be either a recovery key stored on a USB drive or recovery through



Constant/Value	Description
	a data recovery agent. Check your Group Policy settings configuration.
FVE_E_NOT_DECRYPTED 0x80310039	The drive must be fully decrypted to complete this operation.
FVE_E_INVALID_PROTECTOR_TYPE 0x8031003A	The key protector specified cannot be used for this operation.
FVE_E_NO_PROTECTORS_TO_TEST 0x8031003B	No key protectors exist on the drive to perform the hardware test.
FVE_E_KEYFILE_NOT_FOUND 0x8031003C	The BitLocker startup key or recovery password cannot be found on the USB device. Verify that you have the correct USB device, that the USB device is plugged into the computer on an active USB port, restart the computer, and then try again. If the problem persists, contact the computer manufacturer for BIOS upgrade instructions.
FVE_E_KEYFILE_INVALID 0x8031003D	The BitLocker startup key or recovery password file provided is corrupt or invalid. Verify that you have the correct startup key or recovery password file and try again.
FVE_E_KEYFILE_NO_VMK 0x8031003E	The BitLocker encryption key cannot be obtained from the startup key or recovery password. Verify that you have the correct startup key or recovery password and try again.
FVE_E_TPM_DISABLED 0x8031003F	The TPM is disabled. The TPM must be enabled, initialized, and have valid ownership before it can be used with BitLocker Drive Encryption.
FVE_E_NOT_ALLOWED_IN_SAFE_MODE 0x80310040	The BitLocker configuration of the specified drive cannot be managed because this computer is currently operating in Safe Mode. While in Safe Mode, BitLocker Drive Encryption can only be used for recovery purposes.
FVE_E_TPM_INVALID_PCR 0x80310041	The TPM was not able to unlock the drive because the system boot information has changed or a PIN was not provided correctly. Verify that the drive has not been tampered with and that changes to the system boot information were caused by a trusted source. After verifying that the drive is safe to access, use the BitLocker recovery console to unlock the drive and then suspend and resume BitLocker to update system boot information that BitLocker associates with this drive.
FVE_E_TPM_NO_VMK 0x80310042	The BitLocker encryption key cannot be obtained from the TPM.
FVE_E_PIN_INVALID 0x80310043	The BitLocker encryption key cannot be obtained from the TPM and PIN.
FVE_E_AUTH_INVALID_APPLICATION 0x80310044	A boot application has changed since BitLocker Drive Encryption was enabled.



Constant/Value	Description
FVE_E_AUTH_INVALID_CONFIG 0x80310045	The Boot Configuration Data (BCD) settings have changed since BitLocker Drive Encryption was enabled.
FVE_E_FIPS_DISABLE_PROTECTION_NOT_ALLOWED 0x80310046	The Group Policy setting requiring FIPS compliance prohibits the use of unencrypted keys, which prevents BitLocker from being suspended on this drive. Please contact your domain administrator for more information.
FVE_E_FS_NOT_EXTENDED 0x80310047	This drive cannot be encrypted by BitLocker Drive Encryption because the file system does not extend to the end of the drive. Repartition this drive and then try again.
FVE_E_FIRMWARE_TYPE_NOT_SUPPORTED 0x80310048	BitLocker Drive Encryption cannot be enabled on the operating system drive. Contact the computer manufacturer for BIOS upgrade instructions.
FVE_E_NO_LICENSE 0x80310049	This version of Windows does not include BitLocker Drive Encryption. To use BitLocker Drive Encryption, please upgrade the operating system.
FVE_E_NOT_ON_STACK 0x8031004A	BitLocker Drive Encryption cannot be used because critical BitLocker system files are missing or corrupted. Use Windows Startup Repair to restore these files to your computer.
FVE_E_FS_MOUNTED 0x8031004B	The drive cannot be locked when the drive is in use.
FVE_E_TOKEN_NOT_IMPERSONATED 0x8031004C	The access token associated with the current thread is not an impersonated token.
FVE_E_DRY_RUN_FAILED 0x8031004D	The BitLocker encryption key cannot be obtained. Verify that the TPM is enabled and ownership has been taken. If this computer does not have a TPM, verify that the USB drive is inserted and available.
FVE_E_REBOOT_REQUIRED 0x8031004E	You must restart your computer before continuing with BitLocker Drive Encryption.
FVE_E_DEBUGGER_ENABLED 0x8031004F	Drive encryption cannot occur while boot debugging is enabled. Use the bcdedit command-line tool to turn off boot debugging.
FVE_E_RAW_ACCESS 0x80310050	No action was taken as BitLocker Drive Encryption is in raw access mode.
FVE_E_RAW_BLOCKED 0x80310051	BitLocker Drive Encryption cannot enter raw access mode for this drive because the drive is currently in use.
FVE_E_BCD_APPLICATIONS_PATH_INCORRECT 0x80310052	The path specified in the Boot Configuration Data (BCD) for a BitLocker Drive Encryption integrity-protected application is incorrect. Please verify and correct your BCD settings and try again.



Constant/Value	Description
FVE_E_NOT_ALLOWED_IN_VERSION 0x80310053	BitLocker Drive Encryption can only be used for limited provisioning or recovery purposes when the computer is running in pre-installation or recovery environments.
FVE_E_NO_AUTOUNLOCK_MASTER_KEY 0x80310054	The auto-unlock master key was not available from the operating system drive.
FVE_E_MOR_FAILED 0x80310055	The system firmware failed to enable clearing of system memory when the computer was restarted.
FVE_E_HIDDEN_VOLUME 0x80310056	The hidden drive cannot be encrypted.
FVE_E_TRANSIENT_STATE 0x80310057	BitLocker encryption keys were ignored because the drive was in a transient state.
FVE_E_PUBKEY_NOT_ALLOWED 0x80310058	Public key based protectors are not allowed on this drive.
FVE_E_VOLUME_HANDLE_OPEN 0x80310059	BitLocker Drive Encryption is already performing an operation on this drive. Please complete all operations before continuing.
FVE_E_NO_FEATURE_LICENSE 0x8031005A	This version of Windows does not support this feature of BitLocker Drive Encryption. To use this feature, upgrade the operating system.
FVE_E_INVALID_STARTUP_OPTIONS 0x8031005B	The Group Policy settings for BitLocker startup options are in conflict and cannot be applied. Contact your system administrator for more information.
FVE_E_POLICY_RECOVERY_PASSWORD_NOT_ALLOWED 0x8031005C	Group policy settings do not permit the creation of a recovery password.
FVE_E_POLICY_RECOVERY_PASSWORD_REQUIRED 0x8031005D	Group policy settings require the creation of a recovery password.
FVE_E_POLICY_RECOVERY_KEY_NOT_ALLOWED 0x8031005E	Group policy settings do not permit the creation of a recovery key.
FVE_E_POLICY_RECOVERY_KEY_REQUIRED 0x8031005F	Group policy settings require the creation of a recovery key.
FVE_E_POLICY_STARTUP_PIN_NOT_ALLOWED 0x80310060	Group policy settings do not permit the use of a PIN at startup. Please choose a different BitLocker startup option.
FVE_E_POLICY_STARTUP_PIN_REQUIRED 0x80310061	Group policy settings require the use of a PIN at startup. Please choose this BitLocker startup option.



Constant/Value	Description
FVE_E_POLICY_STARTUP_KEY_NOT_ALLOWED 0x80310062	Group policy settings do not permit the use of a startup key. Please choose a different BitLocker startup option.
FVE_E_POLICY_STARTUP_KEY_REQUIRED 0x80310063	Group policy settings require the use of a startup key. Please choose this BitLocker startup option.
FVE_E_POLICY_STARTUP_PIN_KEY_NOT_ALLOWED 0x80310064	Group policy settings do not permit the use of a startup key and PIN. Please choose a different BitLocker startup option.
FVE_E_POLICY_STARTUP_PIN_KEY_REQUIRED 0x80310065	Group policy settings require the use of a startup key and PIN. Please choose this BitLocker startup option.
FVE_E_POLICY_STARTUP_TPM_NOT_ALLOWED 0x80310066	Group policy does not permit the use of TPM-only at startup. Please choose a different BitLocker startup option.
FVE_E_POLICY_STARTUP_TPM_REQUIRED 0x80310067	Group policy settings require the use of TPM-only at startup. Please choose this BitLocker startup option.
FVE_E_POLICY_INVALID_PIN_LENGTH 0x80310068	The PIN provided does not meet minimum or maximum length requirements.
FVE_E_KEY_PROTECTOR_NOT_SUPPORTED 0x80310069	The key protector is not supported by the version of BitLocker Drive Encryption currently on the drive. Upgrade the drive to add the key protector.
FVE_E_POLICY_PASSPHRASE_NOT_ALLOWED 0x8031006A	Group policy settings do not permit the creation of a password.
FVE_E_POLICY_PASSPHRASE_REQUIRED 0x8031006B	Group policy settings require the creation of a password.
FVE_E_FIPS_PREVENTS_PASSPHRASE 0x8031006C	The group policy setting requiring FIPS compliance prevented the password from being generated or used. Please contact your domain administrator for more information.
FVE_E_OS_VOLUME_PASSPHRASE_NOT_ALLOWED 0x8031006D	A password cannot be added to the operating system drive.
FVE_E_INVALID_BITLOCKER_OID 0x8031006E	The BitLocker object identifier (OID) on the drive appears to be invalid or corrupt. Use manage-BDE to reset the OID on this drive.
FVE_E_VOLUME_TOO_SMALL 0x8031006F	The drive is too small to be protected using BitLocker Drive Encryption.
FVE_E_DV_NOT_SUPPORTED_ON_FS 0x80310070	The selected discovery drive type is incompatible with the file system on the drive. BitLocker To Go discovery drives must be created on FAT formatted drives.

Constant/Value	Description
FVE_E_DV_NOT_ALLOWED_BY_GP 0x80310071	The selected discovery drive type is not allowed by the computer's Group Policy settings. Verify that Group Policy settings allow the creation of discovery drives for use with BitLocker To Go.
FVE_E_POLICY_USER_CERTIFICATE_NOT_ALLOWED 0x80310072	Group Policy settings do not permit user certificates such as smart cards to be used with BitLocker Drive Encryption.
FVE_E_POLICY_USER_CERTIFICATE_REQUIRED 0x80310073	Group Policy settings require that you have a valid user certificate, such as a smart card, to be used with BitLocker Drive Encryption.
FVE_E_POLICY_USER_CERT_MUST_BE_HW 0x80310074	Group Policy settings requires that you use a smart card-based key protector with BitLocker Drive Encryption.
FVE_E_POLICY_USER_CONFIGURE_FDV_AUTO_UNLOCK_NOT_ALLOWED 0x80310075	Group Policy settings do not permit BitLocker-protected fixed data drives to be automatically unlocked.
FVE_E_POLICY_USER_CONFIGURE_RDV_AUTO_UNLOCK_NOT_ALLOWED 0x80310076	Group Policy settings do not permit BitLocker-protected removable data drives to be automatically unlocked.
FVE_E_POLICY_USER_CONFIGURE_RDV_NOT_ALLOWED 0x80310077	Group Policy settings do not permit you to configure BitLocker Drive Encryption on removable data drives.
FVE_E_POLICY_USER_ENABLE_RDV_NOT_ALLOWED 0x80310078	Group Policy settings do not permit you to turn on BitLocker Drive Encryption on removable data drives. Please contact your system administrator if you need to turn on BitLocker.
FVE_E_POLICY_USER_DISABLE_RDV_NOT_ALLOWED 0x80310079	Group Policy settings do not permit turning off BitLocker Drive Encryption on removable data drives. Please contact your system administrator if you need to turn off BitLocker.
FVE_E_POLICY_INVALID_PASSPHRASE_LENGTH 0x80310080	Your password does not meet minimum password length requirements. By default, passwords must be at least 8 characters in length. Check with your system administrator for the password length requirement in your organization.
FVE_E_POLICY_PASSPHRASE_TOO_SIMPLE 0x80310081	Your password does not meet the complexity requirements set by your system administrator. Try adding upper and lowercase characters, numbers, and symbols.
FVE_E_RECOVERY_PARTITION 0x80310082	This drive cannot be encrypted because it is reserved for Windows System Recovery Options.
FVE_E_POLICY_CONFLICT_FDV_RK_OFF_AUK_ON 0x80310083	BitLocker Drive Encryption cannot be applied to this drive because of conflicting Group Policy settings. BitLocker cannot be configured to automatically unlock fixed data drives when user recovery options are disabled. If you want BitLocker-protected fixed data drives to be automatically unlocked after key validation has occurred, please ask your system administrator to resolve the settings conflict before enabling BitLocker.
FVE_E_POLICY_CONFLICT_RDV_RK_OFF_AUK_ON	BitLocker Drive Encryption cannot be applied to this drive because of conflicting Group Policy settings. BitLocker cannot be configured



Constant/Value	Description
0x80310084	to automatically unlock removable data drives when user recovery option are disabled. If you want BitLocker-protected removable data drives to be automatically unlocked after key validation has occurred, please ask your system administrator to resolve the settings conflict before enabling BitLocker.
FVE_E_NON_BITLOCKER_OID 0x80310085	The Enhanced Key Usage (EKU) attribute of the specified certificate does not permit it to be used for BitLocker Drive Encryption. BitLocker does not require that a certificate have an EKU attribute, but if one is configured it must be set to an object identifier (OID) that matches the OID configured for BitLocker.
FVE_E_POLICY_PROHIBITS_SELF_SIGNED 0x80310086	BitLocker Drive Encryption cannot be applied to this drive as currently configured because of Group Policy settings. The certificate you provided for drive encryption is self-signed. Current Group Policy settings do not permit the use of self-signed certificates. Obtain a new certificate from your certification authority before attempting to enable BitLocker.
FVE_E_POLICY_CONFLICT_RO_AND_STARTUP_KEY_REQUIRED 0x80310087	BitLocker Encryption cannot be applied to this drive because of conflicting Group Policy settings. When write access to drives not protected by BitLocker is denied, the use of a USB startup key cannot be required. Please have your system administrator resolve these policy conflicts before attempting to enable BitLocker.
FVE_E_CONV_RECOVERY_FAILED 0x80310088	BitLocker Drive Encryption cannot be applied to this drive because there are conflicting Group Policy settings for recovery options on operating system drives. Storing recovery information to Active Directory Domain Services cannot be required when the generation of recovery passwords is not permitted. Please have your system administrator resolve these policy conflicts before attempting to enable BitLocker.
FVE_E_VIRTUALIZED_SPACE_TOO_BIG 0x80310089	The requested virtualization size is too big.
FVE_E_POLICY_CONFLICT_OSV_RP_OFF_ADB_ON 0x80310090	BitLocker Drive Encryption cannot be applied to this drive because there are conflicting Group Policy settings for recovery options on operating system drives. Storing recovery information to Active Directory Domain Services cannot be required when the generation of recovery passwords is not permitted. Please have your system administrator resolve these policy conflicts before attempting to enable BitLocker.
FVE_E_POLICY_CONFLICT_FDV_RP_OFF_ADB_ON 0x80310091	BitLocker Drive Encryption cannot be applied to this drive because there are conflicting Group Policy settings for recovery options on fixed data drives. Storing recovery information to Active Directory Domain Services cannot be required when the generation of recovery passwords is not permitted. Please have your system administrator resolve these policy conflicts before attempting to enable BitLocker.
FVE_E_POLICY_CONFLICT_RDV_RP_OFF_ADB_ON 0x80310092	BitLocker Drive Encryption cannot be applied to this drive because there are conflicting Group Policy settings for recovery options on removable data drives. Storing recovery information to Active Directory Domain Services cannot be required when the generation of recovery passwords is not permitted. Please have your system administrator resolve these policy conflicts before attempting to enable BitLocker.



Constant/Value	Description
FVE_E_NON_BITLOCKER_KU 0x80310093	The Key Usage (KU) attribute of the specified certificate does not permit it to be used for BitLocker Drive Encryption. BitLocker does not require that a certificate have a KU attribute, but if one is configured it must be set to either Key Encipherment or Key Agreement.
FVE_E_PRIVATEKEY_AUTH_FAILED 0x80310094	The private key associated with the specified certificate cannot be authorized. The private key authorization was either not provided or the provided authorization was invalid.
FVE_E_REMOVAL_OF_DRA_FAILED 0x80310095	Removal of the data recovery agent certificate must be done using the Certificates snap-in.
FVE_E_OPERATION_NOT_SUPPORTED_ON_VISTA_VOLUME 0x80310096	This drive was encrypted using the version of BitLocker Drive Encryption included with Windows Vista and Windows Server 2008 which does not support organizational identifiers. To specify organizational identifiers for this drive upgrade the drive encryption to the latest version using the "manage-bde -upgrade" command.
FVE_E_CANT_LOCK_AUTOUNLOCK_ENABLED_VOLUME 0x80310097	The drive cannot be locked because it is automatically unlocked on this computer. Remove the automatic unlock protector to lock this drive.
FVE_E_FIPS_HASH_KDF_NOT_ALLOWED 0x80310098	The default BitLocker Key Derivation Function SP800-56A for ECC smart cards is not supported by your smart card. The Group Policy setting requiring FIPS-compliance prevents BitLocker from using any other key derivation function for encryption. You have to use a FIPS compliant smart card in FIPS restricted environments.
FVE_E_ENH_PIN_INVALID 0x80310099	The BitLocker encryption key could not be obtained from the TPM and enhanced PIN. Try using a PIN containing only numerals.
FVE_E_INVALID_PIN_CHARS 0x8031009A	The requested TPM PIN contains invalid characters.
FVE_E_INVALID_DATUM_TYPE 0x8031009B	The management information stored on the drive contained an unknown type. If you are using an old version of Windows, try accessing the drive from the latest version.
FVE_E_EFI_ONLY 0x8031009C	The feature is only supported on EFI systems.
FVE_E_MULTIPLE_NKP_CERTS 0x8031009D	More than one Network Key Protector certificate has been found on the system.
FVE_E_REMOVAL_OF_NKP_FAILED 0x8031009E	Removal of the Network Key Protector certificate must be done using the Certificates snap-in.
FVE_E_INVALID_NKP_CERT 0x8031009F	An invalid certificate has been found in the Network Key Protector certificate store.
FVE_E_NO_EXISTING_PIN 0x803100A0	This drive is not protected with a PIN.



Constant/Value	Description
FVE_E_PROTECTOR_CHANGE_PIN_MISMATCH 0x803100A1	Please enter the correct current PIN.
FVE_E_PROTECTOR_CHANGE_BY_STD_USER_DISALLOWED 0x803100A2	You must be logged on with an administrator account to change the PIN or password. Click the link to reset the PIN or password as an administrator.
FVE_E_PROTECTOR_CHANGE_MAX_PIN_CHANGE_ATTEMPTS_REACHED 0x803100A3	BitLocker has disabled PIN and password changes after too many failed requests. Click the link to reset the PIN or password as an administrator.
FVE_E_POLICY_PASSPHRASE_REQUIRES_ASCII 0x803100A4	Your system administrator requires that passwords contain only printable ASCII characters. This includes unaccented letters (A-Z, a-z), numbers (0-9), space, arithmetic signs, common punctuation, separators, and the following symbols: # \$ & @ ^ _ ~ .
FVE_E_FULL_ENCRYPTION_NOT_ALLOWED_ON_TP_STORAGE 0x803100A5	BitLocker Drive Encryption only supports used space only encryption on thin provisioned storage.
FVE_E_WIPE_NOT_ALLOWED_ON_TP_STORAGE 0x803100A6	BitLocker Drive Encryption does not support wiping free space on thin provisioned storage.
FVE_E_KEY_LENGTH_NOT_SUPPORTED_BY_EDRIVE 0x803100A7	The required authentication key length is not supported by the drive.
FVE_E_NO_EXISTING_PASSPHRASE 0x803100A8	This drive is not protected with a password.
FVE_E_PROTECTOR_CHANGE_PASSPHRASE_MISMATCH 0x803100A9	Please enter the correct current password.
FVE_E_PASSPHRASE_TOO_LONG 0x803100AA	The password cannot exceed 256 characters.
FVE_E_NO_PASSPHRASE_WITH_TPM 0x803100AB	A password key protector cannot be added because a TPM protector exists on the drive.
FVE_E_NO_TPM_WITH_PASSPHRASE 0x803100AC	A TPM key protector cannot be added because a password protector exists on the drive.
FVE_E_NOT_ALLOWED_ON_CSV_STACK 0x803100AD	This command can only be performed from the coordinator node for the specified CSV volume.
FVE_E_NOT_ALLOWED_ON_CLUSTER 0x803100AE	This command cannot be performed on a volume when it is part of a cluster.
FVE_E_EDRIVE_NO_FAILOVER_TO_SW	BitLocker did not revert to using BitLocker software encryption due to group policy configuration.



Constant/Value	Description
0x803100AF	
FVE_E_EDRIVE_BAND_IN_USE	The drive cannot be managed by BitLocker because the drive's hardware encryption feature is already in use.
0x803100B0	
FVE_E_EDRIVE_DISALLOWED_BY_GP	Group Policy settings do not allow the use of hardware-based encryption.
0x803100B1	
FVE_E_EDRIVE_INCOMPATIBLE_VOLUME	The drive specified does not support hardware-based encryption.
0x803100B2	
FVE_E_NOT_ALLOWED_TO_UPGRADE_WHILE_CONVERTING	BitLocker cannot be upgraded during disk encryption or decryption.
0x803100B3	
FVE_E_EDRIVE_DV_NOT_SUPPORTED	Discovery Volumes are not supported for volumes using hardware encryption.
0x803100B4	
FVE_E_NO_PREBOOT_KEYBOARD_DETECTED	No preboot keyboard detected. The user may not be able to provide required input to unlock the volume.
0x803100B5	
FVE_E_NO_PREBOOT_KEYBOARD_OR_WINRE_DETECTED	No preboot keyboard or Windows Recovery Environment detected. The user may not be able to provide required input to unlock the volume.
0x803100B6	
FVE_E_POLICY_REQUIRES_STARTUP_PIN_ON_TOUCH_DEVICE	Group Policy settings require the creation of a startup PIN, but a preboot keyboard is not available on this device. The user may not be able to provide required input to unlock the volume.
0x803100B7	
FVE_E_POLICY_REQUIRES_RECOVERY_PASSWORD_ON_TOUCH_DEVICE	Group Policy settings require the creation of a recovery password, but neither a preboot keyboard nor Windows Recovery Environment is available on this device. The user may not be able to provide required input to unlock the volume.
0x803100B8	
FVE_E_WIPE_CANCEL_NOT_APPLICABLE	Wipe of free space is not currently taking place.
0x803100B9	
FVE_E_SECUREBOOT_DISABLED	BitLocker cannot use Secure Boot for platform integrity because Secure Boot has been disabled.
0x803100BA	
FVE_E_SECUREBOOT_CONFIGURATION_INVALID	BitLocker cannot use Secure Boot for platform integrity because the Secure Boot configuration does not meet the requirements for BitLocker.
0x803100BB	
FVE_E_EDRIVE_DRY_RUN_FAILED	Your computer does not support BitLocker hardware-based encryption. Check with your computer manufacturer for firmware updates.
0x803100BC	
FVE_E_SHADOW_COPY_PRESENT	BitLocker cannot be enabled on the volume because it contains a Volume Shadow Copy. Remove all Volume Shadow Copies before encrypting the volume.
0x803100BD	



Constant/Value	Description
FVE_E_POLICY_INVALID_ENHANCED_BCD_SETTINGS 0x803100BE	BitLocker Drive Encryption cannot be applied to this drive because the Group Policy setting for Enhanced Boot Configuration Data contains invalid data. Please have your system administrator resolve this invalid configuration before attempting to enable BitLocker.
FVE_E_EDRIVE_INCOMPATIBLE_FIRMWARE 0x803100BF	This PC's firmware is not capable of supporting hardware encryption.
FVE_E_PROTECTOR_CHANGE_MAX_PASSPHRASE_CHANGE_ATTEMPTS_REACHED 0x803100C0	BitLocker has disabled password changes after too many failed requests. Click the link to reset the password as an administrator.
FVE_E_PASSPHRASE_PROTECTOR_CHANGE_BY_STD_USER_DISALLOWED 0x803100C1	You must be logged on with an administrator account to change the password. Click the link to reset the password as an administrator.
FVE_E_LIVEID_ACCOUNT_SUSPENDED 0x803100C2	BitLocker cannot save the recovery password because the specified Microsoft account is Suspended.
FVE_E_LIVEID_ACCOUNT_BLOCKED 0x803100C3	BitLocker cannot save the recovery password because the specified Microsoft account is Blocked.
FVE_E_NOT_PROVISIONED_ON_ALL_VOLUMES 0x803100C4	This PC is not provisioned to support device encryption. Please enable BitLocker on all volumes to comply with device encryption policy.
FVE_E_DE_FIXED_DATA_NOT_SUPPORTED 0x803100C5	This PC cannot support device encryption because unencrypted fixed data volumes are present.
FVE_E_DE_HARDWARE_NOT_COMPLIANT 0x803100C6	This PC does not meet the hardware requirements to support device encryption.
FVE_E_DE_WINRE_NOT_CONFIGURED 0x803100C7	This PC cannot support device encryption because WinRE is not properly configured.
FVE_E_DE_PROTECTION_SUSPENDED 0x803100C8	Protection is enabled on the volume but has been suspended. This is likely to have happened due to an update being applied to your system. Please try again after a reboot.
FVE_E_DE_OS_VOLUME_NOT_PROTECTED 0x803100C9	This PC is not provisioned to support device encryption.
FVE_E_DE_DEVICE_LOCKEDOUT 0x803100CA	Device Lock has been triggered due to too many incorrect password attempts.
FVE_E_DE_PROTECTION_NOT_YET_ENABLED 0x803100CB	Protection has not been enabled on the volume. Enabling protection requires a connected account. If you already have a connected account and are seeing this error, please refer to the event log for more information.



Constant/Value	Description
FVE_E_INVALID_PIN_CHARS_DETAILED 0x803100CC	Your PIN can only contain numbers from 0 to 9.
FVE_E_DEVICE_LOCKOUT_COUNTER_UNAVAILABLE 0x803100CD	BitLocker cannot use hardware replay protection because no counter is available on your PC.
FVE_E_DEVICELOCKOUT_COUNTER_MISMATCH 0x803100CE	Device Lockout state validation failed due to counter mismatch.
FVE_E_BUFFER_TOO_LARGE 0x803100CF	The input buffer is too large.



Glossary

Activate - Activation occurs when the computer has been registered with the Security Management Server/Security Management Server Virtual and has received at least an initial set of policies.

Active Directory (AD) - A directory service created by Microsoft for Windows domain networks.

Advanced Authentication - The Advanced Authentication product supports login with self-encrypting drives, SSO, and manages user credentials and passwords. In addition, Advanced Authentication can be used to access not only PCs, but any website, SaaS, or application. Once users enroll their credentials, Advanced Authentication allows use of those credentials to logon to the device and perform password replacement.

Application Data Encryption - Application Data Encryption encrypts any file written by a protected application, using a category 2 override. This means that any directory that has a category 2 protection or better, or any location that has specific extensions protected with category 2 or better, will cause ADE to not encrypt those files.

BitLocker Manager - Windows BitLocker is designed to help protect Windows computers by encrypting both data and operating system files. To improve the security of BitLocker deployments and to simplify and reduce the cost of ownership, Dell provides a single, central management console that addresses many security concerns and offers an integrated approach to managing encryption across other non-BitLocker platforms, whether physical, virtual, or cloud-based. BitLocker Manager supports BitLocker encryption for operating systems, fixed drives, and BitLocker To Go. BitLocker Manager enables you to seamlessly integrate BitLocker into your existing encryption needs and to manage BitLocker with the minimum effort while streamlining security and compliance. BitLocker Manager provides integrated management for key recovery, policy management and enforcement, automated TPM management, FIPS compliance, and compliance reporting.

Cached Credentials - Cached credentials are credentials that are added to the PBA database when a user successfully authenticates with Active Directory. This information about the user is retained so that a user can log in when they do not have a connection to Active Directory (for example, when taking their laptop home).

Common Encryption - The Common key makes encrypted files accessible to all managed users on the device where they were created.

Deactivate - Deactivation occurs when SED management is turned OFF in the Remote Management Console. Once the computer is deactivated, the PBA database is deleted and there is no longer any record of cached users.

Encryption External Media - This service within the Dell Encryption client applies policies to removable media and external storage devices.

Encryption External Media Access Code - This service within the Security Management Server/Security Management Server Virtual allows for recovery of Encryption External Media protected devices where the user forgets their password and can no longer login. Completing this process allows the user to reset the password set on the removable media or external storage device.

Encryption Client - The Encryption client is the on-device component that enforces security policies, whether an endpoint is connected to the network, disconnected from the network, lost, or stolen. Creating a trusted computing environment for endpoints, the Encryption client operates as a layer on top of the device operating system, and provides consistently-enforced authentication, encryption, and authorization to maximize the protection of sensitive information.

Endpoint - a computer that is managed by Security Management Server/Security Management Server Virtual.

Encryption Keys - In most cases, the Encryption client uses the User key plus two additional encryption keys. However, there are exceptions: All SDE policies and the Secure Windows Credentials policy use the SDE key. The Encrypt Windows Paging File policy and Secure Windows Hibernation File policy use their own key, the General Purpose Key (GPK). The Common key makes files accessible to all managed users on the device where they were created. The User key makes files accessible only to the user who created them, only on

the device where they were created. The User Roaming key makes files accessible only to the user who created them, on any Shielded Windows (or Mac) device.

Encryption Sweep - An encryption sweep is the process of scanning the folders to be encrypted on a managed endpoint to ensure the contained files are in the proper encryption state. Ordinary file creation and rename operations do not trigger an encryption sweep. It is important to understand when an encryption sweep may happen and what may affect the resulting sweep times, as follows: - An encryption sweep will occur upon initial receipt of a policy that has encryption enabled. This can occur immediately after activation if your policy has encryption enabled. - If the Scan Workstation on Logon policy is enabled, folders specified for encryption will be swept on each user logon. - A sweep can be re-triggered under certain subsequent policy changes. Any policy change related to the definition of the encryption folders, encryption algorithms, encryption key usage (common versus user), will trigger a sweep. In addition, toggling between encryption enabled and disabled will trigger an encryption sweep.

Malware Protection (Full Scan) -Malware Protection Full Scan scans the following locations for threats:

- The computer memory for installed rootkits.
- Hidden processes, and other behavior that suggests malware is attempting to hide itself.
- The memory of all running processes, all drives and their subfolders on the computer.

Malware Protection (Quick Scan) -Malware Protection Quick Scan scans the following locations for threats:

- The memory of all running processes.
- The files that the Windows Registry references.
- The contents of the Windows folder.
- The contents of the Temp folder.

On-Access Malware Protection - When a user accesses files, folders, and programs, the on-access scanner intercepts the operation and scans the item.

Preboot Authentication (PBA) - Preboot Authentication serves as an extension of the BIOS or boot firmware and guarantees a secure, tamper-proof environment external to the operating system as a trusted authentication layer. The PBA prevents anything being read from the hard disk, such as the operating system, until the user has confirmed they have the correct credentials.

SED Management - SED Management provides a platform for securely managing self-encrypting drives. Although SEDs provide their own encryption, they lack a platform to manage their encryption and available policies. SED Management is a central, scalable management component, which allows you to more effectively protect and manage your data. SED Management ensures that you will be able to administer your enterprise more quickly and easily.

System Data Encryption (SDE) - SDE is designed to encrypt the operating system and program files. To accomplish this purpose, SDE must be able to open its key while the operating system is booting. Its intent is to prevent alteration or offline attacks on the operating system by an attacker. SDE is not intended for user data. Common and User key encryption are intended for sensitive user data because they require a user password in order to unlock encryption keys. SDE policies do not encrypt the files needed by the operating system to start the boot process. SDE policies do not require preboot authentication or interfere with the Master Boot Record in any way. When the computer boots up, the encrypted files are available before any user logs in (to enable patch management, SMS, backup and recovery tools). Disabling SDE encryption triggers automatic decryption of all SDE encrypted files and directories for the relevant users, regardless of other SDE policies, such as SDE Encryption Rules.

Threat Protection - The Threat Protection product is based on centrally managed policies that protect enterprise computers against security threats. Threat Protection consists of: - Malware Protection - Checks for viruses, spyware, unwanted programs, and other threats by automatically scanning items when accessed or based on schedules defined in policy. - Client Firewall - Monitors communication between the computer and resources on the network and the Internet and intercepts potentially malicious communications. - Web Protection - Blocks unsafe websites and downloads from those websites during online browsing and searching, based on safety ratings and reports for websites.

Trusted Platform Module (TPM) - TPM is a security chip with three major functions: secure storage, measurement, and attestation. The Encryption client uses TPM for its secure storage function. The TPM can also provide encrypted containers for the software vault.



User Encryption – The User key makes files accessible only to the user who created them, only on the device where they were created. When running Dell Server Encryption, User Encryption is converted to Common Encryption. One exception is made for external media devices; when inserted into a server with Encryption installed, files are encrypted with the User Roaming key.

