

CyberLink

LabelPrint

User's Guide

CyberLink

Copyright and Disclaimer

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means electronic, mechanical, photocopying, recording, or otherwise without the prior written permission of CyberLink Corporation.

To the extent allowed by law, LABELPRINT IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING WITHOUT LIMITATION ANY WARRANTY FOR INFORMATION, SERVICES, OR PRODUCTS PROVIDED THROUGH OR IN CONNECTION WITH LABELPRINT AND ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, EXPECTATION OF PRIVACY, OR NON-INFRINGEMENT.

BY USING THIS SOFTWARE, YOU AGREE THAT CYBERLINK WILL NOT BE LIABLE FOR ANY DIRECT, INDIRECT, OR CONSEQUENTIAL LOSS ARISING FROM THE USE OF THIS SOFTWARE OR MATERIALS CONTAINED EITHER IN THIS PACKAGE.

The terms and conditions here under shall be governed and construed in accordance with the laws of Taiwan.

LabelPrint is a registered trademark along with other company and product names mentioned in this publication, used for identification purposes and remain the exclusive property of their respective owners.

International Headquarters

Mailing Address CyberLink Corporation
15F, #100, Minchiuan Road,
Shindian City, Taipei 231, Taiwan

Web Site www.cyberlink.com

Telephone 886-2-8667-1298

Fax 886-2-8667-1300

Copyright © 2006 CyberLink Corporation. All rights reserved.

Contents

Introduction	1
The Cyberlink LabelPrint Program	2
Navigate in Cyberlink LabelPrint	3
Configuration Options	4
Register Your Software	6
Upgrade Your Software	7
System Requirements	8
Creating Labels	9
LightScribe Media Identification	10
LabelFlash Media Identification	11
Select a Label Type	12
Edit Disc Information	13
Display Disc Information	13
Add Items to the Content List	14
Remove Items from the Content List	15
Insert a Row in the Middle of the Content List	15
Re-Order Items in the Content List	16
Modify Content List Information	16
Edit a Label's Layout	17
Layout-Editing Tools	17
Select a Label Layout	18
Add a Background Image	19
Add or Modify Text	19
Add a Foreground Image	20
Re-Order Text and Images	20

Delete a Text Box or Image	20
Print a Label	21
Display Printer Options	21
Print a Label on a Printer	22
Print a Label directly on a disc face	23
Burn a Disc Label Using LightScribe	24
Burn a Disc Label Using LabelFlash	26
Technical Support	27
Web Support	28
Telephone Support	29
Index	31

Chapter 1:

Introduction

Cyberlink LabelPrint is a handy tool for printing labels for use with your disc media. This chapter introduces the Cyberlink LabelPrint program, including how to navigate through the program windows, configure the program to suit your working methods, register your copy of the program, and upgrade to a new version. The final section presents the minimum system requirements for using Cyberlink LabelPrint.


This chapter contains the following sections:

- The Cyberlink LabelPrint Program on p.2
- Register Your Software on p.6
- Upgrade Your Software on p.7
- System Requirements on p.8

The Cyberlink LabelPrint Program

Cyberlink LabelPrint is a handy program for printing disc labels, covers, and inlays. Cyberlink LabelPrint offers a wide variety of layout formats and supports a number of printing options, including printing directly on your disc using LightScribe technology, burning images on either side of your disc using LabelFlash, and direct CD/DVD printing.


When you first open Cyberlink LabelPrint, the program appears as follows:



Note: The LabelFlash option only appears if you have a LabelFlash-compatible burning drive installed on your computer.

Note: The LightScribe option only appears if you have a LightScribe-compatible burning drive installed on your computer. If your drive is installed but the LightScribe option still does not appear, make sure that the LightScribe Host Software that came with your drive is installed.

Navigate in Cyberlink LabelPrint

After you have finished selecting options on a page, click  to advance to the next page. Alternately, you can click a step in the Procedure pane on the left-hand side of the program to skip directly to a specific page.


Configuration Options

Cyberlink LabelPrint offers several configuration options in order to suit your working methods.

Printer Calibration

Calibrating your printer ensures that your printer is properly aligned with your template. You may wish to calibrate your printer before printing to ensure optimal printing quality.


Note: You won't normally need to calibrate your printer unless you have inserted a new ink cartridge or installed a new printer.

To display printer calibration options, click . The Configuration dialog box opens.

- **X Offset and Y Offset:** Correlate the printer's position to the original calibration. Click the up/down arrows to move the calibration mark **+**, or drag the calibration mark to the desired position.

General Settings

Before you begin creating labels, you may want to make sure the program is configured to suit your preferred working methods. You can set general configuration options in the General Settings tab of the Configuration dialog box.


To display general configuration options, click . In the Configuration dialog box, click the **General Settings** tab.

- **Draw outline of the disc label:** Draws a border around your disc label. This border is helpful for cutting out the label when you print onto a plain piece of paper.
- **Hide item number:** Prints your disc's contents list without numbering the items it contains.

LightScribe Settings

If you are burning your disc label using a LightScribe drive, you can specify that drive in the Configuration dialog box.

Note: The LightScribe tab only appears if you have a LightScribe-compatible burning drive installed on your computer.


To display LightScribe configuration options, click . In the Configuration dialog box, click the **LightScribe** tab.

- **Select your LightScribe disc label printing drive:** Allows you to select your LightScribe-compatible burning drive from the drop-down menu. Drive-specific information appears below the selected drive.

LabelFlash Settings

If you are burning a label using a LabelFlash drive, you can specify that drive in the Configuration dialog box.


Note: The LabelFlash tab only appears if you have a LabelFlash-compatible burning drive installed on your computer.

To display LabelFlash configuration options, click . In the Configuration dialog box, click the **LabelFlash** tab.

- **Select your LabelFlash disc label printing drive:** Allows you to select your LabelFlash-compatible burning drive from the drop-down menu. Drive-specific information appears below the selected drive.

Register Your Software

After you install the program, a registration window opens, prompting you to register your product. It is important to register your software in order to receive technical support or other information from CyberLink.



CyberLink
LabelPrint™

Thank you for choosing CyberLink software.
Register today to receive technical support
and useful information that will maximize
your enjoyment of digital media on the PC.

First Name:

Last Name:

Email:

Yes, I would like to receive a newsletter from CyberLink.

Yes, I would like to receive information about CyberLink products.

Register Now

I Have Already Registered

Remind Me Later


CyberLink

To register your software, do this:

1. Enter your personal information in the **First Name**, **Last Name**, and **Email** entry boxes.
 - Check one or both of the options to receive information from CyberLink, or uncheck if you do not wish to receive this information.
2. Click **Register Now**.

- If you have previously registered this product, click **I Have Already Registered**. The registration box will no longer open when you run the program.
- If you would like to register this product at a later time, click **Remind Me Later**. The registration box will open each time you run the program until you register.

Upgrade Your Software

Software upgrades may be periodically available from CyberLink. To upgrade your software, click  in the row of buttons across the top of the window. A web browser window opens to CyberLink's website, where you can upgrade your program as well as receive other information about CyberLink and CyberLink's products.

Note: You must be connected to the Internet to use this feature.

System Requirements

The system requirements listed below are recommended as minimums for using this program.

Minimum System Requirements	
OS	Windows 98SE/ME/2000/XP (Windows 2000/XP required to enable LightScribe technology)
Memory	128 MB RAM
CPU	Pentium III 700 MHz or above or AMD Athlon 700 or above
Hard Disk Space	80 MB
Other	DirectX 9 Printer, LightScribe-compatible CD/DVD burner or LabelFlash-compatible burner

Chapter 2:

Creating Labels

The process of creating and printing labels in Cyberlink LabelPrint is a simple four-step procedure. This chapter describes the label creation procedure in full, with information on all of the available options.

This chapter contains the following sections:

- LightScribe Media Identification on p.10
- LabelFlash Media Identification on p.11
- Select a Label Type on p.12
- Edit Disc Information on p.13
- Edit a Label's Layout on p.17
- Print a Label on p.21

LightScribe Media Identification

The LightScribe system requires the use of LightScribe-enabled discs. LightScribe uses control features in the center/hub of the disc to identify media as LightScribe media. If your system does not seem to recognize the media as LightScribe media, take the following steps.

1. Make sure the disc is a LightScribe-enabled disc. LightScribe media will have the LightScribe logo in the inner hub area. There will also be visible control features inside, and adjacent to, the coated label area.
2. Make sure the disc is properly oriented in the drive. The label side, which contains a special coating, should be face down in the drive.
3. Clean the center area (hub) of the disc. Use a lint-free cloth to wipe the hub area and remove any dirt or smudges that may be covering the control features.
4. If these steps do not fix the problem, try another LightScribe disc.

LabelFlash Media Identification

LabelFlash system requires the following discs:

- Burning on Data Side: CD-R, DVD+R and DVD-R
- Burning on Label Side: LabelFlash DVD+R and LabelFlash DVD-R

If your system does not seem to recognize the media, take the following steps

1. When burning images on the label side, make sure the disc is a LabelFlash-enabled disc. LabelFlash media will have the LabelFlash logo in the inner hub area.
2. Make sure the disc is properly oriented in the drive. The side which will be printed, should be face down in the drive.
3. Clean the center area (hub) of the disc. Use a lint-free cloth to wipe the hub area and remove any dirt or smudges that may be covering the control features.
4. If these steps do not fix the problem, try another LabelFlash disc.


Select a Label Type

The first step in creating a label is to select the type of label you want to print. You can select a label on the first page that appears when Cyberlink LabelPrint opens.

To select the type of label you want to print, do this:

1. Open Cyberlink LabelPrint.
2. Select the type of label you want to create from the following:
 - **LightScribe:** Burn a label directly onto the disc itself using LightScribe technology.
 - **LabelFlash:** Burn a label directly onto the disc's label side and/or data side by using **LabelFlash** technology.
 - **Disc Label:** Print a label to stick directly onto a normal-sized disc.

Note: Cyberlink LabelPrint supports "Epson Direct CD Printer" for Epson's own printers. Please select this label type for printing directly on disc faces with compatible Epson printers.

- **MiniDisc Label:** Print a label to stick directly onto a MiniDisc.
 - **Front Cover:** Print the outside of the disc's jewel case front cover.
 - **Back of Front Cover:** Print the inside of the disc's jewel case front cover.
 - **Disc Inlay:** Print an inlay to insert into the bottom of the disc's jewel case, under the disc holder.
3. Click  to advance to the Edit Disc Information page.


Edit Disc Information

Add or edit disc information, such as a title, which will allow you to recognize the disc. Add or edit content list information to keep track of which files you have added to the disc. You can add or edit this information on the Edit Disc Information page.

Display Disc Information

Available information about both your disc and its contents is printed on your label. Cyberlink LabelPrint automatically generates content list information when you add items, though you can manually change this information if necessary.

To display disc information, do this:


1. Open Cyberlink LabelPrint and display the Edit Disc Information page.
2. Enter or modify your disc information:
 - **Disc Title:** Enter a disc title in this field.
 - **Author:** Enter the name of the disc's author in this field.
 - **Date:** The current date is displayed by default. To change the date, click the down-arrow, then select a new date.
3. Enter or modify your content list information.
4. Click  to advance to the Edit Layout page.

Add Items to the Content List

Use this function to add items to the content list. Since Cyberlink LabelPrint can read MP3 file information, the process of adding MP3 information to the content list is automated. Adding other information must be done manually.

Add MP3s to the Content List

To add MP3s to the content list, do this:

1. Open Cyberlink LabelPrint and display the Edit Disc Information page.
2. Click . The Import dialog box opens.
3. Locate and import the files (in MP3 or M3U format) you want to import. Items are inserted into the first available content list row.

Add Items to the Content List



To add items to the content list, do this:

1. Open Cyberlink LabelPrint and display the Edit Disc Information page.
2. Double-click in an entry box, then enter the content list information manually.

Remove Items from the Content List

Use this function to remove items from the content list if you decide later on not to add them, or if you have added them in error.



To remove items from the content list, do this:

1. Open Cyberlink LabelPrint and display the Edit Disc Information page.
2. Click an item, then do the following:
 - Click  to remove the selected item.
 - Click  to remove all items.

Insert a Row in the Middle of the Content List

When you add new items, they are appended to the bottom of the content list by default. However, you can also insert an item in the middle of the content list.



To insert an item in the middle of the content list, do this:

1. Open Cyberlink LabelPrint and display the Edit Disc Information page.
2. Click the item above which you want to insert the new row.
3. Click  to insert a blank row above the selected item.
4. Click , then import a new file.

Re-Order Items in the Content List

After you have added items to the content list, you may wish to modify the order in which they are listed.

To re-order items in the content list, do this:

1. Open Cyberlink LabelPrint and display the Edit Disc Information page.
2. Click an item, then do the following:
 - Click  to move the item one position up.
 - Click  to move the item one position down.

Modify Content List Information

Cyberlink LabelPrint automatically generates content list information when you add items to the content list. Some of this information may be outdated or missing. In such a case, you can modify the content list information to provide a complete and accurate content list.

To modify content list information, do this:








1. Open Cyberlink LabelPrint and display the Edit Disc Information page.
2. Double-click inside the information field that you want to modify, then enter the modified information.

Edit a Label's Layout

Cyberlink LabelPrint supports a wide variety of label templates, offering you a number of default options. You can further customize default layouts, allowing you to tailor the label to suit your specific requirements. You can design your label using a number of options, including layout templates, text options, and background images. By selecting a layout, modifying the fonts, and using a custom background image, you can create a more personalized disc label.



Layout-Editing Tools


You can use the following tools to create a label:

Tool	Description
	Inserts a horizontal text object.
	Inserts a curved text object that follows the arc of the disc.
	Inserts a background image.
	Moves the selected object towards the top layer.
	Moves the selected object towards the bottom layer.
	Allows you to edit the selected text object.
	Deletes the selected object.

Select a Label Layout

To select label layout options, do this:

1. Open Cyberlink LabelPrint and display the Edit Layout page.
2. Select a paper template from the drop-down box. (A paper template allows you to print on any sheet of paper your printer supports.)
3. Select a layout style by doing one of the following:
 - Click  or  to scroll through the list of templates.
 - Click **Select...** under Layout Style to view the templates in a dialog box.






The following layout options are available:

- **Title** (first option): A simple title that allows you to identify a disc. Use for routine or utility discs.
- **Content** (second option): More complete information about the contents of a disc. Use when you have several discs with the same title but different contents.
- **Full** (all other options): A creative label of words and graphics that uses most of the space on the label. Use for important or keepsake discs.




Add a Background Image

To add a background image to your label, do this:

1. Open Cyberlink LabelPrint and display the Edit Layout page.
2. Select a background image by doing one of the following:
 - Click  or  to scroll through the list of background images.
 - Click **Select...** under Background Image to view the background images in a dialog box. To open a custom image, click **Browse...**, then locate and open the image you want to use.
 - Click , then select a stretch mode. **Stretch** resizes the image to the size of the label, but without keeping the image's aspect ratio. (This option may result in image distortion.) **Crop** cuts off the portions of the image that fall outside the boundaries of the label. **Fit** resizes the image to the size of the label, keeping the image's aspect ratio. **Tile** repeats the image to fit the label.


Add or Modify Text

To add or modify text on your label, do this:

1. Open Cyberlink LabelPrint and display the Edit Layout page.
2. Click a text insertion button to insert a text box.
 - Click  to insert text in a horizontal text box.
 - Click  to insert text in a curved text box.
3. Highlight a text box, click , then modify the text.
4. Double-click a text box to open the standard Font dialog box, in which you can modify the font size and style.
5. Drag the text box to reposition it on your label.



Add a Foreground Image

To add a foreground image to your label, do this:


1. Open Cyberlink LabelPrint and display the Edit Layout page.
2. Click . The Open dialog opens.
3. Locate and open the desired image.
4. Drag the image to reposition it on your label.

Re-Order Text and Images

To re-order text and images on your label, select the desired object, then do one of the following:

- Click  to move the selected object towards the top layer.
- Click  to move the selected object towards the bottom layer.

Delete a Text Box or Image

To delete a text box or image, select the desired object, then click  to delete.

Print a Label

Cyberlink LabelPrint offers a number of printing options, including printing directly on your disc using LightScribe technology and burning images on either side of your disc using LabelFlash.

You can print on one of the following media:

- **Plain paper:** Allows you to print on any sheet of paper your printer supports.
- **Label paper:** Provides labels for easy printing.
- **Ink-Jet Printable discs:** Requires special Epson printer and compatible disc.
- **Directly onto your disc:** Special LightScribe burning drive or LabelFlash burning drive let you print your label directly on the disc.

Display Printer Options

Display printer options in order to set up your printing device to suit your project.

To display printer options, do this:

1. Open Cyberlink LabelPrint and display the Print page.
2. Select your printer device.
 - Click **Properties** to open the Print Setup dialog box.

Print a Label on a Printer

You can print any type of label on a printer, using either plain paper or on label paper. The Print page allows you to select both your template and your printer.

Note: To select a new label type to print, you must return to Step 1 in the label creation process. For more information, see Select a Label Type on p.12.

To print a label on a printer, do this:

1. Open Cyberlink LabelPrint and display the Print page.
2. Select the **Printer** option.
 - If multiple printers are available, select the desired printer from the drop-down menu.
3. Enter the number of copies you want to print.
4. Select your paper template from the drop-down menu, if necessary.
 - To print on plain paper, select **Plain Paper (A4)**.
 - If the sample template contains two available labels, reflecting the two labels on the paper template, click the label you would like to print on.

Note: The arrow next to the template sample indicates the proper direction to insert your paper into your printer.

5. Click  to begin printing your label.

Print a Label directly on a disc face

With Epson printers, colorful labels can be printed directly on compatible disc faces.

Note: Please make sure that your discs are Ink-Jet Printable CD-R and DVD-R Recordable media.

Note: To select a new label type, you must return to Step 1 in the label creation process. For more information, see Select a Label Type on p.12.

To print disc faces directly, do this:

1. Open Cyberlink LabelPrint and display the Print page.
2. Select the **Printer** option.
 - If multiple printers are available, select the compatible Epson printer from the drop-down menu.
3. Enter the number of copies you want to print.
4. Select **Epson Direct CD-DVD Printing** as your template from the drop-down menu.

Note: The arrow next to the template sample indicates the proper direction to insert your disc into your printer.

5. Click  to begin printing your label.

Burn a Disc Label Using LightScribe


LightScribe Direct Disc Labeling is a disc labeling technology that enables you to burn disc labels simply by flipping the disc over and putting them back in the same disc drive that burned your data. LightScribe technology combines the CD or DVD drive of your computer with specially coated discs to produce precise, silkscreen-quality labels.

Note: Using LightScribe, you can only print disc labels. You cannot print other types of labels using LightScribe technology.

To burn a disc label using LightScribe, do this:

1. Open Cyberlink LabelPrint and display the Print page.

Note: You must have selected LightScribe as your label type. See Select a Label Type on p.12.

2. Click . The LightScribe wizard opens.

3. Select a quality level:

- **Best (Recommended)** - Provides the sharpest contrast with the longest burn time. Use Best level for important business transactions, gifts, and personal keepsakes.
- **Normal** - Provides moderate burn time with good contrast. Use Normal level for professional labels.
- **Draft** - Provides the fastest burn time with lowest contrast. Use Draft level for utility labels.

4. Click **Preview** to see how your LightScribe disc might appear after labelling.

Note: Text or images that extend beyond the editable region are cropped when printing. If your label is cropped, you may select a different layout style on the Edit Layout page. See Edit a Label's Layout on p.17.

5. Click **Next** to begin burning your label. The label burn time varies with the amount of information contained on the label, the placement of the information on the label, the contrast level selected, the LightScribe disc used, and the drive.

Note: If the special 'barcode' in the middle of a LightScribe disc on the label (not data) side becomes dusty or dirty, the disc may not be detected as a LightScribe disc. If this happens, gently clean the barcode with a tissue, then try again.

Burn a Disc Label Using LabelFlash


LabelFlash is a disc labeling technology that enables you to burn labels on either side of the disc. LabelFlash technology combines the CD or DVD drive of your computer with specially coated discs to produce precise, glossy-finish labels.

To burn a disc label using LabelFlash, do this:

1. Open Cyberlink LabelPrint and display the Print page.

Note: You must have selected LabelFlash as your label type. See Select a Label Type on p.12.

Note: The side, which will be burned, should be face down in the drive.

2. Click . The LabelFlash wizard opens.
3. Enter desired **Inner** and **Outer** printing range. Select suitable **Rotation** and **Contrast**.
4. Click **Preview** to see how your disc might appear after labelling.

Note: Text or images that extend beyond the editable region are cropped when printing. If your label is cropped, you may select a different layout style on the Edit Layout page. See Edit a Label's Layout on p.17.

5. Click **Next** to begin burning your label. The label burn time varies with the amount of information contained on the label, the placement of the information on the label, the contrast level selected, rotation speed, the disc used, and the drive.

Technical Support

This chapter contains technical support information. Before asking CyberLink for technical support, please refer to this user's guide or online help for information. It contains all the information you generally need to use the program. You may also find answers quickly by contacting your local distributor/dealer.

If your problem is not resolved using the above methods, please feel free to contact CyberLink for technical support.

Web Support

Solutions to your problems are available 24 hours a day and at no cost on our Web sites:

support.cyberlink.com

www.cyberlink.com

In addition to frequently asked questions, we also provide troubleshooting techniques, the latest in product news, and other relevant information.

Telephone Support

You are welcome to call the CyberLink's Technical Support Hotline at the phone number listed below during hours of availability:

CyberLink Technical Support Information

Support Phone Number	(886) 2-8667-1298
----------------------	--------------------------

Support Hours	9:00 a.m. -5:00 p.m. Taiwan time (GMT +8:00) Monday to Friday, excluding holidays
---------------	---

Note: Technical support is only offered to registered users. Please be sure to have your **CD-key** (located on your CD case) on hand when calling.

When calling for support, please have your computer ready and provide us with the following information:

- **your registered CD-key**
- the product version
- the version of Windows installed on your system
- the hardware devices on your system and their specifications
- the wording of any warning messages that were displayed (You may want to write this down or make a screen capture.)
- a detailed description of the problem and under what circumstances it occurred

Index

A

- add a background image 19
- add a foreground image 20
- add items to content list 14
- add MP3 items to content list 14
- add text 19

B

- background image, add 19
- burn a disc label using LabelFlash 26
- burn a disc label using LightScribe 24
- burning drive, select 5

C

- calibrate your printer 4
- CD key, location of 29
- configuration options 4
- Content layout option 18

- content list
 - modify information 16

D

- delete text or images 20
- disc information, edit 13
- disc label
 - burn using LabelFlash 26
 - burn using LightScribe 24
 - draw outline 4
- draw outline of the disc label 4

E

- edit
 - content information 16
 - disc information 13
 - layout 17

F

- foreground image, add 20
- Full layout option 18

G

general settings 4

H

hide item number 4

I

images

delete 20

re-order 20

insert an item within content list 15

items

add MP3 14

add to content list 14

insert within content list 15

remove from content list 15

re-order in content list 16

L

label

draw outline 4

edit layout 17

print on a printer 22, 23

types 12

LabelFlash

use to print disc labels 26

LabelFlash settings 5

layout options, select 18

layout, edit 17

layout-editing tools 17

LightScribe 21

drive, select 5

use to print disc labels 24

LightScribe settings 5

M

media available for printing on 21

minimum system requirements 8

modify text 19

MP3, add information to content list 14

N

navigate in LabelPrint 3

O

outline of disc label, draw 4

P

- paper templates 21
- phone number, tech support 29
- plain paper 21
- preview your disc 26
- preview your LightScribe disc 24
- print
 - available media 21
 - disc label using LabelFlash 26
 - disc label using LightScribe 24
 - label on a printer 22, 23
- printer
 - calibration 4
 - print a label on 22, 23
 - select 21

Q

- quality level for LightScribe 24

R

- registration 6
- remove items from content list 15
- re-order items in content list 16
- re-order text and images 20

S

- select
 - label type 12
 - LightScribe burning drive 5
- select label layout options 18
- settings
 - general 4
 - LabelFlash 5
 - LightScribe 5
 - printer calibration 4
- system requirements 8

T

- technical support 27
- text
 - add or modify 19
 - delete 20
 - re-order 20
- Title layout option 18
- tools for editing label layout 17
- types of labels 12

U

- upgrade your software 7

W

Web sites for technical support 28

X

X Offset 4

Y

Y Offset 4