## Installing Emulation on Windows 64-bit

- 1. Make sure the CueCable DMX interface is unplugged
- 2. Install Emulation version 1.01 build 14 or higher




3. Open a Command Prompt, run as administrator




4. Go to the installation folder of Emulation.

If your folder is C:\Program Files (x86)\Elation\Emulation10114\drivers\win64

Then type cd \Program Files (x86)\Elation\Emulation10114\drivers\win64



5. Run the install batch file by typing install.bat



You can trust 'Jungo'; this is the name of the supplier of the driver.




Windows can't verify the publisher of the CueCable; Click 'Install this driver software anyway'




6. Check your Device Manager. You can reach the Device Manager through:






It should display class 'Jungo' containing item 'Windriver6'.



- 7. Plug in the CueCable DMX Interface
- 8. Check your Device Manager. In the class 'Jungo' it should now also show item 'CueCable'.



9. Run Emulation and check in the 'Options' -> 'Hardware' that the CueCable is detected.



Finished!