



ClarIDy UHF USB Reader Demo Program

ClarIDy UHF USB Reader Demo Program User's Manual for Win32

Product Name: UHF USB Reader Module

Model No.: UEE006

Applicant: ClarIDy Solutions, Inc.

Version: A.2-02

2009-01-05

ClarIDy Solutions, Inc.



ClarIDy UHF USB Reader Demo Program

Copyright Notice

© Copyright 2008 ClarIDy Solutions, Inc. All rights reserved.

No part of this document may be reproduced without the prior written permission of ClarIDy Solutions, Inc.

Disclaimer

The information of this document is subject to change without notice and does not represent a commitment on any part of ClarIDy Solutions, Inc.

Trademarks

Intel is a registered trademark of Intel Corporation.

AMD is a registered trademark of Advanced Micro Devices, Inc.

Microsoft, Windows Vista, Windows XP, Visual Studio, .NET Framework, and CSharp (C#) are registered trademarks of Microsoft Corporation.

All other product names are trademarks or registered trademarks of their respective owners.

ClarIDy UHF USB Reader Demo Program

Change Log

Revision	Date	Author	Description
A.1	2008.09.02.	Hoe Huang	Create the ClarIDy UHF Demo Program User's Manual.
A.2	2008.11.07	Hoe Huang	Modified Demo Program User's Manual, and added examples.
A.2-01	2008.12.09	Jun-Rong Chang	Added the application of Lock Tag and Kill Tag
A.2-02	2009.01.05	Jun-Rong Chang	Added the application of enable password function and write password.

ClarIDy UHF USB Reader Demo Program

Table of Contents

1. Introduction..... 5

2. Installation 6

 2.1 Prerequisites to Installation..... 6

 2.2 Setup the USB Driver 6

 2.3 Install .Net Framework 2.0..... 12

 2.3 Install ClarIDy UHF Demo 15

3. Demo Program Operation Guide 19

 3.1 Setting Control 19

 3.2 Algorithm Control 22

 3.3 Inventory Control 27

 3.4 Read/Write Control 29

 3.5 Filter Inventory 31

 3.6 Filter Write Read 33

 3.7 Lock/Kill Tag..... 34

4. Error Code 37

5. Uninstall..... 39

ClarIDy UHF USB Reader Demo Program

1. Introduction

This document describes the demo program (ClarIDy_UHF_Demo_Setup.exe) for ClarIDy UHF RFID Reader. The demo program provides “Setting”, “Algorithm”, “Inventory”, “Read/Write”, “Filter Inventory”, “Filter Read/Write” and “Lock/Kill” functions. Users can use this application to control the ClarIDy UHF RFID Reader to communicate with EPC RFID tags. The operational procedures are described as the following chapters.

ClarIDy UHF USB Reader Demo Program

2. Installation

Before Installing the USB Driver and ClarIDy UHF Demo program, please see prerequisites first.

2.1 Prerequisites to Installation

In order to run ClarIDy UHF Demo program as smoothly as possible, we recommend some conditions as following.

2.1.1 Hardware Platform Requirements

The following hardware Platforms are supported by ClarIDy UHF RFID Reader.

- CPU: Intel® Pentium® 4 or AMD Athlon™ processor, 1.4 GHz or above
- RAM: 512MB or above

2.1.2 Operating System Requirements

The following host operating systems are supported by ClarIDy UHF RFID Reader:

- Microsoft®, Windows Vista®, Windows XP® with Service Pack 2 or Service Pack 3 on an IA-32 platform; USB Host Controller – OHCI, UHCI or EHCI

2.1.3 Other Software Requirements

The following other systems are supported by ClarIDy UHF RFID Reader:

- Microsoft® .Net Framework® Release 2.0
- Microsoft® Visual C++ Libraries 2008

2.2 Setup the USB Driver

First time using the ClarIDy's UHF RFID Reader (USB Interface), you must install the driver. (The Driver programs are located in the "drivers" folder of the disc.)

Please directly connect the ClarIDy UHF RFID Reader to the USB port of the computer. The Windows system will detect the ClarIDy UHF RFID Reader as a new device and popup the device driver setup dialog, as figure 1.

Install ClarIDy UHF RFID driver step by step as the following instructions:

1. Select "Install from a list or specific location (Advanced)", as figure 2.
2. Click "Next" while the wizard searches, as figure 3.
3. System show out figure 4.
4. Select "No, do not connect to the internet now", as figure 5.

ClarIDy UHF USB Reader Demo Program

5. Click "Next" while the installation option dialog is shown, as figure 6.
6. When "Hardware Installation" dialog is shown, please click "Continue Anyway" to continue the installation, as figure 8 and figure 9.
7. Click "Finish" to finalize the installation of the RFID USB device driver, as figure 10.



Figure 1

ClarIDy UHF USB Reader Demo Program




Figure 2




Figure 3

ClarIDy UHF USB Reader Demo Program




Figure 4




Figure 5

ClarIDy UHF USB Reader Demo Program




Figure 6




Figure 7

ClarIDy UHF USB Reader Demo Program




Figure 8




Figure 9

ClarIDy UHF USB Reader Demo Program




Figure 10

2.3 Install .Net Framework 2.0

If your O/S doesn't have installed .Net Framework 2.0 yet, "Setup.exe" would install .Net Framework 2.0 automatically. And install .Net Framework 2.0 step by step as the following instructions:

1. Double click "Setup.exe" (The file is located in the win32 folder of the disc.)
2. Select Read and accept the terms of the license agreement, and click "Install", as figure 11.
3. Wait the installation, as figure 12.
4. Click "Exit" to finish the installation, as figure 13.

ClarIDy UHF USB Reader Demo Program




Figure 11

ClarIDy UHF USB Reader Demo Program




Figure 12

ClarIDy UHF USB Reader Demo Program




Figure 13

2.3 Install ClarIDy UHF Demo

Install ClarIDy UHF Demo step by step as the following instructions:

1. Double click "Setup.exe" which is in the disc (The file is located in the win32 folder of the disc.).
2. Click "Next", as figure 14.
3. Click "Browser" to the Folder to install and select the user, and click "Next", as figure 15.
4. Click "Next" to start installation, as figure 16.
5. Wait for the installation, as figure 17.
6. Click "Close" to exit, as figure 18.

ClarIDy UHF USB Reader Demo Program



Figure 14




Figure 15

ClarIDy UHF USB Reader Demo Program




Figure 16




Figure 17

ClarIDy UHF USB Reader Demo Program




Figure 18

ClarIDy UHF USB Reader Demo Program

3. Demo Program Operation Guide

The following sections will describe the usage of the ClarIDy UHF Demo application. The application includes seven Controls, "Setting Control", "Algorithm Control", "Set-Session Control", "Inventory Control", "Read/Write Control", "Filter Inventory Control", "Filter Read/Write Control" and "Lock/Kill Control".

3.1 Setting Control

Click the "Setting" button of the main form, as figure 19. The Settings Page is displayed. This page allows the user to configure the following items:

- Link Profile
- Data Format (Compact, Normal or Extended)
- Operational Mode (Continuous Mode or Discontinuous Mode)
- Inventory Algorithm (Fixed "Q", Variable "Q", Variable "Q" Adjustable or Variable "Q" Threshold)



ClarIDy UHF USB Reader Demo Program

Figure 19: Setting View Panel

As you can see in Figure 20, the settings page has a two column layout. The left column is used to specify the startup settings that will be automatically applied to the reader when the application starts. The right column allows the user to change the current reader configuration.




Figure 20: Settings

1. Link Profile: Sets the current link profile for the reader module, as figure 21. The option is as follows:

- 0: DSB_ASK / M0 / 40 khz
- 1: DSB_ASK / M1 / 160 khz
- 2: PR_ASK / M2 / 25U khz
- 3: PR_ASK / M2 / 300 khz
- 4: DSB_ASK / M0 / 400 khz
- 5: PR_ASK / M1 / 250 khz




Figure 21

2. Data Format: Sets the operation response data reporting mode for tag-protocol operations, as figure 22. The option is as follows:

COMPACT: The response data is limited to provide the application with the pertinent tag-access operation data, but minimize the amount of MAC-to-host communication overhead.

NORMAL: The response data builds on the compact mode to provide the application with status and contextual information to give additional finer-grained feedback such as the beginning of inventory cycles, etc.

EXTENDED: The response data builds on the normal mode by providing additional

ClarIDy UHF USB Reader Demo Program

diagnostics and statistical information.



Figure 22

3. Operation Mode: Sets the reader's operation mode, as figure 23. The option is as follows:

CONTINUOUS: In continuous mode, when a tag-protocol-operation cycle (i.e., one iteration through all enabled antenna ports) has completed, the reader module will begin a new tag-protocol-operation cycle with the first enabled antenna port and will continue to do so until the operation is explicitly cancelled by the application.

NONCONTINUOUS: In non-continuous mode, only a single tag-protocol-operation cycle is executed upon the reader module.



Figure 23

4. Inventory Algorithm: Allows the application to set the currently-active singulation algorithm, as figure 24. The option is as follows:

0: ALGORITHM_FIXEDQ

1: DYNAMICQ

2: DYNAMICQ_ADJUST

3: DYNAMICQ_THRESHOLD




Figure 24

ClarIDy UHF USB Reader Demo Program

3.2 Algorithm Control

Click the “Algorithm” button of the main form, as figure 25. The Algorithm pane is used to view, the parameters for the selected singulation algorithm. The user may select Fixed Q, Dyanmic Q, Dynamic Q Adjustable and Dynamic Q Threshold from the Active Algorithm combo box and click “Load” button to query the current selected Algorithm and refresh the values displayed in the Algorithm Settings View panel, as figure 26.




Figure 25: Algorithm View Panel

ClarIDy UHF USB Reader Demo Program

Activate Select Rules: FixedQ

Algorithm	Q Value	Retry Count	Toggle Target	Repeat Until No Tags	Algorithm	Q Value
FixedQ	8	0	Enable	Enable		

Algorithm Setting:

Q Value:

Retry Count:

Toggle Target (A<>B):

Repeat Until No Tags:

Figure 26: Load Value

To modify the algorithm settings for the current reader, click on the “Edit” button. This will enable a algorithm setting panel similar to the one shown in Figure 27.

Activate Select Rules: FixedQ

Algorithm	Q Value	Retry Count	Toggle Target	Repeat Until No Tags	Algorithm	Q Value
FixedQ	8	0	Enable	Enable		

Algorithm Setting:

Q Value:

Retry Count:

Toggle Target (A<>B):

Repeat Until No Tags:

Figure 27: Modify Algorithm Settings

ClarIDy UHF USB Reader Demo Program

1. FixedQ : Fixed Q algorithm. The items as follows:
 - 1: **qValue**: The Q value to use. Valid values are 0 to 15, inclusive.
 - 2: **retryCount**: Specifies the number of times to try another execution of the singulation algorithm for the specified session/target before either toggling the target (if toggleTarget is non-zero) or terminating the inventory/tag access operation. Valid values are 0-255, inclusive.
 - 3: **toggleTarget**: A flag that indicates if, after performing the inventory cycle for the specified target (i.e., A or B), if the target should be toggled (i.e., A to B or B to A) and another inventory cycle run. A non-zero value indicates that the target should be toggled. A zero value indicates that the target should not be toggled. Note that if the target is toggled, retryCount and repeatUntilNoTags will also apply to the new target.
 - 4: **repeatUntilNoTags**: A flag that indicates whether or not the singulation algorithm should continue performing inventory rounds until no tags are singulated. A non-zero value indicates that, for each execution of the singulation algorithm, inventory rounds should be performed until no tags are singulated. A zero value indicates that a single inventory round should be performed for each execution of the singulation algorithm.
2. DynamicQ: Adjusts the Q value based on the presence or absence of tags. The items as follows:
 - 1: **startQValue**: The starting Q value to use. Valid values are 0 to 15, inclusive.
 $\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$
 - 2: **minQValue**: The minimum Q value to use. Valid values are 0 to 15, inclusive.
 $\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$
 - 3: **maxQValue**: The maximum Q value to use. Valid values are 0 to 15, inclusive.
 $\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$
 - 4: **retryCount**: Specifies the number of times to try another execution of the singulation algorithm for the specified session/target before either toggling the target (if toggleTarget is non-zero) or terminating the inventory/tag access operation. Valid values are 0-255, inclusive.
 - 5: **maxQueryRepCount**: The maximum number of ISO 18000-6C QueryRep commands that will follow the ISO 18000-6C Query command during a single inventory round. Valid values are 0-255, inclusive.
 - 6: **toggleTarget**: A flag that indicates if, after performing the inventory cycle for the specified target (i.e., A or B), if the target should be toggled (i.e., A to B or B to A) and another inventory cycle run. A non-zero value indicates that the target should be toggled. A zero value indicates that the target should not be toggled. Note that if the target is toggled, retryCount and repeatUntilNoTags

ClarIDy UHF USB Reader Demo Program

will also apply to the new target.

3. **DynamicQAdjust:** This algorithm modifies the previous dynamic Q algorithm by issuing ISO 18000-6C Query Adjust commands instead of ISO 18000-6C Query commands when adjusting the Q value. The items as follows:

1: startQValue: The starting Q value to use. Valid values are 0 to 15, inclusive.

$\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$

2: minQValue: The minimum Q value to use. Valid values are 0 to 15, inclusive.

$\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$

3: maxQValue: The maximum Q value to use. Valid values are 0 to 15, inclusive.

$\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$

4: retryCount: Specifies the number of times to try another execution of the singulation algorithm for the specified session/target before either toggling the target (if toggleTarget is non-zero) or terminating the inventory/tag access operation. Valid values are 0-255, inclusive.

5: maxQueryRepCount: The maximum number of ISO 18000-6C QueryRep commands that will follow the ISO 18000-6C Query command during a single inventory round. Valid values are 0-255, inclusive.

6: toggleTarget: A flag that indicates if, after performing the inventory cycle for the specified target (i.e., A or B), if the target should be toggled (i.e., A to B or B to A) and another inventory cycle run. A non-zero value indicates that the target should be toggled. A zero value indicates that the target should not be toggled. Note that if the target is toggled, retryCount and repeatUntilNoTags will also apply to the new target.

4. **DynamicQThreshold:** This algorithm uses a Q-modification algorithm that allows the application to control the change of the Q-adjustment-threshold value. The items as follows:

1: startQValue: The starting Q value to use. Valid values are 0 to 15, inclusive.

$\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$

2: minQValue: The minimum Q value to use. Valid values are 0 to 15, inclusive.

$\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$

3: maxQValue: The maximum Q value to use. Valid values are 0 to 15, inclusive.

$\text{minQValue} \leq \text{startQValue} \leq \text{maxQValue}$

4: retryCount: Specifies the number of times to try another execution of the singulation algorithm for the specified session/target before either toggling the target (if toggleTarget is non-zero) or terminating the inventory/tag access operation. Valid values are 0-255, inclusive.

5: toggleTarget: A flag that indicates if, after performing the inventory cycle for the specified target (i.e., A or B), if the target should be toggled (i.e., A to B or B to

ClarIDy UHF USB Reader Demo Program

A) and another inventory cycle run. A non-zero value indicates that the target should be toggled. A zero value indicates that the target should not be toggled. Note that if the target is toggled, retryCount and repeatUntilNoTags will also apply to the new target.

6: thresholdMultiplier: The multiplier, specified in units of fourths (i.e., 0.25), that will be applied to the Q-adjustment threshold as part of the dynamic-Q algorithm. Valid values are 0-255, inclusive.

ClarIDy UHF USB Reader Demo Program

3.3 Inventory Control

Click the “Inventory” button of the main form, as figure 28. The Inventory panel is used to read tag data and view tag data. Click the “Start” button to read tags, as figure 29.



Figure 28: Inventory Control.

ClarIDy UHF USB Reader Demo Program

No	PC	EPC	CRC	Count	RSSI
1	3000	123456789012345678ABCDEF	0525	238	87.2
2	3000	1B0C5678901234567890ABCD	D0C9	192	85.6
3	3000	E00012345678901234500001	4CF4	163	87.2
4	3000	123400005678901234500005	A87A	138	87.2
5	3000	E00012345678901234500002	0525	134	79.2

Figure 29: Start Read Tags

Click the “Stop” button to stop read tags, as figure 30.

No	PC	EPC	CRC	Count	RSSI
1	3000	123456789012345678ABCDEF	0525	2475	86.4
2	3000	1B0C5678901234567890ABCD	D0C9	2435	84.8
3	3000	E00012345678901234500001	4CF4	2402	80.8
4	3000	123400005678901234500005	A87A	2388	87.2
5	3000	E00012345678901234500002	0525	2386	87.2

Figure 30: Stop Read Tags

ClarIDy UHF USB Reader Demo Program

3.4 Read/Write Control

Click the “Read/Write” button of the main form, as figure 31. The “Read/Write” panel is used to read tag data and write tag data. The user may select “Reserved – Memory Band 0”, “EPC – Memory Band 1”, “TID – Memory Band 2” and “User – Memory Band 3” from the Memory Bank combo box. When this combo box is modified, the group box enabled with the indicated memory bank in the “Read/Write” panel.





Figure 31: Read/Write Control

The user can write or read EPC code and User Memory. When the user wants to write EPC, the user must input 24 hexadecimal digits, as figure 32.



ClarIDy UHF USB Reader Demo Program

Figure 32: Write EPC

When the user wants to read EPC, the user clicks the “Read” button and value is showed to message list, as figure 33.





Figure 33: Read EPC

When the user wants to write User Memory, the user must input location and 4 hexadecimal digits, as figure 34



A screenshot of a dialog box titled "Read/Write User Memory". It contains two input fields: "Location : 0" and "Value : 0000". Below the "Value" field, there is a note: "(Please input 4 Hexadecimal digits 0-9, A-F)".

Figure 34: Write User Memory

When the user wants to read User Memory, the user must input location and value is showed to message list, as figure 35.




Figure 35: Read User Memory

ClarIDy UHF USB Reader Demo Program

3.5 Filter Inventory

Click the “Filter Inventory” button of the main form, as figure 36. The “Filter Inventory” panel is used to read tag UID. The user may select to read tag UID by filter value. If the user selects “NONE” from the rule combo box, the reader will read all cards. If the user selects “NOT EQUAL” from the rule combo box, the reader will read card which is not match filter value. If the user selects “EQUAL” from the rule combo box, the reader will read card which is match filter value.

Follow the instructions step by step as following:

1. Select “Rule”
2. Select start location of filter value
3. Input filter value
4. Select “Memory Bank”
5. Click the “Start” button, the result as figure 37.




Figure 36: Filter Inventory Control

ClarIDy UHF USB Reader Demo Program

claridy_uem001_000001

Rule: Start Location: Length: Filter Value:

Memory Bank :

No	PC	EPC	CRC	Count	RSSI
1	3000	123456789012345678ABCDEF	0525	79	84.8

Figure 37

ClarIDy UHF USB Reader Demo Program

3.6 Filter Write Read

Click the “Filter Write/Read” button of the main form, as figure 38. The “Filter Write/Read” panel is used to read and write tag. The user may select to read and write by filter value. If the user selects “NONE” from the rule combo box, the reader will read or write one of cards. If the user selects “NOT EQUAL” from the rule combo box, the reader will read or write one of cards which is not match filter value. If the user selects “EQUAL” from the rule combo box, the reader will read or write one of cards which is match filter value.

Follow the instructions step by step as following:

1. Select “Rule”
2. Select start location of filter value
3. Input filter value
4. Select “Memory Bank”
5. Click the “Read” button or “Write button.”




Figure 38: Filter Write/Read Control

ClarIDy UHF USB Reader Demo Program

3.7 Lock/Kill Tag

Click the “Lock/Kill” page of the main form, as figure 39. The “Lock/Kill” panel is used to Lock tag data and Kill tag.




Figure 39

Follow the instructions step by step as following:

1. Select “Mask Memory Bank”
2. Select “Rule”
3. Select start location of filter value
4. Input “Filter Value”
5. If you want to lock the tag, please select state (Access PWD, Kill PWD, EPC Bank, TID Bank, User Bank) and input “AccessPWD”. And if you want to kill the tag, please input “AccessPWD” and KillPWD”.
6. If you want to kill or lock the tag, please select “OK”, as Figure 40.

ClarIDy UHF USB Reader Demo Program

- The kill and lock function would not be change permanently, please confirm again as figure 41.




Figure 40




Figure 41

Note:

For individual passwords, the access permissions can be set as figure42.




Figure 42

Accessible: The password may be read and written when the tag is in either the open or secured states.

Accessible Permanently: The password may be read and written when the tag is in either the open

ClarIDy UHF USB Reader Demo Program

or secured states and this access permission should be set permanently.

Secured Accessible: The password may be read or written only when the tag is in the secured state.

Not Accessible Permanently: The password may not be read or written and this access permission should be set permanently.

No Change: The password's access permission should remain unchanged.

The memory bank is writeable when the tag is in either the open or secured states, as figure 43.




Figure 43

Writeable: The memory bank is writeable when the tag is in either the open or secured states.

Writeable Permanently: The memory bank is writeable when the tag is in either the open or secured states and this access permission should be set permanently.

Secured Writeable: The memory bank is writeable only when the tag is in the secured state.

Not Writeable Permanently: The memory bank is not writeable and this access permission should be set permanently.

No Change: The memory bank's access permission should remain unchanged.

ClarIDy UHF USB Reader Demo Program

4. Error Code

The following lists provide error codes of UHF Reader Demo Program. These values are defined in the description.

Code (dec)	Description
0	Success
-9999	Attempted to open a reader that is already open
-9998	Buffer supplied is too small
-9997	General failure
-9996	Failed to load reader bus driver
-9995	Library cannot use version of reader bus driver present on system
-9994	Operation cannot be performed while library is in emulation mode
-9993	Antenna number is invalid
-9992	Reader handle provided is invalid
-9991	One of the parameters to the function is invalid
-9990	Attempted to open a non-existent reader
-9989	Library has not been successfully initialized
-9988	Function not supported
-9987	Operation was cancelled by call to cancel operation, close reader, or shut down the library
-9986	Library encountered an error allocating memory
-9985	The operation cannot be performed because the reader is currently busy
-9984	The underlying reader module encountered an error
-9983	The reader has been detached from the system
-9982	The RFID library function is not allowed at this time.
-9981	The reader module's MAC firmware is not responding to requests.
-9980	The MAC firmware encountered an error while initiating the nonvolatile memory update. The MAC firmware will return to its normal idle state without resetting the reader module.
-9979	An attempt was made to write data to an address that is not in the valid range of reader module nonvolatile memory addresses.
-9978	The MAC firmware encountered an error while trying to write to the reader module's nonvolatile memory region.
-9977	The underlying transport layer detected that there was an overflow error resulting in one or more bytes of the incoming data being dropped. The operation was aborted and all data in the pipeline was flushed.

ClarIDy UHF USB Reader Demo Program

-7999	Fail to find reader
-7998	Fail to allocate memory
-7997	Write Data failure
-7996	Read Data failure
-7995	Lock Tag failure
-7994	Kill Tag failure

ClarIDy UHF USB Reader Demo Program

5. Uninstall

Uninstall ClarIDy UHF Demo program step by step as the following instructions:

1. Double click "Setup.exe" which is in the disc.
2. Select "Remove ClarIDy UHF Demo", as figure 44.
3. Waiting system to remove, as figure 45.
4. The "ClarIDy UHF Demo" is completed removed and click "Close" to close window, as figure 46.




Figure 44

ClarIDy UHF USB Reader Demo Program




Figure 45




Figure 46