

Software Name: Firmware for ioLogik E1200 Series (E1241)

Version No.	Build Date No./ Release Date	Supported OS	Apply to Models	New Features/ Enhancements	Bugs Fixed/Changes	Note
v3.0.0	Build17111512	N/A	ioLogik E1241-T, ioLogik E1241	New Features: 1. Added OPTIONS method for RESTful API. 2. Added quick access URI for RESTful API. Enhancements: 1. Added SNMP Trap Community Setting on web console 2. Mentioned max. 16 characters on password setting page	Bugs Fixed: 1. Fixed DHCP lease time did not ask for extension when half of the lease time elapsed. 2. Closed IP forwarding function (Port 0). 3. Closed UDP Port 161 when SNMP agent is disabled. 4. Fixed RESTful API header case-sensitive issue. 5. Fixed invalid token issue on login page when using Firefox. Changes: N/A	1. This version of firmware works with the ioSearch V2.0 or later only. 2. Update only the next or the previous released firmware version to prevent from system failure.
v2.5	Build16091211	N/A	ioLogik E1241, ioLogik E1241-T	New Features: 1. Added AO 0-20 mA mode (only on hardware v1.0.2 and later). 2. Added EtherNet/IP protocol. 3. Added RESTful API. 4. Added new registers for Modbus/TCP protocol. 5. Added new OIDs of SNMP protocol. 6. Modbus, EtherNet/IP, RESTful Services can be disabled (default: enable). 7. Added sending heartbeat to 9500 port of MX-AOPC UA Server after heartbeat function is enabled. 8. Increased password length from 8 to 16. 9. Added checking special character function for preventing from Cross-Site Scripting. 10. Changed sending password from GET to POST method. Enhancements: N/A	Bugs Fixed: 1. Fixed file transfer with Chrome browser issue (e.g. firmware update, configuration import or export). 2. Fixed wrong scaled value. Changes: N/A	N/A

Form number: HQ-PD.450 Version: v3.0.0 Page 1 of 3



Software Name: Firmware for ioLogik E1200 Series (E1241)

Version No.	Build Date No./ Release Date	Supported OS	Apply to Models	New Features/ Enhancements	Bugs Fixed/Changes	Note
v2.4	Build16053018	N/A	ioLogik E1241, ioLogik E1241- T	New Features: 1. Improve protocol efficiency with ioLogik 2500 series . Enhancements: N/A	Bugs Fixed: N/A Changes: N/A	N/A
v2.2	Build14121211	N/A	ioLogik E1241-T, ioLogik E1241	New Features: 1. Support ioLogik 2500 expansion mode. 2. Support safe mode auto-clear function. 3. Support scaling. Enhancements: N/A	Bugs Fixed: 1. When the Heart beat Interval Time = 0, the P2P server will reconnect continuously. 2. When the P2P client heartbeat is set to a value larger than 256, the time interval will be incorrect. Changes: N/A	N/A
v2.0	Build13041515	N/A	ioLogik E1241, ioLogik E1241- T	New Features: 1. Support SNMP protocol. 2. Add P2P heartbeat function . Enhancements: N/A	Bugs Fixed: N/A Changes: N/A	1. This version of firmware works with the ioSearch V1.5 or later only. 2. Use web console when upgrading firmware from V1.0 to V1.10.
v1.9	Build11112413	N/A	ioLogik E1241, ioLogik E1241- T	New Features: N/A Enhancements: 1. Ensured system to work properly after unstable power condition.	Bugs Fixed: N/A Changes: N/A	N/A

Form number: HQ-PD.450 Version: v3.0.0 Page 2 of 3



Software Name: Firmware for ioLogik E1200 Series (E1241)

Version No.	Build Date No./ Release Date	Supported OS	Apply to Models	New Features/ Enhancements	Bugs Fixed/Changes	Note
v1.8	Build11092917	N/A	ioLogik E1241, ioLogik E1241-T	New Features: 1. Added Locating I/O function in General Settings. 2. Added Modbus address function code=0x08 for "ECHO" function. 3. Counter overflow status is displayed on Channel Settings, and can be manually cleared. 4. Added Modbus address for Peerto-peer connection and safe mode status. 5. Peer-to-peer connection and safe mode status are displayed on Channels Safe Mode Settings. Enhancements: 1. Improved firmware upgrading speed. 2. Removed Modbus/TCP ID	Bugs Fixed: 1. One DO/AO channel should only be peered by one DI/AI channel. 2. No matter safe mode is triggered by Watchdog or Peerto-peer, the DO/AO status under safe mode should be the same. Changes: N/A	N/A
				checking mechanism.		

Form number: HQ-PD.450 Version: v3.0.0 Page 3 of 3