

PT2

Products: PTZApp for Mac OS

Software Version: 1.4.1090.97

Published Date: NOV. 26, 2020

Copyright © 2020

Copyright Notice

This publication, including all photographs, illustrations and software, is protected under international copyright laws, with all rights reserved. Neither this manual, nor any of the material contained herein, may be reproduced without written consent of the author.

Disclaimer

The information in this document is subject to change without notice. The manufacturer makes no representations or warranties with respect to the contents hereof and specifically disclaim any implied warranties of merchantability or fitness for any particular purpose. The manufacturer reserves the right to revise this publication and to make changes from time to time in the content hereof without obligation of the manufacturer to notify any person of such revision or changes.

Limitations of Liability

UNDER NO CIRCUMSTANCES SHALL AVER BE LIABLE FOR DAMAGES OF ANY CHARACTER (E.G. DAMAGES FOR LOSS OF PROFIT, SOFTWARE RESTORATION, WORK STOPPAGE, LOSS OF SAVED DATA OR ANY OTHER COMMERCIAL DAMAGES OR LOSSES) RESULTING FROM THE APPLICATION OR IMPROPER USE OF THE AVER PRODUCT OR FAILURE OF THE PRODUCT, EVEN IF AVER IS INFORMED OF THE POSSIBILITY OF SUCH DAMAGES. FURTHERMORE, AVER WILL NOT BE LIABLE FOR THIRD-PARTY CLAIMS AGAINST CUSTOMER FOR LOSSES OR DAMAGES. AVER WILL IN NO EVENT BE LIABLE FOR ANY DAMAGES IN EXCESS OF THE AMOUNT AVER RECEIVED FROM THE END-USER FOR THE PRODUCT.

Content

Revision History and System Requirement	2
Important Notice	3
New Features	4
Problems Fixed	7
Known Issues	9





Software Version	Region	OS	Date	Model
1.4.1090.97	WW	MAC	NOV. 26 , 2020	All USB Camera
1.4.1087.90	WW	MAC	June 22, 2020	All USB Camera
1.4.1087.88	WW	MAC	June 05, 2020	All USB Camera
1.4.1081.87	WW	MAC	May 11, 2020	All USB Camera
1.4.1081.84	WW	MAC	March 10, 2020	All USB Camera
1.4.1077.81	WW	MAC	December 13, 2019	All USB Camera
1.4.1071.77	WW	MAC	October 14, 2019	All USB Camera
1.4.1067.71	WW	MAC	September 05, 2019	All USB Camera
1.3.1067.68	WW	MAC	August 08, 2019	All USB Camera
1.3.1063.67	WW	MAC	May 13, 2019	All USB Camera
1.3.1060.63	WW	MAC	January 28. 2019	All USB Camera
1.3.1059.60	WW	MAC	November 26, 2018	All USB Camera
				VB342/CAM540/VC 322/
1.3.1052.59	WW	MAC	October 12,2018	VC520+/CAM520/
				CAM530/CAM340
				VC 322/
1.3.1050.52	WW	MAC	March 16, 2018	VC520+/CAM520/CAM5
				30/CAM340
1.3.1045.48	1.3.1045.48 WW MAC December 27. 2017	December 27, 2017	VC 322/VC520/CAM520/	
1.3.1043.40	VVVV	IVIAC		CAM530/CAM340





Important Notice

- 1. PTZ app is a software tool used to configure and upgrade AVer USBCam series
- 2. Supports Mac OS 10.9 or above.





New Features

Software Version		New Feature	s
	1. Support I/O port enab	le/disable function for	VC/CAM520 Pro, C
	VB342+.		
	Two options: Enable all p	oorts; Only enable USB	port.
	ê	<u></u>	R70
	८ (२) २ 17	Settings	Diagnostic Utility
			blughoodo ounky
1.4.1090.97	I/O port	Enable all ports	s 🔻
	2. Support VC/CAM520 F	Pro to lock/unlock "Set	Preset function". V
	users can't set preset po	ints via remote contro	l, VISCA command,
	webpage. Please upgrade	e FW of VC/CAM520 P	ro to v.38 or later v
	enable this function.		
	Set Preset	On	-
	Gerneser	011	1
.4.1087.90	None		
	Support CAM540 to select	SmartFrame preset poin	t setting.
	PP AVer PTZApp		
	AVer CAM540		
	۵Ö۵ PTZ	Settings Dia	
	- ne	N	·
	Mirror	Off	-
	ADDR	01	•
.4.1087.88	Protocol	VISCA	-
	Baud Rate	9600	•
	Tracking mode	Manual frame	•
	SmartFrame preset point	Default(central of the scre	
	On Screen Menu	Detault(central of the scre Preset 0	en)
	Auto Focus	Preset 1 Preset 2	~
		Preset 3 Preset 4	
	Factory Default	Preset 5 Preset 6	
		Preset 7 Preset 8	~
4 4 4 0 0 4 0 7			
1.4.1081.87	Support FONE540 and Exp		etting.
1.4.1081.84	Revised Japanese translati	on sentences.	





1.4.1077.81	Support Japanese language and fix some bugs on CAM520 Pro.			
	1. Support Sleep timer for CAM520/VC520+			
	2. Please update cameras to the newest FW version (v.0.0.0018.36) to support this			
	function.			
1.4.1071.77	Sleep timer 10 sec Speakerphone Off 5 minutes 10 minutes			
	Noise suppression 20 minutes			
	Automatically gain control			
	3. Support VB342+ audio tracking functions.			
	Notes: Please upgrade VB342+ FW to v.48 to enable audio tracking functions.			
1.4.1067.71	Tracking mode Manual frame On Screen Menu Auto frame Off Off			
	Hotkey Control Audio Tracking			
	Audio Frame Audio Preset Tracking			
1.3.1067.68	 4. Support CAM540 Smart Frame OFF function. Please go with CAM540 FW. V.0.0.6002.58 			
1.3.1063.67	5. Support CAM340+, FOV 120/FOV 90 degree options			
1.5.1005.07	5. Support VB342+			
	 Add Smart frame button on PTZapp for CAM540. (Please upgrade CAM540 FW to version 0 0 6000.34.) 			
	PTZ Settings Diagnostic Utility			
1.3.1060.63	2. Add "Auto", "Manual" smart frame option for CAM540.			





	d Ô ⊳ PTZ	Settings Diagnostic Utility	
	Flip	Off	
	ADDR	01	
	Protocol	VISCA 🔻	
	Baud Rate	9600 🔻	
	Smart Framing	Manual	
	On Screen Menu	Manual Auto	
	1. Add " auto power on/off" option for VB342.		
		vice buttons option for VB342	
	3. Add displaylink enable,	/disable option for VB342 (While connecting to	
	Chrome box, please se	lect "OFF")	
	*To have these new options, please upgrade VB342 FW with version:		
	0.0.4002.48		
1.3.1059.60			
	<u>System</u>		
	Auto power on	On 💌	
	Enable device buttons	On 💌	
	Displaylink	On 💌	





Problems Fixed

Software Version	Problem Fixed		
1.4.1090.97	None		
1.4.1087.90	Fix the bug of VC520 Pro: The PTZApp v.114 has some bugs while operating VC520 Pro.		
1.4.1087.88	None		
1.4.1081.84	None		
1.4.1077.81	Some bugs fixed		
1.4.1071.77	None		
1.4.1067.71	None		
1.3.1067.68	None		
1.3.1063.67	None		
1.3.1060.63	None		
1.3.1059.60	None		
1.3.1052.59	None		
	Bug fixed.		
	1. For Macmini 10.10, when user open PTZApp and connect USB camera, and then		
	execute ISP under view seeing environment. It still jump a windows to block ISP.		
1.3.1050.52	2. Use VC322 to connect Mac and ZOOM ROOM at the same time. When users		
	execute ISP twice, it will jump " Upload file fail" information at the second times.		
	Users open PTZApp and Ucam at the same time. When user click auto update at		
	PTZApp. It will jump a message "the version doesn't match the devices."		
1.3.1045.48	None		
	"Upload file failed!" pops-up when performing ISP PTZApp at MAC		
1 2 1024 45	10.11.		
1.2.1024.45	The device is incompatible with this version! Pops-up when performing		
	ISP PTZApp at VC520 at MAC10.11.		
1.2.1025.30	None		
1 2 1021 25	"Upload file failed!" pops-up when performing ISP PTZApp under		
1.2.1021.25	MAC10.9.		
1.0.1019.21	None		
	1. Let PTZ app could record the last setting information on BLC(Back		
1.0.1011.19	Light Compensation).		
1.0.1011.19	2. Support Multi-Device. (VC520/CAM520)		
	3. Support new model.(CAM520)		
1.0.100.11	None		









Known Issues

Software Version	Known Issues
1.4.1090.97	None
1.4.1087.90	None
1.4.1087.88	None
1.4.1081.84	None
1.4.1077.81	None
1.4.1071.77	None
1.4.1067.71	None
1.3.1067.68	None
1.3.1063.67	None
1.3.1060.63	None



-