



Monitoring Citrix XenDesktop Site

eG Enterprise v6.0

Restricted Rights Legend

The information contained in this document is confidential and subject to change without notice. No part of this document may be reproduced or disclosed to others without the prior permission of eG Innovations Inc. eG Innovations Inc. makes no warranty of any kind with regard to the software and documentation, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose.

Trademarks

Microsoft Windows, Windows NT, Windows 2003, and Windows 2000 are either registered trademarks or trademarks of Microsoft Corporation in United States and/or other countries.

The names of actual companies and products mentioned herein may be the trademarks of their respective owners.

Copyright

©2014 eG Innovations Inc. All rights reserved.

Table of Contents

| | |
|---|-----------|
| MONITORING THE CITRIX XENDESKTOP BROKER SITE | 1 |
| 1.1 The Infrastructures Layer | 3 |
| 1.1.1 Hypervisor Details Test..... | 3 |
| 1.2 The Sites Layer | 8 |
| 1.2.1 Site Details Test | 8 |
| 1.3 The Controllers Layer | 14 |
| 1.3.1 Controller Details Test | 14 |
| 1.3.2 Controller Services Test..... | 17 |
| 1.4 The Delivery Groups Layer | 27 |
| 1.4.1 Desktop OS Machines Test | 28 |
| 1.4.2 Failed Machines Test | 32 |
| 1.4.3 Server OS Machines Test..... | 34 |
| 1.4.4 Machine Catalogs Test..... | 39 |
| 1.5 The Users Layer | 43 |
| 1.5.1 Logon Performance Test | 44 |
| 1.5.2 Session Details Test | 49 |
| 1.5.3 User Connection Failures | 52 |
| 1.5.4 User Connections Test | 54 |
| 1.5.5 User Logon Performance Test..... | 56 |
| CONCLUSION | 62 |

Table of Figures

| | |
|--|----|
| Figure 1.1: The layer model of a Citrix XenDesktop Site..... | 1 |
| Figure 1.2: The tests mapped to the Infrastructures layer | 3 |
| Figure 2.4: The detailed diagnosis of the State of the controller's connection to hypervisor measure | 8 |
| Figure 1.3: The test mapped to the Sites layer | 8 |
| Figure 1.4: The detailed diagnosis of the License server availability measure | 13 |
| Figure 1.5: The detailed diagnosis of the Total brokers for this site measure | 13 |
| Figure 1.6: The tests mapped to the Controllers layer | 14 |
| Figure 1.7: The detailed diagnosis of the Controller state measure | 17 |
| Figure 1.8: The tests mapped to the Delivery Groups layer | 28 |
| Figure 1.9: The detailed diagnosis of the Total machines measure..... | 31 |
| Figure 1.10: The detailed diagnosis of the Power state measure..... | 39 |
| Figure 1.11: The detailed diagnosis of the Allocation type measure | 43 |
| Figure 1.12: The tests mapped to the Users layer | 44 |

1

Monitoring the Citrix XenDesktop Broker Site

Deployment of XenDesktop in a single geographical location may be called as a site. A site therefore typically comprises of one/more brokers that point to the same database, a database server, a license server, a Citrix Studio, Citrix StoreFront, hypervisors, virtual machines, and XenApp servers on the server-side, and receivers at the client side.

Monitoring a XenDesktop site will therefore provide administrators with an overview of the hypervisors used, delivery groups managed, and desktops delivered by all the controllers in the site, and also points to probable problem areas. For this site-level overview of performance, eG Enterprise provides a dedicated *XenDesktop Site* monitoring model.




Figure 1.1: The layer model of a Citrix XenDesktop Site

MONITORING CITRIX XENDESKTOP BROKER SITE

Each layer in Figure 1.1. above is mapped to tests that to pull out a wealth of performance information related to a broker site. To enable the eG agent to collect these metrics, you need to deploy the agent on any broker in the site. This agent then leverages the Citrix ODATA API and runs Citrix Powershell SDK commands on the broker to report on site composition and to monitor the connectivity between the monitored broker and key site components such as the license server, database server, hypervisors, etc. In the process, breaks in connectivity between the broker and a hypervisor and unavailability of the license server/database server can be promptly detected. In addition, delivery groups managed by all the brokers in the site are monitored, and state of server/desktop OS machines in each group is reported, so that powered-off/unavailable machines can be isolated.

Using the metrics so collected, administrators can find quick and accurate answers for the following performance queries:

- Is the controller not able to communicate with any hypervisor? If so, which hypervisor is it?
- Is the license server in the site available? If so, how quickly is it responding to requests?
- Have any controllers in the site been inactive for a long time? Which brokers are these?
- Is any controller powered-off now?
- Which controller in the site has failed?
- Are the critical site services running on the controller being monitored?
- Which delivery group is overloaded with desktop sessions?
- Are any machines in the site waiting for image updates? Which ones are these and which delivery group do they belong to?
- Which machines are in the 'Suspended' or 'Powered off' state currently?
- Which machines in the site have failed to start?
- Which machines are stuck on boot?
- Which are the machines that have violated their maximum load limit?
- Is any machine in the maintenance mode?
- Which machine has the highest load evaluator index? What is contributing to this - high CPU/memory/disk space usage? or high user session load?
- How many catalogs have been configured on the broker? What are they? What is the type of each catalog?
- How many machines in each catalog have been assigned to users, and how many are unassigned?
- Does any catalog consist of machines that do not belong to any delivery group?
- Which user's logon is taking the maximum time? Where is the user experiencing delays - when brokering? at VM startup? during HDX connection? during authentication? when applying GPOs? at the time of logon script execution? when loading user profile? when handing off keyboard and mouse control to the user?

This document will elaborate on the top 5 layers of Figure 1.1 only.

1.1 The Infrastructures Layer

Use the test mapped to this layer to determine connectivity issues (if any) between the broker and the hosting platform.



Figure 1.2: The tests mapped to the Infrastructures layer

1.1.1 Hypervisor Details Test

This test reports the status of the connection between the XenDesktop broker and each server that hosts the machines. In the absence of a healthy connection between the two, the broker may not be able to provision machines on-demand.

If users complaint of any delay in the servicing of their machine requests, you may want to use this test to check the connection status between the broker and the server hosting that machine, so that connection errors (if any) can be promptly detected.

| | |
|---------------------------------|--|
| Purpose | Reports the status of the connection between the XenDesktop broker and each server that hosts the machines |
| Target of the test | A broker in a Citrix XenDesktop Site |
| Agent deploying the test | An internal agent |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--------------------------------------|---|------------------|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. DOMAIN, USERNAME and PASSWORD – To connect to a delivery controller in a site and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the DOMAIN to which the target controller belongs and enter the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 5. CONFIRM PASSWORD – Confirm the PASSWORD by retping it here. 6. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for each hypervisor with which the target controller communicates | | |
| Measurements made | Measurement | Measurement Unit | Interpretation |

| by the test | <p>State of controller’s connection to hypervisor:</p> <p>Indicates the status of the connection between the broker and this hosting server.</p> | <p>This test reports one of the following values to indicate the status of the connection between the broker and a hosting server:</p> <ul style="list-style-type: none">➤ On➤ InMaintenanceMode➤ Unavailable <p>The numeric values that correspond to the above-mentioned states are as follows:</p> <table><tr><th>State</th><th>Numeric Value</th><th>Description</th></tr><tr><td>On</td><td>1</td><td>Indicates that the broker is in contact with the hypervisor</td></tr><tr><td>InMaintenanceMode</td><td>2</td><td>Indicates that the hosting server (e.g., XenServer, Hyper-V) through which machines are managed, is under maintenance</td></tr><tr><td>Unavailable</td><td>3</td><td>Indicates that the broker is unable to contact the hypervisor</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned States while indicating the connection status of the broker and the hypervisor. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – 1 to 3– only.</p> <p>The detailed diagnosis capability of this measure if enabled, reveals the connection name, connection type, Hypervisor address, the preferred controller and the user who is accessing the hypervisor.</p> | State | Numeric Value | Description | On | 1 | Indicates that the broker is in contact with the hypervisor | InMaintenanceMode | 2 | Indicates that the hosting server (e.g., XenServer, Hyper-V) through which machines are managed, is under maintenance | Unavailable | 3 | Indicates that the broker is unable to contact the hypervisor |
|-------------------|---|---|-------|---------------|-------------|----|---|---|-------------------|---|---|-------------|---|---|
| State | Numeric Value | Description | | | | | | | | | | | | |
| On | 1 | Indicates that the broker is in contact with the hypervisor | | | | | | | | | | | | |
| InMaintenanceMode | 2 | Indicates that the hosting server (e.g., XenServer, Hyper-V) through which machines are managed, is under maintenance | | | | | | | | | | | | |
| Unavailable | 3 | Indicates that the broker is unable to contact the hypervisor | | | | | | | | | | | | |

| | <p>Is controller's connection to hypervisor in maintenance mode?:</p> <p>Indicates whether the connection between the broker and the hosting server is in maintenance mode.</p> | | <p>This measure reports a value <i>Yes</i> if the connection between the broker and the hosting server is in maintenance mode and <i>No</i> if otherwise.</p> <p>The numeric values corresponding to the above-mentioned measure values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>Yes</td><td>1</td></tr><tr><td>No</td><td>0</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating whether the connection between the broker and the hosting server is in maintenance mode. However, the graph of this measure will be represented using the corresponding numeric equivalents i.e., <i>0</i> or <i>1</i> only.</p> | Measure Value | Numeric Value | Yes | 1 | No | 0 |
|---------------|--|--|---|---------------|---------------|-----|---|----|---|
| Measure Value | Numeric Value | | | | | | | | |
| Yes | 1 | | | | | | | | |
| No | 0 | | | | | | | | |
| | <p>Is controller's connection to hypervisor in persistent?:</p> <p>Indicates whether/not the connection is persistent between the broker and the hosting server.</p> | | <p>This measure reports a value <i>Yes</i> if the connection between the broker and the hosting server is persistent and <i>No</i> if otherwise.</p> <p>The numeric values corresponding to the above-mentioned Measure Values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>Yes</td><td>1</td></tr><tr><td>No</td><td>0</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating whether the connection between the broker and the hosting server is persistent. However, the graph of this measure will be represented using the corresponding numeric equivalents i.e., <i>0</i> or <i>1</i> only.</p> | Measure Value | Numeric Value | Yes | 1 | No | 0 |
| Measure Value | Numeric Value | | | | | | | | |
| Yes | 1 | | | | | | | | |
| No | 0 | | | | | | | | |

| | <p>Is local storage caching enabled?:</p> <p>Indicates whether the local storage caching is enabled or not.</p> | <p>This measure reports a value <i>Yes</i> if the local storage caching capability is enabled and <i>No</i> if otherwise.</p> <p>The numeric values corresponding to the above-mentioned measure values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>Yes</td><td>1</td></tr><tr><td>No</td><td>0</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating whether the local storage caching capability is enabled. However, the graph of this measure will be represented using the corresponding numeric equivalents i.e., <i>0</i> or <i>1</i> only.</p> | Measure Value | Numeric Value | Yes | 1 | No | 0 |
|---------------|--|--|---------------|---------------|-----|---|----|---|
| Measure Value | Numeric Value | | | | | | | |
| Yes | 1 | | | | | | | |
| No | 0 | | | | | | | |
| | <p>Is machine creation service used to create VMs?:</p> <p>Indicates whether/not the machine creation service is used to create provisioned machines.</p> | <p>This measure reports a value <i>Yes</i> if the machine creation service is used to create provisioned machines and <i>No</i> if otherwise.</p> <p>The numeric values corresponding to the above-mentioned measure values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>Yes</td><td>1</td></tr><tr><td>No</td><td>0</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating whether the machine creation service is used to create provisioned machines. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents i.e., <i>0</i> or <i>1</i> only.</p> | Measure Value | Numeric Value | Yes | 1 | No | 0 |
| Measure Value | Numeric Value | | | | | | | |
| Yes | 1 | | | | | | | |
| No | 0 | | | | | | | |

MONITORING CITRIX XENDESKTOP BROKER SITE

The detailed diagnosis of the *State of the controller's connection to hypervisor* measure reveals the connection name, connection type, Hypervisor address, the preferred controller and the user who is accessing the hypervisor.

| Shows the Hypervisor connection information | | | | | |
|---|-----------------------|-----------------------------|----------------------|---------------|--------|
| CONNECTION NAME | CONNECTION TYPE | HYPERVISOR ADDRESS | PREFERRED CONTROLLER | USERNAME | SCOPES |
| Sep 26, 2014 10:37:33 | | | | | |
| VMware-VC | VMWare Virtualization | https://WIN-LJ278DNN4IQ/sdk | CITRIX\EXCL-1 | administrator | - |

Figure 1.1: The detailed diagnosis of the State of the controller's connection to hypervisor measure

1.2 The Sites Layer

Using the test mapped to this layer, you can monitor the availability and responsiveness of the license server in the site, the session related information and the number of brokers managed by this site.



Figure 1.3: The test mapped to the Sites layer

1.2.1 Site Details Test

This test promptly alerts administrators to the following anomalies related to the monitored site:

- The sudden non-availability of the license server in the site;
- Poor responsiveness of the license server;
- A session overload on the site;
- Inactive brokers in the site

| | |
|---------------------------------|---|
| Purpose | This test promptly alerts administrators to the following anomalies related to the monitored site: <ul style="list-style-type: none">➤ The sudden non-availability of the license server in the site;➤ Poor responsiveness of the license server;➤ A session overload on the site;➤ Inactive brokers in the site |
| Target of the test | A broker in a Citrix XenDesktop Site |
| Agent deploying the test | An internal agent |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--------------------------------------|---|-------------------------|---|
| Configurable parameters for the test | <ol style="list-style-type: none"> TEST PERIOD - How often should the test be executed HOST - The host for which the test is to be configured. PORT – The port number at which the specified HOST listens to. By default, this is 80. DOMAIN, USERNAME and PASSWORD – To connect to a delivery controller in a site and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the DOMAIN to which the target controller belongs and enter the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> The eG manager license should allow the detailed diagnosis capability Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for the XenDesktop server site to which the target broker belongs | | |
| Measurements made by the test | Measurement | Measurement Unit | Interpretation |
| | License server availability: Indicates the availability of the license server in this site. | Percent | <p>If the license server is available, a value of <i>100</i> is shown and if the license server is not available, a value of <i>0</i> is shown.</p> <p>Since the license server is responsible for managing the licenses for all the components of XenDesktop, the non-availability of the license server, should have serious repercussions on the performance of the XenDesktop site. However, such adversities are averted by the 90-day grace period that XenDesktop embeds; this allows the system to function normally for 90 days if the license server becomes unavailable.</p> <p>Moreover, if this measure reports that the license server is unavailable, then you may instantly want to know which license server the XenDesktop is communicating with. At this juncture, you can use the detailed diagnosis of this measure (if enabled) to ascertain the name of the license server and the port at which it listens.</p> |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | License server response time: Indicates the time taken by the broker to establish a connection with the license server. | Secs | Ideally, the response time should be low. | | | | | | |
|---------------|---|--------|--|---------------|---------------|----|---|-----|---|
| | Active licensed sessions: Indicates the total number of licensed sessions that are currently active on this site. | Number | This measure is a good indicator of the load on this site and the extent of license usage. | | | | | | |
| | Is DNS resolution enabled?: Indicates whether the DNS resolution is enabled or not on this site. | | <p>The values and their corresponding numeric values that this measure could report are:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>No</td><td>0</td></tr><tr><td>Yes</td><td>1</td></tr></table> <p>Note:</p> <p>By default, this measure reports the values <i>Yes</i> or <i>No</i> while indicating whether DNS resolution is enabled or not on this site. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents of <i>0</i> and <i>1</i> only.</p> | Measure Value | Numeric Value | No | 0 | Yes | 1 |
| Measure Value | Numeric Value | | | | | | | | |
| No | 0 | | | | | | | | |
| Yes | 1 | | | | | | | | |

| | <p>Is secure ICA required?:</p> <p>Indicates whether/not a secure ICA is required for this site.</p> | | <p>By default, client-server communications are obfuscated at a basic level through the SecureICA feature, which can be used to encrypt the ICA protocol.</p> <p>Plug-ins use the ICA protocol to encode user input (keystrokes and mouse clicks) and address it to a server farm for processing. Server farms use the ICA protocol to format application output (display and audio) and return it to the client device.</p> <p>You can increase the level of encryption for the ICA protocol when you publish a resource or after you publish a resource.</p> <p>In addition to situations when you want to protect against internal security threats, such as eavesdropping, you may want to use ICA encryption in the following situations:</p> <p>You need to secure communications from devices that use Microsoft DOS or run on Win16 systems</p> <p>You have older devices running plug-in software that cannot be upgraded to use SSL</p> <p>As an alternative to SSL/TLS encryption, when there is no risk of a "man-in-the-middle" attack</p> <p>The values that this measure can report and their corresponding numeric values are:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>No</td><td>0</td></tr><tr><td>Yes</td><td>1</td></tr></table> <p>Note:</p> <p>By default, this measure reports the values <i>Yes</i> or <i>No</i> while indicating whether a secure ICA is required for this site or not. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents of <i>0</i> and <i>1</i> only.</p> | Measure Value | Numeric Value | No | 0 | Yes | 1 |
|---------------|---|--|--|---------------|---------------|----|---|-----|---|
| Measure Value | Numeric Value | | | | | | | | |
| No | 0 | | | | | | | | |
| Yes | 1 | | | | | | | | |

| | <p>Is the trust request sent to the XML service port?</p> <p>Indicates whether/not trust requests were sent to the XML service.</p> | <p>Trusting requests sent to the XML Service means:</p> <ul style="list-style-type: none">• Smooth Roaming works when connecting with the Web Interface using pass-through or smart card authentication, and when connecting with the online plug-in using smart card authentication or the Kerberos pass-through option.• For example, you can use workspace control to assist health-care workers in a hospital using smart cards, who need to move quickly among workstations and be able to pick up where they left off in published applications.• XenApp can use the information passed on from Access Gateway (Version 4.0 or later) to control application access and session policies. This information includes Access Gateway filters that can be used to control access to published applications and to set XenApp session policies. If you do not trust requests sent to the XML Service, this additional information is ignored. <p>The values that this measure can report and their corresponding numeric values are:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>No</td><td>0</td></tr><tr><td>Yes</td><td>1</td></tr></table> <p>Note:</p> <p>By default, this measure reports the values <i>Yes</i> or <i>No</i> while indicating whether/not trust requests were sent to the XML service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents of <i>0</i> and <i>1</i> only.</p> | Measure Value | Numeric Value | No | 0 | Yes | 1 |
|---------------|--|--|---------------|---------------|----|---|-----|---|
| Measure Value | Numeric Value | | | | | | | |
| No | 0 | | | | | | | |
| Yes | 1 | | | | | | | |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|--|--------|---|
| | Total brokers on this site: Indicates the total number of brokers that are configured for this site. | Number | The detailed diagnosis of the <i>Total brokers for this site</i> measure displays the names of the brokers of this site, the machine on which the broker is installed, total number of desktops managed by this broker, the state of the broker, the version of the broker, the type of operating system, the version of the operating system, the last time at which the broker was active. This information helps you to identify the brokers that are active and are utilized effectively. |
|--|--|--------|---|

The detailed diagnosis of the *License server availability* measure displays the name of the License server in the site and the port at which it listens. Alongside, the detailed diagnosis displays the desktop model, desktop edition, application model and application edition that is compatible with the license. The date on which the license would finally expire/the last date for renewal of the license is provided in the *REQUIRED SA DATE* column. This information enables administrators to effectively troubleshoot issues with the availability of the License server.

| Shows the license server information on this site | | | | | |
|---|---------------------------------|---------------------|------------------|---------------|----------------------|
| SITE NAME | LICENSE SERVER NAME | LICENSE SERVER PORT | LICENSE EDITION | LICENSE MODEL | REQUIRED SA DATE |
| Sep 26, 2014 10:44:19 | | | | | |
| XenDesk7 | EXCL-1.Citrix.eginnovations.com | 27000 | Platinum Edition | User/Device | 5/22/2013 5:30:00 AM |

Figure 1.4: The detailed diagnosis of the License server availability measure

The detailed diagnosis of the *Total brokers for this site* measure displays the names of the brokers of this site, the machine on which the broker is installed, total number of desktops managed by this broker, the state of the broker, the version of the broker, the type of operating system, the version of the operating system, the last time at which the broker was active. This information helps you to identify the brokers that are active and are utilized effectively.

| Shows the list of controllers on this site | | | | | | | |
|--|---------------------------------|------------------|----------------|--------------------|---------|----------------|-----------------------|
| MACHINE NAME | DNS NAME | CONTROLLER STATE | TOTAL MACHINES | CONTROLLER VERSION | OS | OS VERSION | LAST ACTIVE TIME |
| Sep 26, 2014 10:44:19 | | | | | | | |
| CITRIX\EXCL-1 | EXCL-1.Citrix.eginnovations.com | Active | 1 | 7.0.0.3012 | Win32NT | 6.1.7601.65536 | 9/26/2014 10:42:29 AM |
| CITRIX\EXCL-2 | EXCL-2.Citrix.eginnovations.com | Active | 2 | 7.0.0.3012 | Win32NT | 6.1.7601.65536 | 9/26/2014 10:42:27 AM |

Figure 1.5: The detailed diagnosis of the Total brokers for this site measure

1.3 The Controllers Layer

For each controller in a site, the tests mapped to this layer report the current state of the controller and the state of each critical service running on the controller. Abnormalities in controller operations can thus be captured quickly.



Figure 1.6: The tests mapped to the Controllers layer

1.3.1 Controller Details Test

Controllers are server machines running instances of the broker service. This test auto-discovers the delivery controllers configured within a site, and reports the current status of each controller and the count of machines registered with every controller.

| | |
|---------------------------------|--|
| Purpose | Auto-discovers the delivery controllers configured within a site, and reports the current status of each controller and the count of machines registered with every controller |
| Target of the test | A broker in a Citrix XenDesktop Site |
| Agent deploying the test | An internal agent |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--------------------------------------|--|------------------|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. DOMAIN, USERNAME and PASSWORD – To connect to a delivery controller in a site and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the DOMAIN to which the target controller belongs and enter the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 5. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 6. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for the XenDesktop server site to which the target broker belongs | | |
| Measurements made by the | Measurement | Measurement Unit | Interpretation |

MONITORING CITRIX XENDESKTOP BROKER SITE

| test | Controller state: Indicates the current state of this desktop delivery controller (broker). | Number | <p>This test reports one of the following values to indicate the current state of a destop delivery controller:</p> <ul style="list-style-type: none">➤ Active – Indicates that the broker is powered-on and fully operational➤ On – Indicates that the broker is powered-on, but not fully operational➤ Failed – Indicates that the broker has failed due to some reason➤ Off – Indicates that the broker is powered-off <p>The numeric values that correspond to the above-mentioned states are as follows:</p> <table><tr><th>State</th><th>Numeric Value</th></tr><tr><td>Active</td><td>1</td></tr><tr><td>On</td><td>2</td></tr><tr><td>Failed</td><td>3</td></tr><tr><td>Off</td><td>4</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned States while indicating the current state of a broker. However, the graph of this measure will represent states using the corresponding numeric equivalents – i.e., <i>1 to 4</i>.</p> <p>The detailed diagnosis of this measure reveals when the controller was last accessed, when it was last started, and also displays the site services that were active on the controller during its last access.</p> | State | Numeric Value | Active | 1 | On | 2 | Failed | 3 | Off | 4 |
|---|---|---------------|--|-------|---------------|--------|---|----|---|--------|---|-----|---|
| | State | Numeric Value | | | | | | | | | | | |
| Active | 1 | | | | | | | | | | | | |
| On | 2 | | | | | | | | | | | | |
| Failed | 3 | | | | | | | | | | | | |
| Off | 4 | | | | | | | | | | | | |
| Total registered machines: Indicates the number of machines that are currently registered with this broker. | Number | | | | | | | | | | | | |

MONITORING CITRIX XENDESKTOP BROKER SITE

The detailed diagnosis of the *Controller state* measure reveals when the controller was last accessed, when it was last started, and also displays the name of the machine on which the broker is installed, the version of the broker, the Operating system of the machine and the Operating system version.

| Shows the controller information | | | | | | |
|----------------------------------|---------------|--------------------|---------|----------------|-----------------------|----------------------|
| DNS NAME | MACHINE NAME | CONTROLLER VERSION | OS | OS VERSION | LAST ACTIVE TIME | LAST START TIME |
| Sep 26, 2014 10:42:42 | | | | | | |
| EXCL-2.Citrix.eginnovations.com | CITRIX\EXCL-2 | 7.0.0.3012 | Win32NT | 6.1.7601.65536 | 9/26/2014 10:42:27 AM | 9/1/2014 11:19:01 AM |

Figure 1.7: The detailed diagnosis of the Controller state measure

1.3.2 Controller Services Test

The broker service is responsible for the brokering of user sessions to desktops or applications, and for power management of the underlying machines. Every controller in a site runs an instance of the broker service. In addition to the broker service, the following critical services also run on a controller:

- AD identity service
- Configuration service
- Host service
- Machine creation service
- Admin service
- Monitoring service
- Logging service

This test periodically checks the health of each of these services on the target controller in a XenDesktop site, and reports abnormalities (if any). With the help of this test, you can promptly detect which services have failed.

| | |
|---------------------------------|---|
| Purpose | Periodically checks the health of each of these services on the target controller in a XenDesktop site, and reports abnormalities (if any). With the help of this test, you can promptly detect which services have failed. |
| Target of the test | A broker in a Citrix XenDesktop Site |
| Agent deploying the test | An internal agent |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--------------------------------------|--|------------------|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. DOMAIN, USERNAME and PASSWORD – To connect to a delivery controller in a site and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the DOMAIN to which the target controller belongs and enter the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 5. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 6. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for every controller configured within a site | | |
| Measurements made by the | Measurement | Measurement Unit | Interpretation |

| test | <p>Broker service status:</p> <p>Indicates the current status of the broker service on this broker.</p> | Number | <p>The Citrix Broker Service brokers connections from endpoint devices to desktops and applications.</p> <p>The numeric values that correspond to the Measure Values that this measure can take are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNewerVersionThanService</td><td>5</td></tr><tr><td>DBOlderVersionThanService</td><td>6</td></tr><tr><td>DBVersionChangeInProgress</td><td>7</td></tr><tr><td>PendingFailure</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr><tr><td>DBNotFound</td><td>11</td></tr><tr><td>DBMissingOptionalFeature</td><td>12</td></tr><tr><td>DBMissingMandatoryFeature</td><td>13</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current state of the broker service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 13</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNewerVersionThanService | 5 | DBOlderVersionThanService | 6 | DBVersionChangeInProgress | 7 | PendingFailure | 8 | Failed | 9 | Unknown | 10 | DBNotFound | 11 | DBMissingOptionalFeature | 12 | DBMissingMandatoryFeature | 13 |
|---------------------------|--|--------|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|---------------------------|---|---------------------------|---|---------------------------|---|----------------|---|--------|---|---------|----|------------|----|--------------------------|----|---------------------------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 5 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 7 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| PendingFailure | 8 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 11 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBMissingOptionalFeature | 12 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |
| DBMissingMandatoryFeature | 13 | | | | | | | | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>AD identity service status:</p> <p>Indicates the current status of the AD Identity Service on this broker.</p> | <p>The Citrix AD Identity Service manages active directory computer accounts. Once the broker validates a user login, this service connects to the broker’s database to identify the virtual desktop that is assigned to the user who has logged in.</p> <p>The values that this measure reports and the numeric values that correspond to them are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the AD Identity Service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|--|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Configuration service status:</p> <p>Indicates the current status of the Configuration Service on this broker.</p> | <p>The Citrix Configuration Service stores the configuration information related to Citrix services in the broker’s MS SQL database.</p> <p>The values that this measure can report and their corresponding numeric values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the Configuration service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|--|---|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Host service status:</p> <p>Indicates the current status of the Host service on this broker.</p> | <p>The Citrix Host Service manages host and hypervisor connections.</p> <p>The values that this measure can take and their corresponding numeric values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the Configuration service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|--|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Machine creation service status:</p> <p>Indicates the current status of the Machine Creation Service on this broker.</p> | <p>The Citrix Machine Creation Service creates new virtual machines.</p> <p>Once a valid user logs into the XenDesktop Broker via the Web Interface, the XenDesktop Broker manages the delivery groups by building, starting, and shutting down the desktops as required. At this juncture, the XenDesktop Broker relies on Machine Creation Services (MCS) to deliver the appropriate desktop image to the Pooled and Dedicated delivery groups.</p> <p>The values that this measure can take and their corresponding numeric equivalents are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the Machine creation service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|--|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Admin service status:</p> <p>Indicates the current status of the Delegated Administration service on this broker.</p> | <p>The Delegated Administration Service (DAS) stores information about Citrix administrators and the rights they have. Services in the XenDesktop deployment use the DAS to determine whether a particular user has the privilege to perform an operation or not.</p> <p>The values that this measure can report and their corresponding numeric equivalents are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the Delegated Administration service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|---|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Licensing service status:</p> <p>Indicates the current status of the Licensing service on this broker.</p> | <p>The values that this measure can take and their corresponding numeric values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the Licensing service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|--|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Monitoring service status:</p> <p>Indicates the current status of the Monitoring service on this broker.</p> | <p>The Citrix Monitor Service monitors the Flexcast system. Citrix FlexCast is a delivery technology that allows an IT administrator to personalize virtual desktops to meet the performance, security and flexibility requirements of end users. Currently, there are five different FlexCast models available.</p> <p>The values that this measure can take and their corresponding numeric values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the Monitoring service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|--|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Logging service status:</p> <p>Indicates the current status of the Logging service on this broker.</p> | <p>The Configuration Logging Service logs configuration changes or administrator requested state changes made to the site.</p> <p>The values that this measure can take and their corresponding numeric values are as follows:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>OK</td><td>1</td></tr><tr><td>DBUnconfigured</td><td>2</td></tr><tr><td>DBRejectedConnection</td><td>3</td></tr><tr><td>InvalidDBConfigured</td><td>4</td></tr><tr><td>DBNotFound</td><td>5</td></tr><tr><td>DBNewerVersionThanService</td><td>6</td></tr><tr><td>DBOlderVersionThanService</td><td>7</td></tr><tr><td>DBVersionChangeInProgress</td><td>8</td></tr><tr><td>Failed</td><td>9</td></tr><tr><td>Unknown</td><td>10</td></tr></table> <p>Note:</p> <p>By default, this measure reports the above-mentioned Measure Values while indicating the current status of the Monitoring service. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents – i.e., <i>1 to 10</i>.</p> | Measure Value | Numeric Value | OK | 1 | DBUnconfigured | 2 | DBRejectedConnection | 3 | InvalidDBConfigured | 4 | DBNotFound | 5 | DBNewerVersionThanService | 6 | DBOlderVersionThanService | 7 | DBVersionChangeInProgress | 8 | Failed | 9 | Unknown | 10 |
|---------------------------|--|--|---------------|---------------|----|---|----------------|---|----------------------|---|---------------------|---|------------|---|---------------------------|---|---------------------------|---|---------------------------|---|--------|---|---------|----|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| OK | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| DBUnconfigured | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| DBRejectedConnection | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| InvalidDBConfigured | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNotFound | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| DBNewerVersionThanService | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| DBOlderVersionThanService | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| DBVersionChangeInProgress | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Failed | 9 | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 10 | | | | | | | | | | | | | | | | | | | | | | | |

1.4 The Delivery Groups Layer

The tests mapped to this layer monitor the desktop OS and server OS machines in each delivery group configured on the broker in a site and report the status of these machines.




Figure 1.8: The tests mapped to the Delivery Groups layer

1.4.1 Desktop OS Machines Test

XenDesktop supports two types of Delivery Agents: one for Windows Server OS machines and one for Windows Desktop OS machines. **Desktop OS Machines** are VMs or physical machines based on the Windows Desktop operating system used for delivering personalized desktops to users, or applications from desktop operating systems.

Delivery groups consist of virtual desktops and applications that are pooled, pre-assigned, or assigned on first use. Each group can contain only one type of desktop or application.

To track the status of desktop OS machines in each delivery group configured in a site, use the **Desktop OS Machines** test.

| | |
|--------------------------|--|
| Purpose | To track the status of desktop OS machines in each delivery group configured in a site |
| Target of the test | A broker in a Citrix XenDesktop Site |
| Agent deploying the test | An internal agent |

MONITORING CITRIX XENDESKTOP BROKER SITE

| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 5. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 6. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs. 9. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes. 10. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
|--------------------------------------|---|------------------|--|
| Outputs of the test | One set of results for each delivery group containing desktop OS machines in the site | | |
| Measurements made by the test | Measurement | Measurement Unit | Interpretation |
| | Total machines: Indicates the total number of machines in this group. | Number | Use the detailed diagnosis of this measure to know which desktop OS machines are part of a delivery group. |
| | Preparing machines: Indicates the number of machines in this group that are currently preparing sessions for users. | Number | |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|---|--------|---|
| | Pending image update machines: Indicates the number of machines managed by this delivery group to which updates are currently pending. | Number | Use the detailed diagnosis of this measure to know which machines are awaiting updates. |
| | Maintenance mode enabled machines: Indicates the number of machines in this group for which maintenance mode has been enabled. | Number | |
| | Powered on machines: Indicates the number of machines in this desktop group that are currently powered on. | Number | Use the detailed diagnosis of this measure to know which machines are currently powered on. |
| | Suspended machines: Indicates the number of machines in this delivery group that are currently in the Suspended state. | Number | Use the detailed diagnosis of this measure to know which machines are currently in the Suspended state. |
| | Powered off machines: Indicates the number of machines in this delivery group that are currently powered off. | Number | Use the detailed diagnosis of this measure to know which machines are currently in the powered off. |
| | Unavailable machines: Indicates the number of machines in the following power states: <ul style="list-style-type: none"> • Unavailable • Unmanaged • Unknown | Number | <p>A low value is desired for this measure.</p> <p>The detailed diagnosis of this measure will reveal the complete details of the unavailable machines, such as, the machine name, IP address, the machine type, the delivery group and catalog to which the machine belongs, the hosting server on which the machine operates, the name of the hypervisor and the controller on which the machine operates, the user who is active on the session, the location at which the changes made by the user is stored, the provision type of the machine, and the application published on the machine, if the machine is a XenAPP server.</p> |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|--|--------|--|
| | Assigned machines: Indicates the number of machines that are assigned to users in this delivery group. | Number | Use the detailed diagnosis of this measure to know which machines are assigned to users. |
| | Unassigned machines: Indicates the number of machines in this delivery group that are not assigned to users. | Number | Use the detailed diagnosis of this measure to know which machines are not assigned to users. |
| | Resuming machines: Indicates the number of machines in this group that are in the Resume state currently. | Number | Use the detailed diagnosis of this measure to know which machines are in the Resume state. |
| | Total sessions: Indicates the total number of user sessions to this delivery group. | | |

Use the detailed diagnosis of the *Total machines* measure to know which desktop OS machines are part of a delivery group.

| Shows the lists of desktop machines | | | | | | | | | | |
|-------------------------------------|--------------------------------------|--------------|-----------|-------------|----------------------------------|---------------------|--------------|----------------|--------------|--------|
| MACHINE NAME | DNS NAME | IP ADDRESS | OS | VDA VERSION | HOSTED MACHINE NAME | HOSTING SERVER NAME | FAILURE TYPE | FAILURE REASON | FAILURE TIME | IS ASS |
| Sep 26, 2014 10:47:12 | | | | | | | | | | |
| CITRIX\excalib7001 | excalib7001.Citrix.eginnovations.com | 192.168.8.74 | Windows 7 | 7.0.0.3018 | excalib7001(8.74) (old-8.248) | 192.168.10.14 | - | - | - | Yes |

Figure 1.9: The detailed diagnosis of the Total machines measure

For a list of powered off machines in a delivery group, use the detailed diagnosis of the *Powered off machines* measure.

MONITORING CITRIX XENDESKTOP BROKER SITE

| Shows the lists of powered off machines | | | | | | | | | | |
|---|--------------------------------------|------------|-----------|-------------|-------------------------------|---------------------|--------------|----------------|--------------|-------------|
| MACHINE NAME | DNS NAME | IP ADDRESS | OS | VDA VERSION | HOSTED MACHINE NAME | HOSTING SERVER NAME | FAILURE TYPE | FAILURE REASON | FAILURE TIME | IS ASSIGNED |
| Sep 26, 2014 06:57:38 | | | | | | | | | | |
| CITRIX\excalib7001 | excalib7001.Citrix.eginnovations.com | - | Windows 7 | 7.0.0.3018 | excalib7001(8.74) (old-8.248) | 192.168.10.14 | - | - | - | Yes |

1.4.2 Failed Machines Test

Using this test, administrator can figure out how many machines of which type are currently in a state of failure. The names of these machines and the precise failure state they are in presently can also be ascertained.

| | |
|---------------------------------|--|
| Purpose | Using this test, administrator can figure out how many machines of which type are currently in a state of failure. The names of these machines and the precise failure state they are in presently can also be ascertained |
| Target of the test | A broker in a Citrix XenDesktop Site |
| Agent deploying the test | An internal agent |

| | | | |
|--------------------------------------|--|------------------|--|
| Configurable parameters for the test | <ol style="list-style-type: none"> TEST PERIOD - How often should the test be executed HOST - The host for which the test is to be configured. PORT – The port number at which the specified HOST listens to. By default, this is 80. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes. REPORT BY MACHINE TYPE – If you want the results of this test to be grouped by machine type – i.e., grouped into Desktop OS Machines and Server OS Machines – then set this flag to Yes. If not, set this flag to No. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> The eG manager license should allow the detailed diagnosis capability Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for each delivery group configured for the XenDesktop broker site | | |
| Measurements made by the test | Measurement | Measurement Unit | Interpretation |
| | Machines that failed to start: Indicates the number of machines in this delivery group that failed to start. | Number | <p>The value of this measure refers to the number of failures that occurred due to a guest machine being unable to start as in disk is detached when attempting to boot or the hosting server reported that the VM could not be booted up.</p> <p>Use the detailed diagnosis of this measure to know which machines failed to start.</p> |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|---|--------|---|
| | Machines stuck on boot: Indicates the number of machines that are stuck on boot. | Number | This measure refers to the number of failures that occurred due to the guest operating system being unable to boot up fully. For example, OS BSOD during boot or unable to locate the boot partition. Use the detailed diagnosis of this measure to know which machines were stuck on boot. |
| | Unregistered machines: Indicates the number of machines in this delivery group that are not registered with the broker. | Number | Machine registration can fail due to loss of network connectivity between the machine and the broker, the clocks on the two being out of sync or the Desktop Service not running on the desktop. Use the detailed diagnosis of this measure to identify the unregistered machines. |
| | Maximum load: Indicates the number of machines in this delivery group that have violated their maximum load limit. | Number | This measure applies only to Server OS Machines. The value of this measure refers to the number of failures that occurred owing to too many sessions on the machine or because CPU or memory usage of the machines crossed the threshold specified for the delivery group. Use the detailed diagnosis of this measure to identify the loaded machines. |

1.4.3 Server OS Machines Test

Server OS Machines are VMs or physical machines based on the Windows Server operating system used for delivering applications or hosted shared desktops to users.

This test auto-discovers the Server OS Machines in the site and reports the session load on, resource usage of, and current state of each machine. This way, administrators can quickly identify machines that are experiencing heavy load and those that are consuming resources abnormally.

| | |
|---------------------------------|---|
| Purpose | Auto-discovers the Server OS Machines in the site and reports the session load on, resource usage of, and current state of each machine |
| Target of the test | A broker in the Citrix XenDesktop site |
| Agent deploying the test | An internal agent |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--------------------------------------|--|------------------|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 5. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 6. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs. 9. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes. 10. REPORT BY DELIVERY GROUP – If you want the results of this test to be grouped by delivery group then set this flag to Yes. In this case therefore, the delivery groups containing the server OS machines will be the primary descriptors of this test; expanding them will reveal the secondary descriptors – i.e., the server OS machines in each delivery group. If you want the results of this test to be indexed only by the names of the server OS machines, then set this flag to No. 11. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for each server OS machine running in the XenDesktop broker site | | |
| Measurements made by the test | Measurement | Measurement Unit | Interpretation |

| | <p>Power state:</p> <p>Indicates the current power state of this server OS machine.</p> | <p>The values this measure can report and their corresponding numeric values are listed in then table below:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>Unknown</td><td>0</td></tr><tr><td>Unavailable</td><td>1</td></tr><tr><td>Off</td><td>2</td></tr><tr><td>On</td><td>3</td></tr><tr><td>Suspended</td><td>4</td></tr><tr><td>Turning on</td><td>5</td></tr><tr><td>Turning Off</td><td>6</td></tr><tr><td>Suspending</td><td>7</td></tr><tr><td>Resuming</td><td>8</td></tr><tr><td>Unmanaged</td><td>9</td></tr></table> <p>Using the detailed diagnosis of the <i>Power state</i> measure you can view the complete configuration details of the server OS machine.</p> <p>Note:</p> <p>By default, this measure reports the Measure Values in the table above to indicate the power state of a server OS machine. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents only.</p> | Measure Value | Numeric Value | Unknown | 0 | Unavailable | 1 | Off | 2 | On | 3 | Suspended | 4 | Turning on | 5 | Turning Off | 6 | Suspending | 7 | Resuming | 8 | Unmanaged | 9 |
|---------------|--|--|---------------|---------------|---------|---|-------------|---|-----|---|----|---|-----------|---|------------|---|-------------|---|------------|---|----------|---|-----------|---|
| Measure Value | Numeric Value | | | | | | | | | | | | | | | | | | | | | | | |
| Unknown | 0 | | | | | | | | | | | | | | | | | | | | | | | |
| Unavailable | 1 | | | | | | | | | | | | | | | | | | | | | | | |
| Off | 2 | | | | | | | | | | | | | | | | | | | | | | | |
| On | 3 | | | | | | | | | | | | | | | | | | | | | | | |
| Suspended | 4 | | | | | | | | | | | | | | | | | | | | | | | |
| Turning on | 5 | | | | | | | | | | | | | | | | | | | | | | | |
| Turning Off | 6 | | | | | | | | | | | | | | | | | | | | | | | |
| Suspending | 7 | | | | | | | | | | | | | | | | | | | | | | | |
| Resuming | 8 | | | | | | | | | | | | | | | | | | | | | | | |
| Unmanaged | 9 | | | | | | | | | | | | | | | | | | | | | | | |

| | <p>Maintenance mode:</p> <p>Indicates whether/not this machine is in the maintenance mode currently.</p> | <p>The values this measure can report and their corresponding numeric values are listed in then table below:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>Off</td><td>0</td></tr><tr><td>On</td><td>1</td></tr></table> <p>Note:</p> <p>By default, this measure reports the Measure Values in the table above to indicate whether/not a server OS machine is in the maintenance mode. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents only.</p> | Measure Value | Numeric Value | Off | 0 | On | 1 |
|---------------|---|--|---------------|---------------|-----|---|-----|---|
| Measure Value | Numeric Value | | | | | | | |
| Off | 0 | | | | | | | |
| On | 1 | | | | | | | |
| | <p>Pending image update:</p> <p>Indicates whether/not image updates are pending on this machine.</p> | <p>The values this measure can report and their corresponding numeric values are listed in then table below:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>No</td><td>0</td></tr><tr><td>Yes</td><td>1</td></tr></table> <p>Note:</p> <p>By default, this measure reports the Measure Values in the table above to indicate whether/not image updates are pending on this server OS machine. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents only.</p> | Measure Value | Numeric Value | No | 0 | Yes | 1 |
| Measure Value | Numeric Value | | | | | | | |
| No | 0 | | | | | | | |
| Yes | 1 | | | | | | | |

| | <p>Is this physical machine?:</p> <p>Indicates whether this server OS machine is a physical or virtual machine.</p> | | <p>The values this measure can report and their corresponding numeric values are listed in then table below:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>No</td><td>0</td></tr><tr><td>Yes</td><td>1</td></tr></table> <p>Note:</p> <p>By default, this measure reports the Measure Values in the table above to indicate whether/not a server OS machine is a physical machine. However, in the graph of this measure, the same will be represented using the corresponding numeric equivalents only.</p> | Measure Value | Numeric Value | No | 0 | Yes | 1 |
|---------------|--|---------|--|---------------|---------------|----|---|-----|---|
| Measure Value | Numeric Value | | | | | | | | |
| No | 0 | | | | | | | | |
| Yes | 1 | | | | | | | | |
| | <p>Total sessions:</p> <p>Indicates the total number of user sessions on this server OS machine.</p> | Number | <p>This is a good indicator of the current session load on a server OS machine. Compare the value of this measure across machines to know which machine is overloaded with sessions.</p> | | | | | | |
| | <p>Load evaluator index:</p> <p>Indicates the load evaluator index of this machine.</p> | Percent | <p>A server’s load index may be the aggregate of:</p> <ul style="list-style-type: none">• Various computer performance counter based metrics, namely CPU, Memory and Disk Usage• Session Count <p>It is designed to indicate how suitable a XenApp Worker is to receive a new user session. It is the Delivery Controller’s responsibility to calculate the load index based on the aggregate of the normalized load rule indexes generated by the various load rules. As only the Delivery Controller can determine the session load, a server’s overall load index is calculated on the Delivery Controller and not the Virtual Delivery Agent.</p> <p>By comparing the value of this measure across server OS machines, you can figure out whether or not load is uniformly balanced across all servers in the site.</p> | | | | | | |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|--|---------|--|
| | CPU: Indicates the CPU load evaluator index of this server OS machine. | Percent | A high value is indicative of excessive CPU usage by the machine over time. |
| | Memory: Indicates the memory load evaluator index of this server OS machine. | Percent | A high value is indicative of excessive memory usage by the machine over time. |
| | Disk: Indicates the disk load evaluator index of this server OS machine. | Percent | A high value is indicative of excessive disk usage by the machine over time. |
| | Session count: Indicates the session count load evaluator index of this server OS machine. | Percent | A high value indicates that the machine has been consistently handling many user sessions. |

Using the detailed diagnosis of the *Power state* measure you can view the details of the server OS machine such as the IP address, DNS name, OS of the machine, the server hosting the machine, and the current status of that machine.

| Shows the list of server machines | | | | | | | | | | |
|-----------------------------------|------------------------------------|---------------|--------------------------------|-------------|------------------------|------------------------|--------------|----------------|--------------|------------------|
| MACHINE NAME | DNS NAME | IP ADDRESS | OS | VDA VERSION | HOSTED MACHINE NAME | HOSTING SERVER NAME | FAILURE TYPE | FAILURE REASON | FAILURE TIME | MAINTENANCE MODE |
| Sep 26, 2014 10:52:35 | | | | | | | | | | |
| CITRIX\CTX-EXCL3 | CTX-EXCL3.Citrix.eginnovations.com | 192.168.8.126 | Windows 2008 R2 Service Pack 1 | 7.0.0.3018 | Win2K8R2-EXCL3 [8.126] | newxenserver61(10.165) | - | - | - | Off |

Figure 1.10: The detailed diagnosis of the Power state measure

1.4.4 Machine Catalogs Test

In XenDesktop, collections of virtual machines (VMs) or physical computers of the same type are managed as a single entity called a catalog. To deliver desktops to users, the machine administrator creates a catalog of machines and the assignment administrator allocates machines from the catalog to users by creating delivery groups.

This test auto-discovers the catalogs managed by the XenDesktop site being monitored, and reports useful statistics related to each catalog, which reveal:

- The catalog type;
- The type of desktops allocated to each catalog;
- The availability, usage, and assignment of desktops in each catalog

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|---|---|-------------------------|-----------------------|
| Purpose | Auto-discovers the catalogs managed by the XenDesktop site being monitored, and reports useful statistics related to each catalog | | |
| Target of the test | A broker in a XenDesktop site | | |
| Agent deploying the test | An internal agent | | |
| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. DOMAIN, USERNAME and PASSWORD – To connect to a delivery controller in a site and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the DOMAIN to which the target controller belongs and enter the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 5. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 6. REPORT BY MACHINE TYPE – If you want the results of this test to be grouped by machine type – i.e., grouped into Desktop OS Machines and Server OS Machines – then set this flag to Yes. If not, set this flag to No. 7. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for every catalog on each broker configured within a site | | |
| Measurements made by the | Measurement | Measurement Unit | Interpretation |

| test | <p>Allocation type:</p> <p>Indicates the allocation type of the machines available in this catalog.</p> | Number | <p>This measure can report any one of the following values:</p> <ul style="list-style-type: none">➤ Static➤ Permanent➤ Random➤ Unknown <p>The table below provides the numeric values that correspond to the allocation types listed above, and a brief description of each type:</p> <table><tr><th>Allocation Type</th><th>Numeric Value</th><th>Description</th></tr><tr><td>Static</td><td>1</td><td>Indicates that the machines in this catalog are either assigned by the administrator or assigned on first use to users. This assignment will change only when the administrator explicitly changes the assignments.</td></tr><tr><td>Permanent</td><td>2</td><td>Indicates that the machines in this catalog are permanently assigned to the user.</td></tr><tr><td>Random</td><td>3</td><td>Indicates that the machines in this catalog are picked in random and are temporarily assigned to the user.</td></tr></table> <p>Note:</p> <p>By default, this measure reports the Allocation Types listed in the table above. However, the graph of this measure will represent the allocation types using their corresponding numeric equivalents – i.e., 1 to 3.</p> | Allocation Type | Numeric Value | Description | Static | 1 | Indicates that the machines in this catalog are either assigned by the administrator or assigned on first use to users. This assignment will change only when the administrator explicitly changes the assignments. | Permanent | 2 | Indicates that the machines in this catalog are permanently assigned to the user. | Random | 3 | Indicates that the machines in this catalog are picked in random and are temporarily assigned to the user. |
|-----------------|--|---|---|-----------------|---------------|-------------|--------|---|---|-----------|---|---|--------|---|--|
| Allocation Type | Numeric Value | Description | | | | | | | | | | | | | |
| Static | 1 | Indicates that the machines in this catalog are either assigned by the administrator or assigned on first use to users. This assignment will change only when the administrator explicitly changes the assignments. | | | | | | | | | | | | | |
| Permanent | 2 | Indicates that the machines in this catalog are permanently assigned to the user. | | | | | | | | | | | | | |
| Random | 3 | Indicates that the machines in this catalog are picked in random and are temporarily assigned to the user. | | | | | | | | | | | | | |

| | | | The detailed diagnosis of this measure if enabled, lists the catalog to which the machine belongs, the machine type, the number of sessions supported by the machine i.e, either Single session or Multi session, the location used for storing user data, the provisioning type and the scopes associated with the chosen catalog. | | | | | | |
|---------------|--|--------|--|---------------|---------------|-----|---|----|---|
| | <p>Are physical machines?:</p> <p>Indicates whether/not the machines in this catalog are power managed by the broker.</p> | | <p>This measure reports a value <i>Yes</i> if the machines are power managed by the broker and <i>No</i>, if otherwise.</p> <p>The table below provides the numeric values that correspond to the abovementioned values:</p> <table><tr><th>Measure Value</th><th>Numeric Value</th></tr><tr><td>Yes</td><td>1</td></tr><tr><td>No</td><td>0</td></tr></table> <p>Note:</p> <p>By default, this measure reports whether the machines are power managed by the broker or not. However, the graph of this measure will be represented using their corresponding numeric equivalents – i.e., <i>0</i> or <i>1</i>.</p> | Measure Value | Numeric Value | Yes | 1 | No | 0 |
| Measure Value | Numeric Value | | | | | | | | |
| Yes | 1 | | | | | | | | |
| No | 0 | | | | | | | | |
| | <p>Entitled machines used in delivery groups:</p> <p>Indicates the number of assigned machines (to users) in this catalog that are within delivery groups.</p> | Number | | | | | | | |
| | <p>Entitled machines available for delivery groups:</p> <p>Indicates the number of machines in this catalog that are available to users within delivery groups.</p> | Number | | | | | | | |
| | <p>Machines not entitled available for delivery groups:</p> <p>Indicates the number of machines within the delivery groups that are not yet assigned to users.</p> | Number | | | | | | | |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|---|--------|--|
| | Machines not entitled used in delivery groups: Indicates the number of unassigned machines in this catalog within the delivery groups but are still used in the pool. | Number | |
| | Machines used in delivery groups: Indicates the number of machines in this catalog that are within delivery groups. | Number | |
| | Total machines in catalog: Indicates the total number of machines in this catalog. | Number | |

The detailed diagnosis of the *Allocation type* measure if enabled, lists the catalog to which the machine belongs, the machine type, the number of sessions supported by the machine i.e, either Single session or Multi session, the location used for storing user data, the provisioning type and the scopes associated with the chosen catalog.

| Shows the Machine Catalog details | | | | | | | | |
|-----------------------------------|-------------|---------------------|-----------------|----------------|---------------------------|-------------|------------|--------|
| CATALOG | DESCRIPTION | MACHINE TYPE | SESSION SUPPORT | USER DATA | PROVISIONING TYPE | PVS ADDRESS | PVS DOMAIN | SCOPES |
| Sep 26, 2014 10:49:23 | | | | | | | | |
| Sales-Desktop-Catalog | XenDesktop | Desktop OS Machines | Single Session | Personal vDisk | Machine Creation Services | - | - | - |

Figure 1.11: The detailed diagnosis of the Allocation type measure

1.5 The Users Layer

Use the tests mapped to this layer to monitor user logons to the broker, assess user load, capture bottlenecks in the logon process, and detect user connection failures.




Figure 1.12: The tests mapped to the Users layer

1.5.1 Logon Performance Test

The process of a user logging into a desktop/server OS machine managed by a XenDesktop Broker is complex. First, the user's login credentials are authenticated. Then, the corresponding user profile is identified and loaded. Next, group policies are applied and logon scripts are processed to setup the user environment. Then, a HDX connection is established with the VM, subsequent to which, the VM starts and hands off keyboard and mouse control to the user. In the meantime, additional processing may take place for a user – say, applying system profiles, creating new printers for the user, and so on. A slowdown in any of these steps can significantly delay the logon process for a user and may adversely impact the logins for other users who may be trying to access desktops/applications at the same time. Hence, if a user complains that he/she is unable to access an application/desktop, administrators must be able to rapidly isolate exactly where the logon process is stalling and for which user.

The **Logon Performance** test tracks user connections to each delivery group configured in a site, measures the average time taken for users to access desktops/applications delivered by each group, isolates the group to which user logins are slow, and accurately pinpoints where the login process is bottlenecked. Detailed diagnostics provided by this test point to the precise user who is experiencing the slowness.

| | |
|---------------------------------|---|
| Purpose | Tracks user connections to each delivery group configured in a site, measures the average time taken for users to access desktops/applications delivered by each group, isolates the group to which user logins are slow, and accurately pinpoints where the login process is bottlenecked. |
| Target of the test | A broker in a XenDesktop broker site |
| Agent deploying the test | An internal agent |

| | | | |
|--------------------------------------|---|------------------|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 5. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 6. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs. 9. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes. 10. REPORT BY MACHINE TYPE – If you want the results of this test to be grouped by machine type then set this flag to Yes. In this case therefore, the machine types (desktop or server OS machines) will be the primary descriptors of this test; expanding them will reveal the secondary descriptors – i.e., the delivery groups containing machines of each type. If you want the results of this test to be indexed only by the names of delivery groups, then set this flag to No. 11. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is <i>1:1</i>. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying <i>none</i> against dd frequency. 12. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for each delivery group configured in the XenDesktop broker site | | |
| Measurements made by the test | Measurement | Measurement Unit | Interpretation |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|--|--------|--|
| | Average logon duration: Indicates the average time taken for users to login to desktops/applications offered by this delivery group. | Secs | <p>If this measure reports a high value consistently, it could indicate a slowdown in the logon process.</p> <p>You can use the detailed diagnosis of this measure to understand the logon experience of each user to the delivery group, identify that user who took the maximum time to login, and accurately isolate where he/she experienced slowness.</p> |
| | Logons: Indicates the number of users who recently logged into desktops/applications delivered by this delivery group. | Number | <p>This is a good indicator of the current user load on a delivery group.</p> |
| | Brokering duration: Indicates time taken to complete the process of brokering sessions to this deliver group. | Secs | <p>A high value indicates that brokering is taking a long time.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Time taken for starting VM, HDX connection duration, Authentication time, GPOs duration, Logon scripts duration, Profile load time, and Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | Time taken for starting VM: Indicates the time taken for starting the machines in this delivery group. | Secs | <p>A high value indicates that machines are taking too long to startup.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration, HDX connection duration, Authentication time, GPOs duration, Logon scripts duration, Profile load time, and Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |

| | | | |
|--|--|------|---|
| | HDX connection duration: Indicates the time taken to complete the steps required for setting up the HDX connection from the client to the machines in this delivery group. | Secs | <p>A high value indicates that HDX connections are taking time to be established.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | Authentication time: Indicates the time taken to authenticate remote sessions to the machines in this delivery group. | Secs | <p>A high value indicates authentication delays.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | GPOs duration: Indicates the time taken to apply group policy settings on the machines in this delivery group. | Secs | <p>A high value indicates that GPO application is taking time.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>Logon scripts duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |

| | | | |
|--|---|------|---|
| | <p>Logon scripts duration:</p> <p>Indicates the time taken for logon scripts to be executed on the machines in this delivery group.</p> | Secs | <p>A high value indicates that logon script execution is taking time.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | <p>Profile load time:</p> <p>Indicates the time taken by the logon process to load the profile of the users to this delivery group.</p> | Secs | <p>A high value indicates that profiles are taking too long to load.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | <p>Interactive session duration:</p> <p>Indicates the time taken by the logon process to handoff keyboard and mouse control to the users to this delivery group.</p> | Secs | <p>A high value indicates delays in handing off keyboard and mouse control to users.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, and <i>Profile load time</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |

1.5.2 Session Details Test

By tracking sessions to each delivery group configured on a site, administrators can not only assess the load on the delivery groups, but can also quickly identify problematic sessions – these could be sessions that are disconnected, sessions that are in an Unknown state, sessions that are reconnecting for some reason. This is what the **Session Details** test does! This test monitors the user sessions to each delivery group in a site, points administrators to overloaded groups, and also reports the status of sessions to each group, so that problem sessions can be isolated and their problems can be investigated.

| | |
|---------------------------------|---|
| Purpose | Monitors the user sessions to each delivery group in a site, points administrators to overloaded groups, and also reports the status of sessions to each group, so that problem sessions can be isolated and their problems can be investigated |
| Target of the test | A broker in a Citrix XenDesktop site |
| Agent deploying the test | An internal agent |

| | | | |
|--------------------------------------|--|--|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none">1. TEST PERIOD - How often should the test be executed2. HOST - The host for which the test is to be configured.3. PORT – The port number at which the specified HOST listens to. By default, this is 80.4. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics.5. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics.6. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes.7. CONFIRM PASSWORD – Confirm the PASSWORD by retping it here.8. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs.9. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes.10. REPORT BY MACHINE TYPE – If you want the results of this test to be grouped by machine type then set this flag to Yes. In this case therefore, the machine types (desktop or server OS machines) will be the primary descriptors of this test; expanding them will reveal the secondary descriptors – i.e., the delivery groups containing machines of each type. If you want the results of this test to be indexed only by the names of delivery groups, then set this flag to No.11. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is <i>1:1</i>. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying <i>none</i> against dd frequency.12. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:<ul style="list-style-type: none">• The eG manager license should allow the detailed diagnosis capability• Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| | Outputs of the test | One set of results for each delivery group configured in the XenDesktop broker ste | |
| Measurements made by the | Measurement | Measurement Unit | Interpretation |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|------|--|--------|--|
| test | Active sessions: Indicates the number of user sessions that are currently active on this delivery group. | Number | <p>This is a good indicator of the current session load on a delivery group. A consistent zero value however could indicate a connection issue.</p> <p>You can compare the value of this measure across delivery groups to know which delivery group is handling the maximum number of sessions currently.</p> <p>To determine the details of the currently active sessions, use the detailed diagnosis of this measure.</p> |
| | Connected sessions: Indicates the number of sessions that are currently connected to this delivery group. | Number | <p>Use the detailed diagnosis of this measure to view the details of connected sessions.</p> |
| | Disconnected sessions: Indicates the number of sessions that are currently disconnected from this delivery group. | Number | <p>If all the current sessions suddenly log out, it indicates a problem condition that requires investigation. The detailed diagnosis of this measure lists the sessions that were logged out.</p> |
| | Reconnecting sessions: Indicates the number of sessions that are reconnecting with this delivery group soon after a disconnect. | Number | |
| | Preparing sessions: Indicates the number of sessions to this delivery group that are currently in the <i>Preparing</i> state. | Number | |
| | Non-brokered sessions: Indicates the number of user sessions that are not brokered by the machines managed by this delivery group. | Number | |
| | Unknown sessions: Indicates the number of sessions to this delivery group that are currently in <i>Unknown</i> state. | Number | |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|---|--------|--|
| | Other sessions: Indicates the number of sessions to this delivery group that are currently in <i>Other</i> state. | Number | |
| | Pending sessions: Indicates the number of sessions to this delivery group that are currently pending. | Number | |

1.5.3 User Connection Failures

If a user complains that his/her connections to a desktop/application failed, then administrators must be able to quickly detect the failure and accurately zero-in on the reason for the failure, so that the problem can be fixed and the user connection can be restored. The **User Connection Failures** test helps administrators do just that! This test monitors the user connections to each delivery group in a site, promptly detects connection failures, and accurately indicates what caused the failure – is it due to a problem at the client side? is it owing to configuration errors? is it because of machine failures? is it due to the exhaustion of delivery group capacity? Or is it due to the absence of a license?

| | |
|---------------------------------|---|
| Purpose | Monitors the user connections to each delivery group in a site, promptly detects connection failures, and accurately indicates what caused the failure – is it due to a problem at the client side? is it owing to configuration errors? is it because of machine failures? is it due to the exhaustion of delivery group capacity? Or is it due to the absence of a license? |
| Target of the test | A Citrix XenDesktop Director |
| Agent deploying the test | An internal agent |

| | | | |
|--------------------------------------|--|------------------|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none">1. TEST PERIOD - How often should the test be executed2. HOST - The host for which the test is to be configured.3. PORT – The port number at which the specified HOST listens to. By default, this is 80.4. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics.5. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics.6. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes.7. CONFIRM PASSWORD – Confirm the PASSWORD by retping it here.8. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs.9. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes.10. REPORT BY MACHINE TYPE – If you want the results of this test to be grouped by machine type then set this flag to Yes. In this case therefore, the machine types (desktop or server OS machines) will be the primary descriptors of this test; expanding them will reveal the secondary descriptors – i.e., the delivery groups containing machines of each type. If you want the results of this test to be indexed only by the names of delivery groups, then set this flag to No.11. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is <i>1:1</i>. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying <i>none</i> against dd frequency.12. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:<ul style="list-style-type: none">• The eG manager license should allow the detailed diagnosis capability• Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| | Outputs of the test | | |
| Measurements made by the | One set of results for each delivery group configured in the XenDesktop broker ste | | |
| | Measurement | Measurement Unit | Interpretation |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|-------------|--|--------|---|
| test | Client connection failures: Indicates the number of connections to this delivery group that failed due to a problem at the client side. | Number | The value of this measure indicates the number of connection failures that occurred due to the inability of the client side to complete the session connection; for example, connection timed out, server was not reachable. |
| | Configuration errors: Indicates the number of connections to this delivery group that failed due to configuration errors. | Number | Connection failures can also occur when administrators change the configuration of the broker; for instance, a failure may occur when administrators put a delivery group or a machine in maintenance mode. |
| | Machine failures: Indicates the number of connections to this delivery group that failed due to machine failures. | Number | This refers to connections that failed because the machines that need to launch the sessions itself failed. For probable reasons, refer to the measures of the <i>Failed Machines</i> test. |
| | Unavailable capacity: Indicates the number of connections to this delivery group that failed because the configured capacity of the machines was consumed. | Number | This refers to failures that occurred due to the configured capacity of a particular delivery group having been completely consumed. For example, too many users logged into a Server Desktop OS delivery group or a user accessing a Pooled Random delivery group once all the machines in the delivery group are already assigned to other users. |
| | Unavailable licenses: Indicates the number of connections to this delivery group that failed because of the absence of a license. | Number | These are failures that occur due to the inability of the delivery controller to acquire a license from the license server to launch a session. |

1.5.4 User Connections Test

This test reports the number of users who recently connected with the machines/applications in each delivery group configured in the broker site. Sudden spikes in user connections to a delivery group can thus be identified.

| | |
|---------------------------------|--|
| Purpose | Reports the number of users who recently connected with the machines/applications in each delivery group configured in the broker site. Sudden spikes in user connections to a delivery group can thus be identified |
| Target of the test | A Citrix XenDesktop Director |
| Agent deploying the test | An internal agent |

| | | | |
|--------------------------------------|---|------------------|----------------|
| Configurable parameters for the test | <ol style="list-style-type: none">1. TEST PERIOD - How often should the test be executed2. HOST - The host for which the test is to be configured.3. PORT – The port number at which the specified HOST listens to. By default, this is 80.4. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics.5. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics.6. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes.7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here.8. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs.9. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes.10. REPORT BY MACHINE TYPE – If you want the results of this test to be grouped by machine type then set this flag to Yes. In this case therefore, the machine types (desktop or server OS machines) will be the primary descriptors of this test; expanding them will reveal the secondary descriptors – i.e., the delivery groups containing machines of each type. If you want the results of this test to be indexed only by the names of delivery groups, then set this flag to No.11. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is <i>1:1</i>. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying <i>none</i> against dd frequency.12. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:<ul style="list-style-type: none">• The eG manager license should allow the detailed diagnosis capability• Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| | Outputs of the test | | |
| Measurements made by the | One set of results for each delivery group configured in the XenDesktop broker ste | | |
| | Measurement | Measurement Unit | Interpretation |

| | | | |
|-------------|--|--------|--|
| test | New connections: Indicates the number of new connections to this delivery group since the last measurement period. | Number | Use the detailed diagnosis of this measure to view the details of each new connection. |
|-------------|--|--------|--|

1.5.5 User Logon Performance Test

The **Logon Performance** test monitors the user logon process from a delivery group perspective; in other words, it monitors user logins to the desktops/applications in a delivery group, measures the 'aggregate' duration of the login across all users to that group, and thus points to bottlenecks in the user logon process to that group.

The **User Logon Performance** test on the other hand, provides the user-perspective to logon monitoring. In other words, this test tracks each user who logs into a desktop or accesses an application via the XenDesktop broker, reports in real-time the logon experience of that user, and pinpoints where exactly that user's logon slowed down. When a user complains of delays in accessing his/her virtual desktop, this test will lead administrators straight to what is causing the delay. Detailed diagnostics provided by this test reveal which machines/applications a user is accessing and which delivery group these machines/applications belong to.

| | |
|---------------------------------|--|
| Purpose | Tracks each user who logs into a desktop or accesses an application via the XenDesktop broker, reports in real-time the logon experience of that user, and pinpoints where exactly that user's logon slowed down |
| Target of the test | A broker in a Citrix XenDesktop site |
| Agent deploying the test | An internal agent |

| | | | |
|--------------------------------------|---|------------------|--|
| Configurable parameters for the test | <ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured. 3. PORT – The port number at which the specified HOST listens to. By default, this is 80. 4. CONTROLLER IP ADDRESS – Specify the IP address of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 5. CONTROLLER PORT – Specify the port number of the delivery controller (i.e., broker) in the site with which the eG agent should communicate for collecting performance metrics. 6. USERNAME and PASSWORD – To connect to a delivery controller and pull out metrics from it, the eG agent requires Farm Administrator rights. In order to configure the eG agent with Farm Administrator privileges, specify the credentials of the Farm Administrator in the USERNAME and PASSWORD text boxes. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. FULLY QUALIFIED DOMAIN NAME – Here, specify the fully-qualified name of the domain to which the specified controller belongs. 9. SSL – Indicate whether/not the controller used for metrics collection is SSL-enabled. By default, this flag is set to Yes. 10. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is <i>1:1</i>. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying <i>none</i> against dd frequency. 11. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> • The eG manager license should allow the detailed diagnosis capability • Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. | | |
| Outputs of the test | One set of results for each user to the XenDesktop broker in the site | | |
| Measurements made by the test | Measurement | Measurement Unit | Interpretation |
| | Average logon duration: Indicates the average time taken for this user to login to desktops/access applications. | Secs | <p>If this measure reports a high value consistently, it could indicate a slowdown in the logon process.</p> <p>Compare the value of this measure across users to know which user's logon is taking the longest.</p> |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|---|--------|--|
| | Logons: Indicates the number of times this user has logged in since the last measurement period | Number | |
| | Brokering duration: Indicates time taken by this user to complete the process of brokering sessions. | Secs | <p>A high value indicates that brokering is taking a long time.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Time taken for starting VM, HDX connection duration, Authentication time, GPOs duration, Logon scripts duration, Profile load time, and Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | Time taken for starting VM: Indicates the time taken by the broker to start the machines accessed by this user. | Secs | <p>A high value indicates that machines are taking too long to startup.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration, HDX connection duration, Authentication time, GPOs duration, Logon scripts duration, Profile load time, and Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |

| | | | |
|--|--|------|---|
| | <p>HDX connection duration:</p> <p>Indicates the time taken by the broker to complete the steps required for setting up the HDX connection from this user to the machines accessed by the user.</p> | Secs | <p>A high value indicates that HDX connections are taking time to be established.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | <p>Authentication time:</p> <p>Indicates the time taken by the broker to authenticate this user's sessions.</p> | Secs | <p>A high value indicates authentication delays.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | <p>GPOs duration:</p> <p>Indicates the time taken to apply group policy settings on the machines accessed by this user.</p> | Secs | <p>A high value indicates that GPO application is taking time.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>Logon scripts duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |

MONITORING CITRIX XENDESKTOP BROKER SITE

| | | | |
|--|---|------|--|
| | <p>Logon scripts duration:</p> <p>Indicates the time taken for logon scripts to be executed on the machines accessed by this user.</p> | Secs | <p>A high value indicates that logon script execution is taking time.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Profile load time</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
| | <p>Profile load time:</p> <p>Indicates the time taken by the logon process to load the profile of this user.</p> | Secs | <p>A high value indicates that profiles are taking too long to load.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, and <i>Interactive session duration</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |

| | | | |
|--|---|------|---|
| | Interactive session duration: Indicates the time taken by the logon process to handoff keyboard and mouse control to this user. | Secs | <p>A high value indicates delays in handing off keyboard and mouse control to users.</p> <p>If the <i>Average logon duration</i> is very high, you may want to compare the value of this measure with that of the <i>Brokering duration</i>, <i>Time taken for starting VM</i>, <i>HDX connection duration</i>, <i>Authentication time</i>, <i>GPOs duration</i>, <i>Logon scripts duration</i>, and <i>Profile load time</i> measures to know where exactly the user logon process slowed down – is it during authentication? Is it during brokering? Is it when establishing the HDX connection? Is it when applying GPOs? Is it during logon scripts execution? Is it while loading user profiles? Is it when starting the VM? Or is it when handing over control to the user?</p> |
|--|---|------|---|

Conclusion

This document has described in detail the monitoring paradigm used and the measurement capabilities of the eG Enterprise suite of products with respect to the **Citrix XenDesktop Broker Site**. For details of how to administer and use the eG Enterprise suite of products, refer to the user manuals.

We will be adding new measurement capabilities into the future versions of the eG Enterprise suite. If you can identify new capabilities that you would like us to incorporate in the eG Enterprise suite of products, please contact support@eginnovations.com. We look forward to your support and cooperation. Any feedback regarding this manual or any other aspects of the eG Enterprise suite can be forwarded to feedback@eginnovations.com.